


5-8



DR. JOHN MANIOTES  
COMPUTER TECHNOLOGY DEPT.  
PURDUE UNIVERSITY  
CALUMET CAMPUS  
HAMMOND, IN 46323



Disclaimer

Although this program was tested by its author prior to submission, no warranty, express or implied, is made by the author, 1620 USERS Group, or IBM as to the accuracy and functioning of the program and related program material and no responsibility is assumed by the author, 1620 USERS Group, or IBM in connection therewith.

LOUISIANA STATE UNIVERSITY COMPUTER RESEARCH CENTER

Frequency Distributions  
Single Column and Double Column  
for I.B.M. 1620

Lew D. Harkins

Both programs allow the selection of from 1 - 5 card columns for control. The single column program allows the selection of from 1 to 80 card columns for frequency distributions, and the double column program allows the selection of from 1 to 40 pairs of columns for frequency distribution. Columns for control or frequencies may be taken from any place on the cards. The only restriction being that they shall not contain negative numbers. Unused columns on the data cards may be left blank or contain other information.

Parameter Cards

For the single column program one parameter card is required; for the double column program two parameter cards are required. These cards designate which columns on the data cards are to be used for control and which are to be used for frequency distributions.

Parameter Card - Single Column

Columns on data cards which are to be used for control shall have the corresponding columns on the parameter card punched,  $\bar{1}$  (minus 1).

Columns on data cards which are to be used for frequency distributions shall have the corresponding columns on the parameter card punched, 1 (one).

Columns on data cards which are not to be used shall have the corresponding columns on the parameter card left blank.

Parameter Cards - Double Column

All fields on both parameter cards are two digit fields and the high order position of each field must be flagged (x-punched).

### Parameter Cards 2 & 3

These two parameter cards specify the location of the variables on the input data cards. The terms "high order position" and "low order position" refer to column number on the data cards, without regard to card number, as the number of variables to be taken from each card is determined by parameter card 1.

Parameter Card 2	Parameter Card 3
Col. 1- 2 High order position of var. 1	Low order position of var. 1
Col. 3- 4 " " " " " 2	" " " " " 2
Col. 5- 6 " " " " " 3	" " " " " 3
.	.
.	.
.	.
Col. 75-76 High order position of var. 38	Low order position of var. 38
Col. 77-78 " " " " " 39	" " " " " 39
Col. 79-80 " " " " " 40	" " " " " 40

Note: Digit located at core storage position 401 determines course of action in case of characteristic overflow or underflow, (see 1620 SPS Subroutines), and may be changed after the program is loaded. Error codes are those of the SPS subroutines.

### Output

Output is under control of program Switch 1. With Switch #1 on, all output is punched on cards. With Switch #1 off, all output is by typewriter.

Switches #2, #3 and #4 are not used.

#### REMARKS:

Corrected as used here means corrected for the mean

$$\sum x - \frac{(\sum x)^2}{n} ; \sum xy - \frac{\sum x \sum y}{n}$$

The following calculations are used to arrive at the means, standard deviations, and correlation coefficients:

$$\bar{x} = \frac{\sum x}{n} ; s_x = \sqrt{\frac{\sum x^2 - \frac{(\sum x)^2}{n}}{n - 1}} ; r_{xy} = \frac{\sum xy - \frac{\sum x \sum y}{n}}{\sqrt{\left(\sum x^2 - \frac{(\sum x)^2}{n}\right) \left(\sum y^2 - \frac{(\sum y)^2}{n}\right)}}$$

Floating point notation used is as follows:

5018640000 = .1864, 5113700000 = 1.37, 4910000000 = .01, etc.

## Operating Instructions

### 1. Clear memory.

- a. Set all check switches to program.
- b. Depress Instant Stop (SCE), Reset, Insert
- c. Type: 26 00003 00009
- d. Depress Release, Start
- e. Allow 2 seconds, then depress Instant Stop (SCE)
- f. Set all check switches to stop.

### 2. Load Program.

- a. Depress Reset (on console)
- b. Place program deck in read hopper
- c. Depress Load Key on 1622 unit
- d. To process last card, depress Reader Start Key.

3. After program is loaded, the halt code (48) will appear in the operation register. Depress Reset, Start. (Reset Key must be depressed before the Start Key as the program interrogates the last card indicator.)

4. If typewriter output is to be given, all tab stops should be cleared from the typewriter, and only margins set.

5. Program switches should be set according to the program specifications.

The program is now ready to accept parameter cards and data cards.

The program is self-initializing between problems and need not be reloaded or restarted to process subsequent problems; however, the last data card in each set must be processed before the next set is placed in the read hopper (due to use of last card indicator).

SAMPLE DATA  
FOR SINGLE AND DOUBLE COLUMN FREQUENCY DISTRIBUTION

0578964123  
0897523461  
0976543215  
0036985214  
0852369147  
0852369147  
0963582741  
0963582741  
1963025874  
1963025847  
1789321456  
1024753689  
1986357420  
1234578962  
1987536420  
1598637423  
1896578965

CARD OUTPUT SINGLE COLUMN FREQUENCY  
WITH NO CONTROL  
FREQUENCIES AND PERCENTAGES

COL	0S	1S	2S	3S	4S	5S	6S	7S	8S	9S
01	0008	0009	0000	0000	0000	0000	0000	0000	0000	0000
01	047.1	052.9	000.0	000.0	000.0	000.0	000.0	000.0	000.0	000.0
02	0002	0000	0001	0000	0000	0002	0000	0001	0004	0007
02	011.8	000.0	005.9	000.0	000.0	011.8	000.0	005.9	023.5	041.2
03	0000	0000	0001	0002	0000	0002	0004	0002	0003	0003
03	000.0	000.0	005.9	011.8	000.0	011.8	023.5	011.8	017.6	017.6
04	0000	0000	0002	0004	0002	0000	0004	0002	0002	0001
04	000.0	000.0	011.8	023.5	011.8	000.0	023.5	011.8	011.8	005.9
05	0002	0000	0000	0004	0000	0007	0001	0001	0000	0002
05	011.8	000.0	000.0	023.5	000.0	041.2	005.9	005.9	000.0	011.8
06	0000	0000	0004	0002	0001	0002	0003	0002	0003	0000
06	000.0	000.0	023.5	011.8	005.9	011.8	017.6	011.8	017.6	000.0
07	0000	0001	0002	0003	0001	0003	0001	0002	0002	0002
07	000.0	005.9	011.8	017.6	005.9	017.6	005.9	011.8	011.8	011.8
08	0000	0003	0002	0000	0005	0000	0001	0002	0002	0002
08	000.0	017.6	011.8	000.0	029.4	000.0	005.9	011.8	011.8	011.8
09	0000	0002	0004	0000	0005	0001	0003	0001	0001	0000
09	000.0	011.8	023.5	000.0	029.4	005.9	017.6	005.9	005.9	000.0
10	0002	0003	0001	0002	0002	0002	0001	0003	0000	0001
10	011.8	017.6	005.9	011.8	011.8	011.8	005.9	017.6	000.0	005.9
TOTAL	0017									



CARD OUTPUT DOUBLE COLUMN FREQUENCY  
 WITH NO CONTROL  
 FREQUENCIES AND PERCENTAGES

COL 01-02

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT		
00	0001	05	0001	08	0003	09	0003	10	0001	12	0001	15	0001	17	0001	18	0001
00	005.9	05	005.9	08	017.6	09	017.6	10	005.9	12	005.9	15	005.9	17	005.9	18	005.9
19	0004																
19	023.5																

COL 03-04

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
24	0001	34	0001	36	0001	52	0002	63	0004	76	0001	78	0001	86	0001	87	0001
24	005.9	34	005.9	36	005.9	52	011.8	63	023.5	76	005.9	78	005.9	86	005.9	87	005.9
89	0001	96	0001	97	0001	98	0001										
89	005.9	96	005.9	97	005.9	98	005.9										

COL 05-06

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
02	0002	32	0001	35	0001	36	0002	52	0001	53	0001	54	0001	57	0002	58	0002
02	011.8	32	005.9	35	005.9	36	011.8	52	005.9	53	005.9	54	005.9	57	011.8	58	011.8
63	0001	75	0001	96	0001	98	0001										
63	005.9	75	005.9	96	005.9	98	005.9										

COL 07-08

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
14	0001	27	0002	32	0001	34	0001	36	0001	41	0001	52	0001	58	0002	64	0001
14	005.9	27	011.8	32	005.9	34	005.9	36	005.9	41	005.9	52	005.9	58	011.8	64	005.9
74	0002	89	0002	91	0002												
74	011.8	89	011.8	91	011.8												

COL 09-10

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
14	0001	15	0001	20	0002	23	0002	41	0002	47	0003	56	0001	61	0001	62	0001
14	005.9	15	005.9	20	011.8	23	011.8	41	011.8	47	017.6	56	005.9	61	005.9	62	005.9
65	0001	74	0001	89	0001												
65	005.9	74	005.9	89	005.9												

TOTAL 0017



CARD OUTPUT DOUBLE COLUMN FREQUENCY  
 WITH CONTROL  
 DATA SORTED ON COLUMN 1  
 FREQUENCIES AND PERCENTAGES

CONTROL GROUP COL 01=0

COL 03-04

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
36	0001	52	0002	63	0002	76	0001	78	0001	97	0001				
36	012.5	52	025.0	63	025.0	76	012.5	78	012.5	97	012.5				

COL 05-06

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
36	0002	52	0001	54	0001	58	0002	96	0001	98	0001				
36	025.0	52	012.5	54	012.5	58	025.0	96	012.5	98	012.5				

COL 07-08

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
27	0002	32	0001	34	0001	41	0001	52	0001	91	0002				
27	025.0	32	012.5	34	012.5	41	012.5	52	012.5	91	025.0				

COL 09-10

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
14	0001	15	0001	23	0001	41	0002	47	0002	61	0001				
14	012.5	15	012.5	23	012.5	41	025.0	47	025.0	61	012.5				

TOTAL 0008

CONTROL GROUP COL 01=1

COL 03-04

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
24	0001	34	0001	63	0002	86	0001	87	0001	89	0001	96	0001	98	0001
24	011.1	34	011.1	63	022.2	86	011.1	87	011.1	89	011.1	96	011.1	98	011.1

COL 05-06

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
02	0002	32	0001	35	0001	53	0001	57	0002	63	0001	75	0001		
02	022.2	32	011.1	35	011.1	53	011.1	57	022.2	63	011.1	75	011.1		

COL 07-08

RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT	RC	N/PCT
14	0001	36	0001	58	0002	64	0001	74	0002	89	0002				
14	011.1	36	011.1	58	022.2	64	011.1	74	022.2	89	022.2				

7

COL 09-10

RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT

20 0002 23 0001 47 0001 56 0001 62 0001 65 0001 74 0001 89 0001

20 022.2 23 011.1 47 011.1 56 011.1 62 011.1 65 011.1 74 011.1 89 011.1

TOTAL 0009

PARAMETER CARD FOR SINGLE COLUMN FREQUENCY WITH NO CONTROL

1111111111 PUNCHED IN COLUMNS 1 THRU 10

PARAMETER CARD FOR SINGLE COLUMN FREQUENCY WITH CONTROL

1111111111 PUNCHED IN COLUMNS 1 THRU 10

PARAMETER CARD FOR DOUBLE COLUMN FREQUENCY WITH NO CONTROL

0500000000000000 PARAMETER CARD NO. 1 PUNCHED IN COLUMNS 1 THRU 14

0103050709 PARAMETER CARD NO. 2 PUNCHED IN COLUMNS 1 THRU 10

PARAMETER CARD FOR DOUBLE COLUMN FREQUENCY WITH CONTROL

0401000000000000 PARAMETER CARD NO. 1 PUNCHED IN COLUMNS 1 THRU 14

03050709 PARAMETER CARD NO. 2 PUNCHED IN COLUMNS 1 THRU 8

Single Column  
Oreg. Dist ②

1		DORG	1000Z		01000				
2	INIT	RN	R1.500Z		01000	36	19801	00500	
3		TFM	**30.A-1Z		01012	16	01042	01755	FLAGS
4		AM	**18.12Z		01024	11	01042	00012	FLAGS
5		TFM	0.0.10Z		01036	16	00000	00000	FLAGS
6		CM	*-6.A+59Z		01048	14	01042	01815	FLAGS
7		BNI	*-36.1200Z		01060	47	01024	01200	
8		TFM	**59.R1-1.10Z		01072	16	01131	19800	FLAGS
9		TFM	IN2+6.A+11Z		01084	16	01186	01767	FLAGS
10		TFM	IN2+42.BCZ		01096	16	01222	03511	FLAGS
11		AM	**23.1.10Z		01108	11	01131	00001	FLAGS
12	INI	BD	**48.R1Z		01120	43	01168	19801	
13		CM	*-1.80.10Z		01132	14	01131	00080	FLAGS
14		BI	IN3.1200Z		01144	46	01252	01200	
15		B	*-48Z		01156	49	01108	00000	
16		BNF	**48.IN1+11.11Z		01168	44	01216	01131	FLAGS IND ADD
17	IN2	TF	A+11.IN1+11Z		01180	26	01767	01131	
18		AM	*-6.12Z		01192	11	01186	00012	FLAGS
19		B	IN1+12Z		01204	49	01132	00000	
20		TF	BC.IN1+11Z		01216	26	03511	01131	
21		AM	*-6.2Z		01228	11	01222	00002	FLAGS
22		B	IN1+12Z		01240	49	01132	00000	
23	IN3	CM	A+11.0.10Z		01252	14	01767	00000	FLAGS
24		BI	NC.1200Z		01264	46	01684	01200	
25		TF	HEAD1+116.BIGB+64Z		01276	26	03453	03241	
26		TFM	**90.HEAD1+64Z		01288	16	01378	03401	FLAGS
27		TFM	**30.HEAD1+40Z		01300	16	01330	03377	FLAGS
28		TFM	**23.A+11Z		01312	16	01335	01767	FLAGS
29		TNF	0.0Z		01324	73	00000	00000	
30		AM	*-1.12Z		01336	11	01335	00012	FLAGS
31		CM	*-13.0.610Z		01348	14	01335	00000	FLAGS IND ADD
32		BI	**60.1200Z		01360	46	01420	01200	
33		TF	0.HEAD1+46Z		01372	26	00000	03383	
34		AM	*-54.18Z		01384	11	01330	00018	FLAGS
35		AM	*-18.18Z		01396	11	01378	00018	FLAGS
36		B	*-84Z		01408	49	01324	00000	
37	READ1	RN	R2.500Z		01420	36	19901	00500	
38		BTM	A.0.10Z		01432	17	01756	00000	FLAGS
39		TF	ID2.ID1Z		01444	26	03509	03504	
40		WA	BIGB.400Z		01456	39	03177	00400	
41		TD	HEAD1+44.ID1-4Z		01468	25	03381	03500	
42		TD	HEAD1+62.ID1-3Z		01480	25	03399	03501	
43		TD	HEAD1+80.ID1-2Z		01492	25	03417	03502	
44		TD	HEAD1+98.ID1-1Z		01504	25	03435	03503	
45		TD	HEAD1+116.ID1Z		01516	25	03453	03504	
46		CF	HEAD1+44Z		01528	33	03381	00000	
47		WA	HEAD1.400Z		01540	39	03337	00400	
48		WA	BIGB.400Z		01552	39	03177	00400	
49		BTM	C.800.9Z		01564	17	01840	00800	FLAGS
50		B	READ2+48Z		01576	49	01636	00000	
51	READ2	RN	R2.500Z		01588	36	19901	00500	
52		BTM	A.0.10Z		01600	17	01756	00000	FLAGS
53		C	ID1.ID2Z		01612	24	03504	03509	
54		BNI	D.1200Z		01624	47	02092	01200	
55		BTM	B.SZ		01636	17	01924	03673	FLAGS

56	BNI	READ2,900Z	01648	47	01588	00900	
57	SF	DZ	01660	32	02092	00000	
58	B	OZ	01672	49	02092	00000	
59 NC	BTM	C,800,9Z	01684	17	01840	00800	FLAGS
60	RN	R2,500Z	01696	36	19901	00500	
61	BTM	B,5Z	01708	17	01924	03673	FLAGS
62	BNI	*-24,900Z	01720	47	01696	00900	
63	SF	DZ	01732	32	02092	00000	
64	B	OZ	01744	49	02092	00000	
65 A	TD	ID1-4,R2Z	01756	25	03500	19901	
66	TD	ID1-3,R2Z	01768	25	03501	19901	
67	TD	ID1-2,R2Z	01780	25	03502	19901	
68	TD	ID1-1,R2Z	01792	25	03503	19901	
69	TD	ID1,R2Z	01804	25	03504	19901	
70	SF	ID1-4,0,10Z	01816	32	03500	00000	FLAGS
71	BB	Z	01828	42	00000	00000	
72 C	TFM	**+30,S-4Z	01840	16	01870	03669	FLAGS
73	AM	**+18,4Z	01852	11	01870	00004	FLAGS
74	TFM	0,0,8Z	01864	16	00000	00000	FLAGS
75	SM	C-1,1,9Z	01876	12	01839	00001	FLAGS
76	BNI	*-36,1200Z	01888	47	01852	01200	
77	TFM	N,0,8Z	01900	16	03499	00000	FLAGS
78	BB	Z	01912	42	00000	00000	
79 B	TFM	**+35,8C-2Z	01924	16	01959	03509	FLAGS
80	AM	**+23,2Z	01936	11	01959	00002	FLAGS
81	CM	IN2+42,0Z	01948	14	01222	00000	FLAGS
82	BI	**+108,1200Z	01960	45	02068	01200	
83	TF	**+23,*-13,11Z	01972	26	01995	01959	FLAGS IND ADD
84	TD	**+21,R2Z	01984	25	02005	19901	
85	MM	**+9,4,810Z	01996	13	02005	00004	FLAGS
86	TF	**+30,B-1Z	02008	26	02038	01923	
87	A	**+18,99Z	02020	21	02038	00099	
88	AM	0,1,8Z	02032	11	00000	00001	FLAGS
89	AM	B-1,40Z	02044	11	01923	00004	FLAGS
90	B	*-120Z	02056	49	01936	00000	
91	AM	N,1,8Z	02068	11	03499	00001	FLAGS
92	BB	Z	02080	42	00000	00000	
93 D	WA	P3,400Z	02092	39	02857	00400	
94	WA	BIGB,400Z	02104	39	03177	00400	
95	TFM	D1+11,8C-2Z	02116	16	02187	03509	FLAGS
96	TFM	D2+11,S-4Z	02128	16	02271	03669	FLAGS
97	TFM	D2+6,P1+2Z	02140	16	02266	02539	FLAGS
98	TFM	D3+54,P2+2Z	02152	16	02338	02699	FLAGS
99	AM	D1+11,2Z	02164	11	02187	00002	FLAGS
100 D1	CM	IN2+42,0Z	02176	14	01222	00000	FLAGS
101	BI	D4,1200Z	02188	46	02464	01200	
102	TNF	P1+2,D1+11,11Z	02200	73	02539	02187	FLAGS IND ADD
103	TNF	P2+2,D1+11,11Z	02212	73	02699	02187	FLAGS IND ADD
104	AM	D2+11,4Z	02224	11	02271	00004	FLAGS
105	BNI	D3,100Z	02236	47	02284	00100	
106	AM	D2+6,14Z	02248	11	02266	00014	FLAGS
107 D2	TNF	P1,0Z	02260	73	02537	00000	
108	BNI	WP1,200Z	02272	47	02368	00200	
109 D3	AM	**+54,10Z	02284	11	02338	00010	FLAGS
110	LD	95,D2+11,11Z	02296	28	00095	02271	FLAGS IND ADD

111	D	95.NZ												02308 29 00095 03499	
112	AM	95.5Z												02320 11 00095 00005	FLAGS
113	TNF	0.93Z												02332 73 00000 00093	
114	AM	*-6.4Z												02344 11 02338 00004	FLAGS
115	TD	*-18.94.6Z												02356 25 02338 00094	FLAGS IND ADD
116 WP1	CM	D2+6.P1+142Z												02368 14 02266 02679	FLAGS
117	BNI	*+36.1200Z												02380 47 02416 01200	
118	WA	P1.400Z												02392 39 02537 00400	
119	BNI	D1-36.200Z												02404 47 02140 00200	
120	CM	D3+54.P2+142Z												02416 14 02338 02839	FLAGS
121	BNI	D2-36.1200Z												02428 47 02224 01200	
122	WA	P2.400Z												02440 39 02697 00400	
123	B	D1-36Z												02452 49 02140 00000	
124 D4	TNF	P4+20.NZ												02464 73 03037 03499	
125	WA	P4.400Z												02476 32 03017 00400	
126	WA	BIGB.400Z												02488 39 03177 00400	
127	BNF	READ1+24.DZ												02500 44 01444 02092	
128	CF	DZ												02512 33 02092 00000	
129	B	INITZ												02524 49 01000 00000	
130 P1	DAC	50.00 0000												02537 00050	Z
131	DAC	30.0 0000 00												02637 00030	Z
132 P2	DAC	50.00 000.0 000.0 000.0 000.0 000.0 000.0 000.0 000.0 000.0												02697 00050	Z
133	DAC	30.0 000.0 000.0 000.0												02797 00030	Z
134 P3	DAC	50.COL 0S 1S 2S 3S 4S 5S 6Z												02857 00050	
135	DAC	30.S 7S 8S 9S												02957 00030	Z
136 P4	DAC	50.TOTAL												03017 00050	Z
137	DAC	30.												03117 00030	Z
138 BIGB	DAC	50.												03177 00050	Z
139	DAC	30.												03277 00030	Z
140 HEAD1	DAC	50.CONTROL GROUP												03337 00050	Z
141	DAC	30.												03437 00030	Z
142	DAC	9.COL 00=0 .HEAD1+30Z												03367 00009	
143 N	DS	4Z												03499 00004	
144 ID1	DS	5Z												03504 00005	
145 ID2	DS	5Z												03509 00005	
146 BC	DSB	2.80Z												03511 00002 00080	
147 S	DSB	4.800Z												03673 00004 00800	
148 R1	DAS	41.19801Z												19801 00041	
149 R2	DAS	41.19901Z												19901 00041	
150	DC	2.00.19900Z												19900 00002	
151	DEND	INITZ												01000	

151

Double Column  
Prog. Dist.

1		DORG	402Z		00402			
2	INIT	RN	R1,500Z		00402	36	03701	00500
3		RN	R2,500Z		00414	36	03801	00500
4		CM	R1+3,0,10Z		00426	14	03704	00000
5		BI	NC,1200Z		00438	46	00918	01200
6		TF	A+11,R1+3Z		00450	26	01001	03704
7		TF	A+23,R1+5Z		00462	26	01013	03706
8		TF	A+35,R1+7Z		00474	26	01025	03708
9		TF	A+47,R1+9Z		00486	26	01037	03710
10		TF	A+59,R1+11Z		00498	26	01049	03712
11		TF	HEAD1+116,BIGB+64Z		00510	26	03217	02195
12		TFM	**90,HEAD1+64Z		00522	16	00612	03165
13		TFM	**30,HEAD1+40Z		00534	16	00564	03141
14		TFM	**23,R1+3Z		00546	16	00569	03704
15		TNF	0,0Z		00558	73	00000	00000
16		AM	*-1,2Z		00570	11	00569	00002
17		CM	*-13,0,610Z		00582	14	00569	00000
18		BT	**60,1200Z		00594	46	00654	01200
19		TF	0,HEAD1+46Z		00606	26	00000	03147
20		AM	*-54,18Z		00618	11	00564	00018
21		AM	*-18,18Z		00630	11	00612	00018
22		B	*-84Z		00642	49	00558	00000
23	READ1	RN	R3,500Z		00654	36	03901	00500
24		BTM	A,0,10Z		00666	17	00990	00000
25		TF	ID2,101Z		00678	26	03099	03094
26		WA	BIGB,400Z		00690	39	02131	00400
27		TD	HEAD1+44,101-4Z		00702	25	03145	03090
28		TD	HEAD1+62,101-3Z		00714	25	03163	03091
29		TD	HEAD1+80,101-2Z		00726	25	03181	03092
30		TD	HEAD1+98,101-1Z		00738	25	03199	03093
31		TD	HEAD1+116,101Z		00750	25	03217	03094
32		CF	HEAD1+44Z		00762	33	03145	00000
33		WA	HEAD1,400Z		00774	39	03101	00400
34		WA	BIGB,400Z		00786	39	02131	00400
35		BTM	C,0,8Z		00798	17	01074	00000
36		B	READ2+48Z		00810	49	00870	00000
37	READ2	RN	R3,500Z		00822	36	03901	00500
38		BTM	A,0,10Z		00834	17	00990	00000
39		C	ID1,102Z		00846	24	03094	03099
40		BNI	D,1200Z		00858	47	01350	01200
41		BTM	B,SZ		00870	17	01170	04003
42		BNI	READ2,900Z		00882	47	00822	00900
43		SF	DZ		00894	32	01350	00000
44		B	DZ		00906	49	01350	00000
45	NC	BTM	C,0,8Z		00918	17	01074	00000
46		RN	R3,500Z		00930	36	03901	00500
47		BTM	B,SZ		00942	17	01170	04003
48		BNI	*-24,900Z		00954	47	00930	00900
49		SF	DZ		00966	32	01350	00000
50		B	DZ		00978	49	01350	00000
51	A	TD	ID1-4,R3Z		00990	25	03090	03901
52		TD	ID1-3,R3Z		01002	25	03091	03901
53		TD	ID1-2,R3Z		01014	25	03092	03901
54		TD	ID1-1,R3Z		01026	25	03093	03901
55		TD	ID1,R3Z		01038	25	03094	03901

56	SF	1D1-4Z	01050	32	03090	00000	
57	BB	Z	01062	42	00000	00000	
58 C	TF	*-3,R1+1Z	01074	26	01071	03702	
59	TFM	**+30,S-4Z	01086	16	01116	03999	FLAGS
60	AM	**+18,4Z	01098	11	01116	00004	FLAGS
61	TFM	0,0,8Z	01110	16	00000	00000	FLAGS
62	SM	C-1,1,8Z	01122	12	01073	00001	FLAGS
63	BNI	*-36,1200Z	01134	47	01098	01200	
64	TFM	N,0,8Z	01146	16	03263	00000	FLAGS
65	BB	Z	01158	42	00000	00000	
66 B	TF	**+141,R1+1Z	01170	26	01311	03702	
67	TFM	**+35,R2-1,10Z	01182	16	01217	03800	FLAGS
68	AM	**+23,2,10Z	01194	11	01217	00002	FLAGS
69	TF	**+18,R2+1Z	01206	26	01224	03802	
70	SF	R3Z	01218	32	03901	00000	
71	AM	*-6,1,10Z	01230	11	01224	00001	FLAGS
72	MM	*-18,4,610Z	01242	13	01224	00004	FLAGS IND ADD
73	TF	**+30,B-1Z	01254	26	01284	01169	
74	A	**+18,99Z	01266	21	01284	00099	
75	AM	S,1,8Z	01278	11	04003	00001	FLAGS
76	AM	B-1,400Z	01290	11	01169	00400	FLAGS
77	SM	**+9,1,10Z	01302	12	01311	00001	FLAGS
78	BNI	B+24,1200Z	01314	47	01194	01200	
79	AM	N,1,8Z	01326	11	03263	00001	FLAGS
80	BB	Z	01338	42	00000	00000	
81 D	TFM	D1+11,R2-1Z	01350	16	01469	03800	FLAGS
82	TFM	D2+6,S-4Z	01362	16	01560	03999	FLAGS
83	TF	D5+69,R1+1Z	01374	26	01947	03702	
84	TFM	D2+78,P1-4Z	01386	16	01632	02287	FLAGS
85	TFM	D3+42,P2-4Z	01398	16	01716	02447	FLAGS
86	TF	P1+158,B1GB+158Z	01410	26	02449	02289	
87	TF	P2+158,B1GB+158Z	01422	26	02609	02289	
88	AM	D1+11,2Z	01434	11	01469	00002	FLAGS
89	TFM	D-1,0,10Z	01446	16	01349	00000	FLAGS
90 D1	TF	**+33,0Z	01458	26	01491	00000	
91	TNF	P3+10,**+21Z	01470	73	02621	01491	
92	AM	**+9,1,10Z	01482	11	01491	00001	FLAGS
93	TNF	P3+16,**-3Z	01494	73	02627	01491	
94	WA	P3,400Z	01506	39	02611	00400	
95	WA	P5,400Z	01518	39	02931	00400	
96	WA	B1GB,400Z	01530	39	02131	00400	
97	AM	D2+6,4Z	01542	11	01560	00004	FLAGS
98 D2	CM	0,0,8Z	01554	14	00000	00000	FLAGS
99	BI	D4,1200Z	01566	46	01830	01200	
100	BNI	D3,100Z	01578	47	01674	00100	
101	CM	**+42,P1+158Z	01590	14	01632	02449	FLAGS
102	BI	WP1,1200Z	01602	46	02034	01200	
103	AM	**+18,6Z	01614	11	01632	00006	FLAGS
104	TNF	0,D-1Z	01626	73	00000	01349	
105	AM	*-6,12Z	01638	11	01632	00012	FLAGS
106	TNF	*-18,D2+6,611Z	01650	73	01632	01560	FLAGS IND ADD
107	BNI	D4,200Z	01662	47	01830	00200	
108 D3	CM	**+42,P2+158Z	01674	14	01716	02609	FLAGS
109	BI	WP2,1200Z	01686	46	02082	01200	
110	AM	**+18,6Z	01698	11	01716	00006	FLAGS

111	TNF	0,D-1Z			01710	73	00000	01349		
112	LD	95,D2+6,11Z			01722	28	00095	01560	FLAGS	IND ADD
113	D	95,NZ			01734	29	00095	03263		
114	AM	95,5Z			01746	11	00095	00005	FLAGS	
115	AM	D3+42,8Z			01758	11	01716	00008	FLAGS	
116	TNF	D3+42,93,6Z			01770	73	01716	00093	FLAGS	IND ADD
117	AM	D3+42,3Z			01782	11	01716	00003	FLAGS	
118	TFM	D3+42,37,69Z			01794	16	01716	00037	FLAGS	IND ADD
119	AM	D3+42,1Z			01806	11	01716	00001	FLAGS	
120	TD	D3+42,94,6Z			01818	25	01716	00094	FLAGS	IND ADD
121 D4	CM	D-1,99,10Z			01830	14	01349	00099	FLAGS	
122	BI	D5,1200Z			01842	46	01878	01200		
123	AM	D-1,1,10Z			01854	11	01349	00001	FLAGS	
124	B	D2-12Z			01866	49	01542	00000		
125 D5	BNI	*+24,100Z			01878	47	01902	00100		
126	WA	P1,400Z			01890	39	02291	00400		
127	BNI	*+24,200Z			01902	47	01926	00200		
128	WA	P2,400Z			01914	39	02451	00400		
129	WA	BIGB,400Z			01926	39	02131	00400		
130	SM	*+9,1,10Z			01938	12	01947	00001	FLAGS	
131	BNI	D+36,1200Z			01950	47	01386	01200		
132	TNF	P4+20,NZ			01962	73	02791	03263		
133	WA	P4,400Z			01974	39	02771	00400		
134	WA	BIGB,400Z			01986	39	02131	00400		
135	BNF	READ1+24,DZ			01998	44	00678	01350		
136	CF	DZ			02010	33	01350	00000		
137	B	INITZ			02022	49	00402	00000		
138 WP1	WA	P1,400Z			02034	39	02291	00400		
139	TF	P1+158,BIGB+158Z			02046	26	02449	02289		
140	TFM	D2+78,P1+2Z			02058	16	01632	02293	FLAGS	
141	B	D2+72Z			02070	49	01626	00000		
142 WP2	WA	P2,400Z			02082	39	02451	00400		
143	TF	P2+158,BIGB+158Z			02094	26	02609	02289		
144	TFM	D3+42,P2+2Z			02106	16	01716	02453	FLAGS	
145	B	D3+36Z			02118	49	01710	00000		
146 BIGB	DAC	50,		Z	02131		00050			
147	DAC	30,		Z	02231		00030			
148 P1	DAC	50,		Z	02291		00050			
149	DAC	30,		Z	02391		00030			
150 P2	DAC	50,		Z	02451		00050			
151	DAC	30,		Z	02551		00030			
152 P3	DAC	50,COL 00-00		Z	02611		00050			
153	DAC	30,		Z	02711		00030			
154 P4	DAC	50,TOTAL 0000		Z	02771		00050			
155	DAC	30,		Z	02871		00030			
156 P5	DAC	50,RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/PCT RC N/Z			02931		00050			
157	DAC	30,PCT RC N/PCT RC N/PCT RC N/PCTZ			03031		00030			
158 ID1	DS	5Z			03094		00005			
159 ID2	DS	5Z			03099		00005			
160 HEAD1	DAC	50,CONTROL GROUP		Z	03101		00050			
161	DAC	30,		Z	03201		00030			
162	DAC	9,COL 00=0 ,HEAD1+30Z			03131		00009			
163 N	DS	4Z			03263		00004			
164 R1	DAS	41,3701Z			03701		00041			
165 R2	DAS	41,3801Z			03801		00041			



166 R3	DAS	41,3901Z	03901	00041
167	DC	2,00,3900Z	03900	00002
168	DC	2,00,3800Z	03800	00002
169 S	DSB	4,4000,4003Z	04003	00004 04000
170	DEND	INITZ	00402	

170