

OS/3 IMS 90 Terminal User Commands Summary

Standard Terminal Commands

ZZCNC	Cancel current transaction
ZZHLD	Temporarily suspend output
ZZMCH <i>tid</i>	Change master terminal
ZZNRM	Resume normal mode
ZZRDY	Release hold
ZZRSD	Resend last message
ZZTMD	Initiate test mode

UNIQUE Terminology

display-content-specification

May be record name, subrecord name, item names, or ALL

id

Actual record key

item

Defined record element (field)

password

Defined file password or file name

selection criteria

May use EQ, NE, GT, GE, LT, or LE. NOT, AND, and/or OR allowed for BOOLEAN expressions.

statistical-function

AVG	Average item from all selected
COUNT	Display number of occurrences of record
MAX	Find and display maximum of item from record selected and show identifier (key)
MIN	As in MAX, but display minimum and id
TOTAL	Total all items specified

Teletypewriter Controls

CTL/G*	Accept unsolicited output
CTL/H	Delete character
CTL/X*	Delete message

*Must be followed by CTL/C or ETX

Master Terminal Commands

ZZALT { *tid,alt-tid* }
 { *tid* }
Send switched messages to alternate terminal, or restore alternated terminal

ZZBTH { *mod-name,file-name* }
 { **[,ALL]* }
 { **CANCEL** }
 { **PAUSE** }
 { **RESUME** }
Initiate and control batch processing in online mode

ZZCLS *file-name*
Close specified file

ZZDWN *tid* Disable specified terminal

ZZHLT Emergency shutdown (halt)

ZZOPN *file-name*
Open specified file

ZZPCH *program-name*
Change action program

ZZSHD Initiate controlled shutdown

ZZTCT *tid* Display status of specified terminal

ZZTST *tid* Test specified terminal

ZZUP *tid* Enable specified terminal

Global Network Terminal Commands

\$\$\$SON *terminal-idprogram-name*
Initiate dynamic session with IMS 90. No space permitted between terminal-id and program-name.

\$\$\$SOFF Terminate dynamic session with IMS 90.

UNIQUE Commands

ADD <i>id-1</i> [: <i>id-2</i>]...	Add record. Headers and format are displayed to fill in the blanks.
(Display format)	
ADD <i>id</i> [:]...[<i>item-1</i> =] <i>value</i> [:]...[<i>item-2</i> =] <i>value</i> ...	Item values are entered with command. A dialog will occur to add each 'MUST ADD' item omitted.
(Hard copy format)	
CANCEL *	Cancel previous update command.
CHANGE <i>id-1</i> [: <i>id-2</i>]...	Change specific records; id is key.
(Display format)	
CHANGE <i>id</i> [:]...[<i>item-1</i> =] <i>value</i> [:]...[<i>item-2</i> =] <i>value</i> ...	Change specific record by replacing values in item names.
(Hard copy format)	
CLOSE	Close the currently opened file for that terminal.
DELETE <i>id-1</i> [: <i>id-2</i>]...	Delete specific records.
DISPLAY <i>id-1</i> [: <i>id-2</i>]...	Display specific records.
{ DETAIL } [[<i>display-content-specification</i>][IF <i>selection-criteria</i>];]...	LIST command lists records or selected parts of records on terminal.
{ LIST }	
[FOR <i>id-1</i>] { { AFTER } <i>id-2</i> }	DETAIL allows interrupting a LIST for more information on one or more records.
{ FROM }	
[<i>statistical-function</i> [<i>item-1</i> , <i>item-2</i>]...]]...	
MORE { { DETAIL } }	Display next screenful of information; if only MORE is keyed in, response is to last DETAIL or LIST command.
{ LIST }	
NEXT	Select next id (record) for DISPLAY, DELETE, ADD, or CHANGE.
OK *	Authorize completion of DELETE, ADD, or CHANGE.
OPEN <i>password</i>	Open file with password or file name.
SHOW	Display format of defined file being accessed.

*Press carriage return key and line feed key before keying in OK or CANCEL on hard copy device.

IMS 90 Transaction Codes

DLMSG [Δ <i>terminal-id</i>]	Display last output message prior to actions that may be or have been rolled back.
DLOAD <i>prog-name</i> [, <i>aux-dev-no</i> , <i>prog-id</i>]	Downline load user program to a UTS 400 terminal or to a UTS 400 local storage device.
SWTCH { ALL } ; Δ <i>message-text</i>	Send message to all configured terminals, the master terminal, or specified terminals.
{ MAST }	
{ <i>tid-1</i> [, <i>tid-2</i>] .. }	
ZSTAT ALL [, CONT] [, AUX <i>n</i>]	Display prompting menu or display terminal status in noncontinuous or continuous output modes on the master terminal or auxiliary device.
ZSTAT HELP	Display the ZSTAT parameters and examples of their use.