

Systems

IBM Virtual Machine Facility/370: CMS Command and Macro Reference

Release 3 PLC 1

This publication provides users of the Conversational Monitor System (CMS) component of the IBM Virtual Machine Facility/370 with detailed reference information concerning command syntax and usage notes for:

- CMS commands
- EDIT subcommands
- DEBUG subcommands
- EXEC control statements, special variables, and built-in functions
- CMS assembler language macro instructions

Prerequisite Publications

IBM Virtual Machine Facility/370:

Terminal User's Guide, Order No. GC20-1810

CMS User's Guide, Order No. GC20-1819

The IBM logo is displayed in its classic, bold, outlined font.

First Edition (March 1976)

This edition, GC20-1818-0, corresponds to Release 3 PLC 1 (Program Level Change) of the IBM Virtual Machine Facility/370, and to all subsequent releases unless otherwise indicated in new editions or Technicals Newsletters (TNLS).

Changes are periodically made to the specifications herein; before using this publication in connection with the operation of IBM systems, consult the latest IBM System/370 Bibliography, Order No. GC20-0001, for the editions that are applicable and current.

Reference information moved to this publication from other VM/370 publications does not have update bars. However, technical changes and additions to text and illustrations are indicated by a vertical bar to the left of the change.

Requests for copies of IBM publications should be made to your IBM representative or to the IBM branch office serving your locality.

A form for readers' comments is provided at the back of this publication. If the form has been removed, comments may be addressed to IBM Corporation, VM/370 Publications, 24 New England Executive Park, Burlington, Massachusetts 01803. Comments become the property of IBM.

Preface

Use this publication as a reference manual; it contains all of the command formats, syntax rules, and operand and option descriptions for CMS commands, subcommands, and macro instructions for general users.

The IBM Virtual Machine Facility/370: CMS User's Guide, Order No. GC20-1819, contains tutorial information and functional descriptions of CMS commands, as well as information on using the editor, EXEC, and debugging facilities of CMS. You should be familiar with the contents of the user's guide before you attempt to use this reference manual. For most of the CMS commands described in this publication, you may find additional useful notes in the user's guide.

This publication has six sections:

"Section 1. Introduction and General Concepts" describes the components of the VM/370 system and tells you how to enter CMS commands. It lists the notational conventions used in this manual, so that you can interpret the command format descriptions in Section 2. Section 1 also contains information about the CMS command search order and a summary of all the CMS commands available under VM/370, including those not for general users.

"Section 2. CMS Commands" contains complete format descriptions, and operand and option lists, for the CMS commands available to general users. Each command description contains usage notes, and lists responses and error messages (with associated return codes) produced by the command.

"Section 3. EDIT Subcommands and Macros" describes the subcommands and macros available in the environment of the CMS Editor, which you can invoke with the EDIT command. Each subcommand description contains usage notes and summarizes the types of responses you might receive. Where applicable, additional information is provided for users of display terminals.

"Section 4. DEBUG Subcommands" describes the subcommands available in the debug environment of CMS. Each subcommand description contains usage notes and, where applicable, lists the responses to the subcommand.

"Section 5. EXEC Control Statements" describes the control statements, special variables, and built-in functions you can use when you create EXEC procedures to execute in CMS. The control statement descriptions contain usage notes, where applicable.

"Section 6. CMS Macro Instructions" lists the formats and operands of the CMS assembler language macro instructions you can use when you write programs to execute in CMS.

This publication also has three appendixes:

"Appendix A: Reserved Filetype Defaults" lists the filetypes that are recognized by the CMS Editor and indicates the default settings that the editor supplies for logical tabs, truncation, verification, logical record length, and so on.

"Appendix B: DOS/VS Access Method Services and VSAM Functions Not Supported in CMS" lists the restrictions on the use of Access Method Services and VSAM in the CMS/DOS environment of CMS.

"Appendix C: OS/VS Access Method Services and VSAM Functions Not Supported in CMS" lists the restrictions for OS programmers using Access Method Services and VSAM in CMS.

Terminology

Some of the following terms are used, for convenience, throughout this publication:

- The term "CMS/DOS" refers to the functions of CMS that become available when you issue the command

set dos on

CMS/DOS is a part of the normal CMS system, and is not a separate system. Users who do not use CMS/DOS are sometimes referred to as OS users, since they use the OS simulation functions of CMS.

- The term "CMS files" refers exclusively to files that are in the 800-byte block format used by CMS file system commands. VSAM and OS data sets and DOS files are

not compatible with the CMS file format, and cannot be manipulated using CMS file system commands.

The terms "disk" and "virtual disk" are used interchangeably to indicate disks that are in your CMS virtual machine configuration. Where necessary, a distinction is made between CMS-formatted disks and disks in OS- or DCS format.

- "3270" refers to both the IBM 3275 Display Station, Model 2 and the IBM 3277 Display Station, Model 2.
- "3330" refers to the IBM 3330 Disk Storage Models 1, 2, and 11, the IBM 3333 Disk Storage and Control Models 1 and 11, and the IBM 3350 Direct Access Storage in 3330 compatibility mode.
- "2305" refers to the IBM 2305 Fixed Head Storage, Models 1 and 2.
- "3340" refers to the IBM 3340 Direct Access Storage Facility and the IBM 3344 Direct Access Storage.
- "3350" refers to the IBM 3350 Direct Access Storage device when used in native mode.
- Any information pertaining to the IBM 2741 terminal also applies to the IBM 3767 terminal, unless otherwise noted.

Note: Information on the IBM 3344 and 3350 Direct Access Storage Devices is for planning purposes only until the availability of the products.

For a glossary of VM/370 terms, see the IBM Virtual Machine Facility/370: Glossary and Master Index, Order No. GC20-1813.

Prerequisite Publications

In addition to the VM/370: CMS User's Guide, prerequisite information is contained in the following publications:

- For information about the terminal that you are using, including procedures for gaining access to the VM/370 system and logging on, see the IBM Virtual Machine Facility/370: Terminal User's Guide, Order No. GC20-1810.

If you are using an IBM 3767 Communications Terminal, the IBM 3767 Operator's Guide, Order No. GA18-2000, is a prerequisite.

- The CP commands that are available to you as a general user are described in

IBM Virtual Machine Facility/370: CP Command Reference for General Users, Order No. GC20-1820.

For additional tutorial information on using CMS, you may want to use CMS for Programmers - A Primer, Order No. SR20-4438.

If you are going to use an IBM Program Product compiler under CMS, you should have available the appropriate program product documentation. These publications are listed in IBM Virtual Machine Facility/370: Introduction.

Corequisite Publications

The IBM Virtual Machine Facility/370: System Messages, Order No. GC20-1808, describes all of the error messages and system responses produced by the CMS commands and EDIT and DEBUG subcommands referenced in this publication. It also lists the error messages issued by the EXEC processor during execution of your EXEC procedures.

If you are using CMS to prepare and develop job streams to run under other virtual machines in VM/370, you should consult IBM Virtual Machine Facility/370: Operating Systems in a Virtual Machine, Order No. GC20-1821.

Related VM/370 Publications

For general information about the VM/370 system, see the publications IBM Virtual Machine Facility/370: Introduction, Order No. GC20-1800, and VM/370 Features Supplement, Order No. GC20-1757.

Additional descriptions of various CMS functions and commands which are normally used by system support personnel are described in

IBM Virtual Machine Facility/370:

System Programmer's Guide, Order No. GC20-1807

Operator's Guide, Order No. GC20-1806

Planning and System Generation Guide, Order No. GC20-1801

Interactive Problem Control System (IPCS) User's Guide Order No. GC20-1823

Environmental Recording, Editing, and Printing (EREP) Program, Order No. GC29-8300.

There are two publications available as ready reference material when you use VM/370 and CMS. They are IBM Virtual Machine Facility/370:

Quick Guide for Users, Order No. GX20-1926

Command Reference Summary, Order No. GX20-1961.

If you are going to use the Remote Spooling Communications Subsystem, see the IBM Virtual Machine Facility/370: Remote Spooling Communications Subsystem (RSCS) User's Guide, Order No. GC20-1816.

Assembler language programmers may find information about the VM/370 assembler in OS/VS, DOS/VS, and VM/370 Assembler Language, Order No. GC33-4010, and OS/VS and VM/370 Assembler Programmer's Guide, Order No. GC33-4021.

Related Publications for VSAM and Access Method Services Users

CMS support of Access Method Services is based on DOS/VS Access Method Services. The control statements that you can use are

described in DOS/VS Access Method Services User's Guide, Order No. GC33-5382. The VM/370: CMS User's Guide contains details on how to use this support. Error messages produced by the Access Method Services program, and return codes and reason codes are listed in DOS/VS Messages, Order No. GC33-5379.

For a detailed description of DOS/VS VSAM macros and macro parameters, refer to the DOS/VS Supervisor and I/O Macros, Order No. GC33-5373. For information on OS/VS VSAM macros, refer to OS/VS Virtual Storage Access Method (VSAM) Programmer's Guide, Order No. GC26-3818.

Related Publications for CMS/DOS Users

The CMS ESERV command invokes the DOS/VS ESERV program, and uses, as input, the control statements that you would use in DOS/VS. These control statements are described in Guide to the DOS/VS Assembler, Order No. GC33-4024.

Linkage editor control statements, used when invoking the DOS/VS linkage editor under CMS/DOS, are described in DOS/VS System Control Statements, Order No. GC33-5376.

CMS SIMULATES FUNCTIONS OF DOS/VS

New: Program Feature

The Conversational Monitor System (CMS) now simulates many of the functions of the Disk Operating System/VS (DOS/VS) to allow interactive development, testing, and debugging of DOS programs in a special superset of the CMS command environment, called CMS/DOS.

This publication incorporates the following changes to reflect this support:

- The SET command has three new operands:

--DOS, which invokes the CMS/DOS environment and optionally identifies the DOS/VS system residence volume to be used during a terminal session.

--UPSI, which allows you to set the UPSI (User Program Switch Indicator) byte for programs that use and test it.

--DOSPART, which allows you to set a virtual partition size for programs to execute in CMS/DOS.

These three operands have corresponding QUERY command operands, so that you can test their current settings.

- The following commands have been added to simulate DOS/VS job control and librarian functions:

ASSGN	ESERV	PSERV
DLBL	FETCH	RSERV
DOSLKED	LISTIO	SSERV
DSERV	OPTION	

The QUERY command has DLBL and OPTION operands, so you can test the file definitions and options set with the DLBL and OPTION commands.

- CMS simulates DOS/VS core image libraries in CMS libraries called DOSLIBS. The CMS commands that recognize DOSLIBS are:

--DOSLIB
--GLOBAL (DOSLIB operand)
--QUERY (DOSLIB and LIBRARY operands)

- A new EXEC special variable, &DOS, allows you to interrogate the status of the CMS/DOS environment.
- The GENMOD command has new options, DOS, OS, or ALL, that indicate whether the CMS/DOS environment should or should not be active when a MODULE file is executed.

The LOADMOD command checks, when a MODULE file is loaded, that the proper environment is active.

CMS READS AND WRITES VSAM DATA SETS

New: Program Feature

You can use CMS to manipulate VSAM data sets with DOS/VS Access Method Services and execute programs written in the COBOL, PL/I, and VS BASIC programming languages that read and write VSAM data sets. The following commands are new or changed to support CMS VSAM:

- The AMSERV command in CMS invokes Access Method Services to manipulate VSAM catalogs and data sets. Access Method Services control statements must be contained in a CMS file with a filetype of AMSERV.

The AMSERV filetype is recognized by the CMS Editor.

- The DLBL command establishes file identifications for VSAM data sets for OS and DOS users. Special options are provided for use with VSAM data sets: VSAM, CAT, EXTENT, MULT, and BUFSP.

- The LISTDS command has two new options, EXTENT and FREE, which provide you with information concerning allocated and unallocated extents on OS and DOS disks.

You can query the status of all accessed OS and DOS disks with the LISTDS command.

- The SET DOS ON command has a VSAM option for CMS/DOS users who are going to invoke Access Method Services or read and write VSAM data sets.
- Responses to the following CMS commands now indicate whether a disk is an OS or DOS disk, and whether it is accessed in read-only (R/O) or read/write (R/W) status:

```
ACCESS
QUERY SEARCH
QUERY DISK
```

CMS SUPPORTS DISCONTIGUOUS SAVED SEGMENTS

New: Program Feature

CMS now loads and releases saved systems beyond the end of user storage. The CMS SET command has a new operand, SYSNAME, that allows you to specify the name of the system that you want loaded, and an additional operand, NONSHARE, that allows you to specify that you want your own copy of a named system.

The QUERY command has a SYSNAMES operand so that you can determine what system names are currently in effect for your virtual machine.

CHANGES TO THE EXEC INTERPRETER

Changed: Programming and Documentation

The CMS EXEC processor now executes in the discontinuous saved segment named CMSSEG. The following enhancements have been made to EXEC:

- EXEC can now read variable-length files, to a maximum of 130 characters. In fixed-length EXEC files, only columns 1 through 72 are processed, but in variable-length files, records are processed for their entire length.

The CMS Editor defaults the record format of EXEC files to variable length.

- The &IF and &LOOP statements recognize the following special

character symbols, as well as mnemonics, for the comparison operators:

<u>Symbol</u>	<u>Mnemonic</u>	<u>Meaning</u>
=	EQ	equals
≠	NE	does not equal
<	LT	less than
<=	LE	less than or equal
>	GT	greater than
>=	GE	greater than or equal

- EXEC can now perform hexadecimal to decimal and decimal to hexadecimal conversion when a token begins with the characters X'. A hexadecimal value can be converted to its decimal equivalent in an assignment statement; in any other statement, a decimal value is converted to its hexadecimal equivalent.
- There are three new EXEC control statements:
 - &HEX, which initiates or inhibits hexadecimal conversion in an EXEC.
 - &EMSG, which allows you to display error messages in accordance with the current CP EMSG settings.
 - &BEGEMSG, which introduces one or more lines of error messages that are not scanned by the EXEC interpreter.
- The following new special variables have been added:
 - &DOS, which indicates whether or not the CMS/DOS environment is active (ON or OFF)
 - &DISKx, which indicates, for the disk accessed as mode 'x', whether the disk is CMS, OS, DOS, or not accessed (NA).
 - &DISK*, which contains the mode letter of the read/write disk with the most space, or NONE if there are no read/write disks accessed.
 - &DISK?, which contains the mode letter of the first read/write disk in the standard search order, or NONE if no read/write disks are accessed.

PUBLICATION REWRITTEN

New: Documentation Only

This publication contains information formerly in the following publications:

- CMS command formats and assembler language macro descriptions, formerly in IBM Virtual Machine Facility/370: Command Language Guide for General Users, are contained in "Section 2. CMS Commands" and "Section 6. CMS Macro Instructions."
- EDIT subcommand descriptions, formerly in IBM Virtual Machine Facility/370: EDIT Guide, are in "Section 3. EDIT Subcommands and Macros."
- EXEC control statement, special variable, and built-in function descriptions, formerly in IBM Virtual Machine Facility/370: EXEC User's Guide, are in "Section 5. EXEC Control Statements."
- DEBUG subcommand descriptions, formerly in the VM/370: System Programmer's Guide, are in "Section 4. DEBUG Subcommands."

Command format and operand descriptions have been rewritten to standardize the formats; notes have been added to clarify command or subcommand usage, with examples, where appropriate. Technical changes and additions to the commands and subcommands are indicated by revision bars in the left margin.

Detailed descriptions of error messages and responses from the editor, EXEC processor, and debug program are in VM/370: System Messages.

MISCELLANEOUS CHANGES

Changed: Programming and Documentation

There are two new CMS commands:

- STATEW, which is described with the STATE command. STATEW performs the same function as the STATE command, but verifies whether a file exists on a read/write disk.
- TAPEMAC, which reads OS macro libraries from tape created by the IEHMOVE utility program and creates a CMS MACLIB file directly from the tape.

The following additions or changes have been made to existing CMS commands:

- The RELEASE command has a new option, DET, which detaches the disk from your virtual machine configuration. The RELEASE command now results in the user file directory being sorted and rewritten on disk. This change also affects the ERASE option of the ACCESS command and the NOUPDIRT option of the RENAME command.
- The SYNONYM command no longer clears existing synonyms by default. You must use the CLEAR option to clear a synonym table. When you enter the SYNONYM command with no options, a list of current synonyms is displayed.

A new CMS macro instruction, FSCBD, which generates a DSECT for the CMS file system control block (FSCB) is documented in "Section 6. CMS Macro Instructions."

Numerous minor corrections have been made to the format descriptions of CMS commands, EDIT subcommands, and EXEC control statements, to clarify usage.

Messages and return codes produced by CMS commands have been updated.

Contents

SECTION 1. INTRODUCTION AND GENERAL		START.179
CONCEPTS.	11	STATE/STATEW180
The CMS Environment.	11	SVCTRACE182
Entering CMS Commands.	12	SYNONYM.186
Character Set Usage.	13	The User Synonym Table187
Notational Conventions	14	TAPE190
CMS Command Search Order	16	TAPEMAC.195
CMS Command Summary.	17	TAPPDS197
		TXTLIB200
SECTION 2. CMS COMMANDS.	25	TYPE202
ACCESS	26	UPDATE204
AMSERV	29	Immediate Commands216
ASSEMBLE	32	HB216
ASSGN.	37	HO216
CMSBATCH	40	HT217
COMPARE.	41	HX217
COPYFILE	43	RO217
Using the COPYFILE Command	46	RT218
CP	53	SO218
DDR	54		
DDR Control Statements	54	SECTION 3. EDIT SUBCOMMANDS AND MACROS .219	
I/O Definition Statements.	55	EDIT Subcommands219
DEBUG.	65	ALTER.220
DISK	66	AUTOSAVE221
DLBL	68	BACKWARD (Primarily 3270).222
DOSLIB	79	BOTTOM222
DOSLKED.	81	CASE223
DSERV.	84	CHANGE223
EDIT	86	CMS.226
ERASE.	88	DELETE227
ESERV.	90	DOWN227
EXEC	92	DSTRING.228
FETCH.	94	FILE229
FILEDEF.	96	FIND229
FORMAT	104	FMODE.230
GENDIRT.	107	FNAME.231
GENMOD	108	FORMAT (3270 only)231
GLOBAL	111	FORWARD (primarily 3270)232
INCLUDE.	113	GETFILE.233
LISTDS	116	IMAGE.234
LISTFILE	120	INPUT.235
LISTIO	123	LINEMODE236
LOAD	125	LOCATE238
Loader Control Statements.	129	LONG238
LOADMOD.	134	NEXT239
MACLIB	135	OVERLAY.240
MODMAP	138	PRESERVE241
MOVEFILE	139	PROMPT241
OPTION	142	QUIT242
PRINT.	144	RECFM.242
PSERV.	147	RENUM.243
PUNCH.	149	REPEAT244
QUERY.	152	REPLACE.245
READCARD	159	RESTORE.245
RELEASE.	162	RETURN246
RENAME	164	REUSE (=)246
RSERV.	166	SAVE248
RUN.	168	SCROLL/SCROLLUP (3270 ONLY).248
SET.	170	SERIAL249
SORT	175	SHORT251
SSERV.	177	STACK.251
		TABSET252

TOP253	&SUBSTR298
TRUNC253	Special Variables299
TYPE254	&n299
UP255	&* and &\$299
VERIFY256	&0299
X or Y257	&DISKx299
ZONE258	&DISK*300
?259	&DISK?300
nnnnn260	&DOS300
EDIT Macros261	&EXEC300
\$DUP261	&GLOBAL300
\$MOVE262	&GLOBALn301
SECTION 4. DEBUG SUBCOMMANDS263	&INDEX301
BREAK264	&LINENUM301
CAW265	&READFLAG301
CSW266	&RETCODE301
DEFINE267	&TYPEFLAG301
DUMP268	SECTION 6. CMS MACRO INSTRUCTIONS303
GO269	COMPSWT304
GPR270	FSCB304
HX270	FSCBD305
ORIGIN271	FSCLOSE306
PSW272	FSErase307
RETURN272	FSOPEN308
SET273	FSREAD309
STORE274	FSSTATE311
X275	FSWRITE312
SECTION 5. EXEC CONTROL STATEMENTS277	HNDEXT314
The Assignment Statement278	HNDINT315
&ARGS279	HND SVC316
&BEGEMSG279	LINEDIT317
&BEGPUNCH281	LINEDIT Macro Operands318
&BEGSTACK281	PRINTL327
&BEGTYPE282	PUNCHC329
&CONTINUE282	RDCARD330
&CONTROL283	RDTAPE331
&EMSG284	RDTERM332
&END285	REGEQU333
&ERROR285	TAPECTL334
&EXIT286	WAITD336
&GOTO287	WAITT337
&HEX287	WRTAPE337
&IF288	WRTERM339
&LOOP289	APPENDIXES341
&PUNCH290	APPENDIX A: RESERVED FILETYPE DEFAULTS343
&READ291	APPENDIX B: DOS/V S ACCESS METHOD SERVICES AND VSAM FUNCTIONS NOT SUPPORTED IN CMS345
&SKIP291	APPENDIX C: OS/V S ACCESS METHOD SERVICES AND VSAM FUNCTIONS NOT SUPPORTED IN CMS347
&SPACE292	INDEX349
&STACK293		
&TIME294		
&TYPE295		
Built-in Functions296		
&CONCAT296		
&DATATYPE297		
&LENGTH297		
&LITERAL298		

Figures

Figure 1.	Character Sets and Their Contents.....	14	Figure 10.	LIBRARY Statement Format.....	129
Figure 2.	How CMS Searches for the Command to Execute.....	18	Figure 11.	LDT Statement Format.....	130
Figure 3.	CMS Command Summary.....	20	Figure 12.	ICS Statement Format.....	130
Figure 4.	COPYFILE Option Incompatibilities.....	46	Figure 13.	SLC Statement Format.....	131
Figure 5.	An Annotated Sample of Output From the TYPE and PRINT Functions of the DDR Program.....	61	Figure 14.	REP Statement Format.....	132
Figure 6.	Determining Which VSAM Catalog to Use.....	74	Figure 15.	Default Device Attributes for the MOVEFILE Command.....	140
Figure 7.	Valid File Characteristics for Each Device Type of the FILEDEF Command.....	97	Figure 16.	Header Card Format.....	150
Figure 8.	Loader Search Order.....	128	Figure 17.	Summary of SVC Trace Output Lines.....	185
Figure 9.	ENTRY Statement Format.....	129	Figure 18.	System and User-defined Truncations.....	189
			Figure 19.	Default EDIT Subcommand Settings for the CMS Reserved Filetypes.....	343
			Figure 20.	OS Access Method Services Operands Not Supported in CMS.....	348



Section 1. Introduction and General Concepts

Virtual Machine Facility/370 (VM/370) is a system control program (SCP) that controls "virtual machines." A virtual machine is the functional equivalent of a real machine, but where the real machine has lights to show status, and buttons and switches on the real system console to control it, the virtual machine has a virtual system console to display status and a command language to start operations and control them. The virtual system console is your terminal; there are three command languages, which correspond roughly to the four components of the VM/370 system:

- The Control Program (CP) controls the resources of the real machine; that is, the physical machine in your computer room. The CP commands are described in VM/370: CP Command Reference for General Users.
- The Remote Spooling Communications Subsystem (RSCS) is a subsystem designed to supervise transmission of files across a teleprocessing network controlled by CP. For information about RSCS, see the VM/370: Remote Spooling Communications Subsystem (RSCS) User's Guide.
- The Conversational Monitor System (CMS) is a conversational operating system designed to run under CP. All of the CMS commands for general use, and the subcommands and macros that you can use in the CMS environment, are described in this publication.
- The Interactive Problem Control System (IPCS) provides system programmers and installation support personnel with VM/370 problem analysis and management facilities, including problem report creation, problem tracking, and CP abend dump analysis. IPCS runs in the CMS command environment; for details, see VM/370: IPCS User's Guide.

Except for IPCS, each of the components of VM/370 has a unique "command environment" which must be active in order for a command to be accepted. For CMS users, the two basic command environments are the CP command environment and the CMS command environment. By default, CP commands are acceptable input in the CMS command environment; if you enter a CP command, it is executed by CP, but control returns to the CMS environment.

The CMS Environment

The CMS command language allows you to create, modify, debug, and, in general, manipulate a system of files.

The OS/VS Assembler and many OS/VS and DOS/VS language processors can be executed under CMS. For example, the OS VS BASIC, FORTRAN IV, COBOL and PL/I compilers, as well as the DOS PL/I and COBOL compilers, can execute under CMS. You can find a complete list of language processors that can be executed under CMS in the VM/370: Introduction. CMS invokes the assembler and the compilers when you issue the appropriate CMS commands. The ASSEMBLE command is described in this manual; the supported compiler commands are described in the appropriate Program Product manuals.

CMS commands allow you to read cards from a virtual card reader, punch cards to a virtual card punch, and print records on a virtual printer. Many commands are provided to help you manipulate your virtual disks and files.

The EDIT command places your virtual machine in the EDIT subcommand environment. In this environment you can use the CMS Editor to create and modify files. In the EDIT subcommand environment, you can place your virtual machine in either of two modes, edit mode or input mode. Edit mode lets you modify a file; input mode lets you create or add to a file. The subcommands available to you in the EDIT subcommand environment are described in "Section 3. EDIT Subcommands and Macros."

The EXEC command executes CMS command procedures, called EXEC files. You can create EXEC procedures consisting of CMS and CP commands and EXEC control statements. The EXEC facility also has a symbolic capability; by manipulating variable symbols within an EXEC file, you can control the execution of the procedure. These procedures are usually created in the edit environment. The EXEC control statements, variable symbols, and built-in functions are described in "Section 5. EXEC Control Statements."

The DEBUG command places your virtual machine in the DEBUG subcommand environment. In this environment you can issue commands to display registers and storage, specify breakpoints (address instruction stops), display the contents of control words, and so on. The DEBUG subcommands are described in "Section 4. DEBUG Subcommands."

| A special set of CMS commands becomes available to you when you issue
| the command

| set dos on

| These commands, called CMS/DOS commands, simulate various functions of
| the Disk Operating System (DOS) in your CMS virtual machine. When the
| CMS/DOS environment is active, the CMS/DOS commands are an integral part
| of the CMS command language; they are listed alphabetically among the
| other CMS commands in "Section 2. CMS Commands."

Entering CMS Commands

A CMS command consists of a command name, usually followed by one or more positional operands and, in many cases, by an option list. CMS commands, and EDIT and DEBUG subcommands described in this publication are shown in the format:

```
command name | [operands...] [(options...[ ])]
```

You must use one or more blanks to separate each entry in the command line unless otherwise indicated. For an explanation of the special symbols used to describe the command syntax, see "Notational Conventions."

The Command Name

The command name is an alphameric symbol of not more than eight characters. In general, the names are based on verbs that describe the

function you want the system to perform. For example, you may want to find out information concerning your CMS files. In this case, you would use the LISTFILE command.

The Command Operands

The command operands are keywords and/or positional operands of no more than eight, and in a few cases, seven alphanumeric characters each. The operands specify the information on which the system operates when it performs the command function.

You must write the operands in the order in which they appear in the command formats in "Section 2. CMS Commands," unless otherwise specified. When you are using CMS, blanks may optionally be used to separate the last operand from the option list. CMS recognizes a left parenthesis "(" as the beginning of an option list; it does not have to be preceded by a blank.

The Command Options

The command options are keywords used to control the execution of the command. The command formats in "Section 2. CMS Commands" show all the options for each CMS command.

The option list must be preceded by a left parenthesis; the closing parenthesis is not necessary.

For most commands, if conflicting or duplicate options are entered, the last entered is the option in effect for the command. Exceptions to this rule are noted where applicable.

Comments in CMS Command Lines

If you want to write comments with CMS commands, you enter them following the closing parenthesis of the option list. The only exception to this rule is the ERASE command, for which comments are not allowed.

You can also enter comments on your console by using the CP * command.

Character Set Usage

CMS commands may be entered using a combination of characters from six different character sets. The contents of each of the character sets is shown in Figure 1.

Character Set	Names	Symbols
Separator	Blank	
National	Dollar Sign	\$
	Pound Sign	#
	At Sign	@
Alphabetic	Uppercase	A - Z
	Lowercase	a - z
Numeric	Numeric	0 - 9
Alphameric	National	\$, #, @
	Alphabetic	A - Z
	Numeric	0 - 9
Special		All other characters

Figure 1. Character Sets and Their Contents

Notational Conventions

The notation used to define the command syntax in this publication is:

- Truncations and Abbreviations of Commands

Where truncation of a command name is permitted, the shortest acceptable version of the command is represented by uppercase letters. (Remember, however, that CMS commands can be entered with any combination of uppercase and lowercase letters.) The following example shows the format specification for the FILEDEF command.

Filedef

This format means that FI, FIL, FILE, FILED, FILEDE, and FILEDEF are all valid specifications for this command name.

Operands and options are specified in the same manner. Where truncation is permitted, the shortest acceptable version of the operand or option is represented by uppercase letters in the command format box. If no minimum truncation is noted, the entire word (represented by all uppercase letters) must be entered.

Abbreviations are shorter forms of command operands, and options. Abbreviations for operands and options are shown in the description of the individual operands and options that follow the format box. For example, the abbreviation for MEMBER in the PRINT command is MEM. Only these two forms are valid and no truncations are allowed. The format box contains

```
MEMBER { name }
      { * }
```

and the description that follows the format box is

```
MEMBER { name }
MEM      { * }
```

- The following symbols are used to define the command format and should never be typed when the actual command is entered.

```

underscore
braces      { - }
brackets    [ ]
ellipsis    ...

```

- Uppercase letters and words, and the following symbols, should be entered as specified in the format box.

```

asterisk    *
comma       ,
hyphen      -
equal sign  =
parentheses ( )
period      .
colon       :

```

- The abbreviations, fn ft and fm, are used to refer to filename, filetype, and filemode, respectively. The combination of fn ft [fm] are sometimes collectively referred to as file identifier, or fileid.

When a command format box shows the characters, fn ft fm or fileid and they are not enclosed by brackets or braces, it indicates that a CMS file identifier must be entered. If an asterisk (*) appears beneath fn, ft, or fm, it indicates that an asterisk may be coded in that position of the fileid. The operand description describes the usage of the *.

- Lowercase letters, words, and symbols that appear in the command format box represent variables for which specific information should be substituted. For example, "fn ft fm" indicates that file identifiers such as "MYFILE EXEC A1" should be entered.

- Choices are represented in the command format boxes by stacking.

```

A
B
C

```

- An underscore indicates an assumed default option. If an underscored choice is selected, it need not be specified when the command is entered.

Example

The representation

```

A
B
C

```

indicates that either A, B, or C may be selected. However, if B is selected, it need not be specified. Or, if none is entered, B is assumed.

- The use of braces denotes choices, one of which must be selected.

Example

The representation

```
{ A }
  B }
  C }
```

indicates that you must specify either A, or B, or C. If a list of choices is enclosed by neither brackets or braces, it is to be treated as if enclosed by braces.

- The use of brackets denotes choices, one of which may be selected.

Example:

The representation

```
[ A ]
[ B ]
[ C ]
```

indicates that you may enter A, B, or C, or you may omit the field.

- An ellipsis indicates that the preceding item or group of items may be repeated more than once in succession.

Example

The representation

(options...)

indicates that more than one option may be coded within the parentheses.

CMS COMMAND SEARCH ORDER

When you enter a command name at the terminal, CMS begins searching for the command of that name. Once a match is found, the search stops. The search order is:

1. EXEC file on any currently accessed disk. CMS uses the standard search order (A through G, S, Y, and Z.)
2. Valid abbreviation or truncation for an EXEC file on any currently accessed disk, according to current SYNONYM file definitions in effect.
3. CMS command that has already been loaded into the transient area.

The commands that execute in the transient are:

ACCESS	FILEDEF	OPTION
ASSGN	GENDIRT	PRINT
COMPARE	GLOBAL	PUNCH
DISK	LISTFILE	QUERY
DLBL	MODMAP	READCARD

RELEASE	SVCTRACE	TAPE
RENAME	SYNONYM	TYPE
SET		

4. CMS nucleus resident command. The nucleus-resident CMS commands are:

CP	GENMOD	START
DEBUG	INCLUDE	STATE
ERASE	LOAD	STATEW
FETCH	LOADMOD	

5. Command module on any currently accessed disk. (All the remaining CMS commands are disk resident and execute in the user area.)

6. Valid abbreviation or truncation for nucleus-resident or transient area command module.

7. Valid abbreviation or truncation for disk resident command.

Figure 2 shows a basic description of the command search order; you can find complete details in the VM/370: System Programmer's Guide.

CMS Command Summary

Figure 3 contains an alphabetical list of the CMS commands and the functions performed by each. Unless otherwise noted, CMS commands are described in this manual. The "Code" column in Figure 3 indicates, for those commands not described in this manual, the reference source for that command:

<u>Code</u>	<u>Meaning</u>
DOS PP	indicates that this command invokes a DOS Program Product, available from IBM for a license fee.
EREP	indicates that this command is described in the <u>VM/370: Environmental Recording, Editing, and Printing (EREP) Program</u> .
IPCS	indicates that this command is a part of the Interactive Problem Control System (IPCS) and is described in the <u>VM/370: Interactive Problem Control System (IPCS) User's Guide</u> .
Op Gd	indicates that this command is described in the <u>VM/370: Operator's Guide</u> .
OS PP	indicates that this command invokes an OS Program Product, available from IBM for a license fee.
SCRIPT	indicates that this command invokes a text processor that is an IBM Installed User Program, available from IBM for a license fee.
SPG	indicates that this command is described in the <u>VM/370: System Programmer's Guide</u> .
SYSGEN	indicates that this command is described in the <u>VM/370: Planning and System Generation Guide</u> .
<u>Note:</u>	If a CMS command is described in this manual, but is also repeated in other VM/370 publications, the chart does not refer to those other publications.




Figure 2. How CMS Searches for the Command to Execute

Any of the commands listed in Figure 3 may be entered when: you are running CMS in your virtual machine, the terminal is idle, and the virtual machine is receptive for input. If however, CMS is processing a previously entered command and your typewriter terminal keyboard is locked, you must signal your virtual machine via an attention interrupt. The system acknowledges the interrupt by unlocking the keyboard. Now you can enter commands.

If your terminal is a display device, there is no problem of entering commands while the virtual machine is busy as its keyboard remains unlocked for additional command input. Note that in these circumstances the command you enter is stacked and is not executed until the command that is currently executing completes. If more commands are entered than can be handled by CP, a NOT ACCEPTED message is displayed at the display terminal.

In addition to the commands listed in Figure 3, there are seven commands called Immediate commands which are handled in a different manner from the others. They may be entered while another command is executing, by pressing the Attention key (or its equivalent) and they are executed immediately. The Immediate commands are:

- HB - Halt batch execution
- HO - Halt tracing
- HT - Halt typing
- HX - Halt execution
- RO - Resume tracing
- RT - Resume typing
- SO - Suspend tracing

Command	Code	Usage
ACCESS		Identify direct access space to a CMS virtual machine, create extensions and relate the disk space to a logical directory.
AMSERV		Invoke Access Method Services utility functions to create, alter, list, copy, delete, import, or export VSAM catalogs and data sets.
ASM3705	SYSGEN	Assemble 3704/3705 source code.
ASSEMBLE		Assemble Assembler Language source code.
ASSGN		Assign or unassign a CMS/DOS system or programmer logical unit for a virtual I/O device.
CMSBATCH		Invoke the CMS Batch Facility.
COBOL	OS PP	Compile OS ANS Version 4 or OS/VS COBOL source code.
COMPARE		Compare records in CMS disk files.
CONVERT	OS PP	Convert free form FORTRAN statements to fixed form.
COPYFILE		Copy CMS disk files according to specifications.
CP		Enter CP commands from the CMS environment.
CPEREP	EREP	Edit and print error information which was recorded by VM/370 error recording routines.
DDR	Op Gd, SYSGEN	Perform backup, restore, and copy operations for disks.
DEBUG		Enter DEBUG subcommand environment, debug mode.
DIRECT	Op Gd, SYSGEN	Set up VM/370 directory entries.
DISK		Perform disk-to-card and card-to-disk operations for CMS files.
DLBL		Define a DOS filename or VSAM ddname and relate that name to a disk file.
DOSGEN	SYSGEN	Load and save the CMSDOS shared segment.
DOSLIB		Delete, compact, or list information about the phases of a CMS/DOS phase library.
DOSLKED		Link-edit CMS text decks or object modules from a DOS/VS relocatable library and place them in executable form in a CMS/DOS phase library.
DOSPLI	DOS PP	Compile DOS PL/I source code under CMS/DOS.
DSERV		Display information contained in the DOS/VS core image, relocatable, source, procedure, and transient directories.

Figure 3. CMS Command Summary (Part 1 of 4)

Command	Code	Usage
DUMPSCAN	IPCS	Provide interactive analysis of CP abend dumps.
EDIT		Invoke the CMS Editor to create or modify a disk file.
ERASE		Delete CMS disk files.
ESERV		Display, punch or print an edited (compressed) macro from a DOS/VS source statement library (E sublibrary).
EXEC		Execute special procedures made up of frequently used sequences of commands.
FCOBOL	DOS PP	Compile DOS/VS COBOL source code under CMS/DOS.
FETCH		Fetch a CMS/DOS or DOS/VS executable phase.
FILEDEF		Define an OS ddname and relate that ddname to any device supported by CMS.
FORMAT		Prepare disks in CMS 800-byte block format.
FORTGI	OS PP	Compile FORTRAN source code using the G1 compiler.
FORTHX	OS PP	Compile FORTRAN source code using the H-extended compiler.
GEN3705	SYSGEN	Generate an EXEC file that assembles and link-edits the 3704/3705 control program.
GENDIRT		Fill in auxiliary module directories.
GENMOD		Generate non-relocatable CMS files (MODULE files).
GLOBAL		Identify specific CMS libraries to be searched for macros, copy files, missing subroutines, or DOS executable phases.
GOFORT	OS PP	Compile FORTRAN source code and execute the program using the FORTRAN Code and Go compiler.
INCLUDE		Bring additional TEXT files into storage and establish linkages.
LISTDS		List information about data sets and space allocation on OS, DOS, and VSAM disks.
LISTFILE		List information about CMS disk files.
LISTIO		Display information concerning CMS/DOS system and programmer logical units.
LKED	SYSGEN	Link-edit the 3704/3705 control program.
LOAD		Bring TEXT files into storage for execution.
LOADMOD		Bring a single MODULE file into storage.
MACLIB		Create or modify CMS macro libraries.

Figure 3. CMS Command Summary (Part 2 of 4)

Command	Code	Usage
MODMAP		Display the load map of a MODULE file.
MOVEFILE		Move data from one device to another device of the same or a different type.
NCPDUMP	Op Gd, SYSGEN, SPG	Process CP spool reader files created by 3704/3705 dumping operations.
OPTION		Change the DOS COBOL compiler (FCOBOL) options that are in effect for the current terminal session.
PLIC	OS PP	Compile and execute PL/I source code using the PL/I Checkout Compiler.
PLICR	OS PP	Execute the PL/I object code generated by the OS PL/I Checkout Compiler.
PLIOPT	OS PP	Compile PL/I source code using the OS PL/I Optimizing Compiler.
PRB	IPCS	Update IPCS problem status.
PRINT		Spool a specified CMS file to the virtual printer.
PROB	IPCS	Enter a problem report in IPCS.
PSERV		Copy a procedure from the DOS/VS procedure library onto a CMS disk, display the procedure at the terminal, or spool the procedure to the virtual punch or printer.
PUNCH		Spool a copy of a CMS file to the virtual punch.
QUERY		Request information about a CMS virtual machine.
READCARD		Read data from spooled card input device.
RELEASE		Make a disk and its directory inaccessible to a CMS virtual machine.
RENAME		Change the name of a CMS file or files.
RSERV		Copy a DOS/VS relocatable module onto a CMS disk, display it at the terminal, or spool a copy to the virtual punch or printer.
RUN		Initiate series of functions to be performed on a source, MODULE, TEXT, or EXEC file.
SAVENC	SYSGEN, SPG	Read 3704/3705 control program load into virtual storage and save an image on a CP-owned disk.
SCRIPT	SCRIPT	Format and print documents according to embedded SCRIPT control words in the document file.
SET		Establish, set, or reset CMS virtual machine characteristics.

Figure 3. CMS Command Summary (Part 3 of 4)

Command	Code	Usage
SETKEY	SPG	Assign storage protect keys to storage assigned to named systems.
SORT		Arrange a specified file in ascending order according to sort fields in the data records.
SSERV		Copy a DOS/VS source statement book onto a CMS disk, display it at the terminal, or spool a copy to the virtual punch or printer.
START		Begin execution of programs previously loaded (OS and CMS) or fetched (CMS/DOS).
STAT	IPCS	Display the status of reported system problems.
STATE		Verify the existence of a CMS disk file.
STATEW		Verify a file on a read/write CMS disk.
SVCTRACE		Record information about supervisor calls.
SYNONYM		Invoke a table containing synonyms you have created for CMS and user-written commands.
TAPE		Perform tape-to-disk and disk-to-tape operations for CMS files, and position tapes.
TAPEMAC		Create CMS MACLIB libraries directly from an IEHMOVE-created partitioned data set on tape.
TAPPDS		Load OS partitioned data set (PDS) files or card image files from tape to disk.
TESTCOB	OS PP	Invoke the OS COBOL Interactive Debug Program.
TESTFORT	OS PP	Invoke the FORTRAN Interactive Debug Program.
TXTLIB		Generate and modify text libraries.
TYPE		Display all or part of a CMS file at the terminal.
UPDATE		Make changes in a program source file as defined by control cards in a control file.
VMFDUMP	Op Gd IPCS	Format and print system abend dumps; under IPCS, create a problem report.
VMFLOAD	SYSGEN	Generate a new CP, CMS or RSCS module.
VSAMGEN	SYSGEN	Load and save the VSAM shared segment.
VSAPL	OS PP	Invoke the VS APL interface.
VS BASIC	OS PP	Compile and execute VS BASIC programs under CMS.
VSUTIL	OS PP	Convert BASIC 1.2 data files to VS BASIC format.
ZAP	Op Gd, SYSGEN, SPG	Modify or dump LOADLIB, TXTLIB, or MODULE files.

Figure 3. CMS Command Summary (Part 4 of 4)

Section 2. CMS Commands

This section contains reference information for the CMS commands used by general users. Each command description indicates the format, operands and options, and error messages and return codes issued by the command. Usage notes are provided, where applicable.

The formats of the DEBUG, EDIT, and EXEC commands are also listed; for details on the EDIT or DEBUG subcommands or EXEC control statements, see:

- "Section 3. EDIT Subcommands and Macros"
- "Section 4. DEBUG Subcommands"
- "Section 5. EXEC Control Statements"

For more detailed usage information on CMS commands, see the VM/370: CMS User's Guide.

ACCESS

ACCESS

Use the ACCESS command to identify a disk to CMS, establish a filemode letter for the files on the disk, and set up a file directory in storage. The specifications of the ACCESS command determine the entries in the user file directory. The format of the ACCESS command is:

```
Access | cuu mode[/ext [fn [ft [fm]]]] [(NOPROF [ ])]  
      | 191 A * * *  
      | cuu mode (ERASE [ ])  
      | (NODISK [ ])
```

where:

cuu makes the disk at the specified virtual device address available. The default value is 191.

Valid addresses are 001 through 5FF for a virtual machine in basic control mode, and 001 through FFF for a virtual machine in extended control mode.

mode assigns a 1-character filemode letter to all files on the disk being accessed. This field must be specified if cuu is specified. The default value is A.

ext indicates the mode of the parent disk. Files on the disk being accessed (cuu) are logically associated with files on the parent disk; the disk at cuu is considered a read-only extension. A blank must not precede or follow the diagonal (/).

fn [ft [fm]] defines a subset of the files on the specified disk. Only the specified files are included in the user file directory and only those files can be read. An asterisk coded in any of these fields indicates all filenames, filetypes, or filemode numbers (except 0) are to be included. (See Usage Notes 3 and 4.)

Options:

NOPROF suppresses execution of a PROFILE EXEC file. This option is valid only if the ACCESS command is the first command entered after you IPL CMS. On subsequent ACCESS commands, the NOPROF option is ignored.

ERASE specifies that you want to erase all of the files on the specified disk. This option is only valid for read/write disks. (See Usage Note 6.)

NODISK lets you gain access to the CMS operating system with no disks accessed except the system disk (S-disk) and its extensions. This option is only valid if the ACCESS command is the first command you enter after you IPL CMS.

Usage Notes

1. If you have disk addresses 190, 191, 192, and 19E defined in the VM/370 directory, or if they are defined before you IPL CMS, these disks are accessed as the S-, A-, D-, and Y-disks respectively. You must issue explicit ACCESS commands to access any other disks you wish to use following an IPL of the CMS system. Ordinarily, you have access only to files with a filemode number of 2 on the system disk.
2. Each CMS disk has associated with it a master file directory, which contains an entry for every CMS file on the disk. The user file directory created in storage by the ACCESS command contains entries for only those files that you can reference.

| You should issue an ACCESS command every time you link to a new
| minidisk with the CP LINK command, to obtain the appropriate file
| directory.

3. The filename, filetype, and filemode fields can only be specified for disks which are accessed as read-only extensions. For example,

```
access 195 b/a * assemble
```

gives you read-only access to all the files with a filetype of ASSEMBLE on the disk at virtual address 195. The command

```
access 190 z/a * * z1
```

gives you access to all files on the system disk (190) that have a filemode number of 1.

When you access any disk in read-only status, files with a filemode number of 0 are not accessed.

4. You can also identify a set of files on a disk by referring to a filename or filetype prefix. For example,

```
access 192 c/a abc*
```

accesses only those files in the disk at virtual address 192 whose filenames begin with the characters ABC. The command line

```
access 192 c/a * a* c2
```

gives you access to all files whose filetypes begin with an A and which have a filemode number of 2.

5. You can force a read/write disk into read-only status by accessing it as an extension of another disk or of itself, for example,

```
access 191 a/a
```

forces your A-disk into read-only status.

| 6. If you enter the ERASE option by mistake you can recover from the
| error as long as you have not yet written any new files onto the
| disk. (That is, you have not yet caused CMS to rewrite the master
| file directory.) Reissue the ACCESS command without the ERASE
| option.

7. You should never attempt to access a disk in read/write status if another user already has it in read/write status; the results are unpredictable.

ACCESS

ACCESSING OS AND DOS DISKS:

1. You cannot specify filename, filetype and filemode when you access OS or DOS disks, nor can you specify any options.
2. When you are using OS or DOS disks, you must have a read/write CMS A-disk available if you are going to use the LOAD command with the MAP option. (MAP is a default option.)

Responses

```
DMSACC723I mode (cuu) { R/O } [ -OS ]
                      { R/W } [ -DOS ]
```

If the specified disk is a CMS disk, this message is displayed if the disk is read-only. If the disk is in OS or DOS format, the message indicates the format, as well as whether it is a read/write or read-only disk.

```
DMSACC724I cuu1 REPLACES mode(cuu2)
```

Before execution of the command, the disk represented by cuu2 was the "mode" disk. The disk, cuu1, is now assigned that filemode letter. This message is followed by message DMSACC726I.

```
DMSACC725I cuu ALSO = 'mode' [ -OS ] DISK
                              [ -DOS ]
```

The disk specified by cuu is the mode disk and an ACCESS command was issued to assign it another filemode letter.

```
DMSACC726I 'cuu mode' RELEASED
```

The disk being accessed at virtual address cuu as a read/write disk is already accessed at a different mode. It is released from that mode. Or, a disk currently accessed at mode is being replaced.

Other Messages and Return Codes

```
DMSACC002E FILE 'DMSROS TEXT' NOT FOUND RC=28
DMSACC003E INVALID OPTION 'option' RC=24
DMSACC017E INVALID DEVICE ADDRESS 'cuu' RC=24
DMSACC048E INVALID MODE 'mode' RC=24
DMSACC059E 'cuu' ALREADY ACCESSED AS READ/WRITE 'mode' DISK RC=36
DMSACC060E FILE(S) 'fn [ft [fm]]' NOT FOUND. DISK 'mode(cuu)' WILL NOT
BE ACCESSED RC=28
DMSACC070E INVALID PARAMETER 'parameter' RC=24
DMSACC112S DISK 'mode(cuu)' DEVICE ERROR RC=100
DMSACC113S mode (cuu) NOT ATTACHED RC=100
DMSACC230W OS DISK - FILEID AND/OR OPTIONS SPECIFIED ARE IGNORED RC=4
DMSACC240S ERROR LOADING READ OS ROUTINE 'DMSROS TEXT'
```

| AMSERV

| Use the AMSERV command to invoke Access Method Services to:

- | • Define VSAM catalogs, data spaces, or clusters
- | • Alter, list, copy, delete, export or import VSAM catalogs and data sets

| The format of the AMSERV command is:

```

|-----|
| AMServ | fn1  [fn2] [(options...[ ])]
|         |   [fn1]
|         |
|         | options:
|         | [PRINT]
|         |
|         | [TAPIN {18n }] [TAPOUT {18n }]
|         | [TAPn }]   [TAPn }]
|         |
|-----|

```

| where:

| fn1 specifies the filename of a CMS file with a filetype of AMSERV that contains the Access Method Services control statements to be executed. CMS searches all of your accessed disks, using the standard search order, to locate the file.

| fn2 specifies the filename of the CMS file that is to contain the Access Method Services listing; the filetype is always LISTING. If fn2 is not specified, the LISTING file will have the same name as the AMSERV input file (fn1).

| The LISTING file is written to the first read/write disk in the standard search order, usually your A-disk. If a LISTING file with the same name already exists, it is replaced.

| Options:

| PRINT spools the output listing to the virtual printer, instead of writing it to disk. If PRINT is specified, fn2 cannot be specified.

| TAPIN {18n }
| {TAPn }
| specifies that tape input is on the tape drive at the addresss indicated by 18n or TAPn. n may be 1, 2, 3, or 4, indicating virtual addresses 181 through 184, respectively.

| TAPOUT {18n }
| {TAPn }
| specifies that tape output should be written to the tape drive at the address indicated by 18n or TAPn. n may be 1, 2, 3, or 4, indicating virtual addresses 181 through 184, respectively.

| Note: If both TAPIN and TAPOUT are specified, their virtual device addresses must be different.

AMSERV

Usage Notes

1. To create a job stream for Access Method Services, you can use the CMS Editor to create a file with the filetype of AMSERV. The editor automatically sets input margins at columns 2 and 72.
2. Refer to the DOS/VS Access Method Services User's Guide, for a description of Access Method Services control statements format and syntax. Restrictions placed on VSAM usage in CMS are listed in this publication, in "Appendix B: DOS/VS Access Method Services and VSAM Functions Not Supported in CMS" and "Appendix C: OS/VS Access Method Services and VSAM Functions Not Supported in CMS."
3. You must use the DLBL command to identify the master catalog and all disk input and output files for Access Method Services; the ddname operand of the DLBL command corresponds to the dname parameter following a FILE, INFILE, or OUTFILE keyword in an Access Method Services statement.
4. When you use tape input and/or output with the AMSERV command, you are prompted to enter the ddnames; a maximum of 16 ddnames are allowed for either input and output. The ddnames can each have maximum of seven characters, and must be separated by blanks.

Since only one tape can be attached at a time for either input or output while using AMSERV, if you enter more than one tape ddname, the tape files must be in the sequence they are used in the input stream.

Additional Notes for CMS/DOS Users:

1. You must assign a logical unit to be associated with each ddname named in a DLBL command when you use the AMSERV command in the CMS/DOS environment.
 2. CMS internally issues an ASSGN command for SYSIPT, and locates the source file; therefore you do not need to assign it. If you use the TAPIN or TAPOUT options, CMS also issues ASSGN commands for the tape drives (assigning logical units SYS004 and SYS005).
- Any other assignments and DLBL definitions that are in effect when you invoke the AMSERV command are saved and restored when the command completes executing.

Responses

The CMS Ready message indicates that Access Method Services has completed processing. If Access Method Services completed with a nonzero return code, the return code is shown in the Ready message. You should examine the LISTING file created by AMSERV to determine the results of Access Method Services processing.

The publication DOS/VS Messages, Order No. GC33-5379, lists and explains all of the messages generated by Access Method Services together with the associated reason codes.

DMSAMS367R ENTER TAPE {INPUT|OUTPUT} DDNAMES:

This message prompts you to enter the ddnames associated with the tape files.

| DMSAMS722I FILE 'fn2 LISTING fm' WILL HOLD AMSERV OUTPUT

| This message is displayed when you enter a fn2 operand or when the
| listing is not being written on your A-disk; it tells you the file
| identifier of the output listing.

| Other Messages and Return Codes

| DMSAMS001E NO FILENAME SPECIFIED RC=24
| DMSAMS002E FILE 'fn1 AMSERV' NOT FOUND RC=28
| DMSAMS003E INVALID OPTION 'option' RC=24
| DMSAMS006E NO READ/WRITE DISK ACCESSED FOR 'fn2 LISTING' RC=36
| DMSAMS007E FILE 'fn1 AMSERV fm' NOT FIXED, 80-CHAR. RECORDS RC=32
| DMSAMS065E 'option' OPTION SPECIFIED TWICE RC=24
| DMSAMS066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
| DMSAMS070E INVALID PARAMETER 'parameter' RC=24
| DMSAMS109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
| DMSAMS113E {TAPIN|TAPOUT} (addr) NOT ATTACHED RC=100
| DMSAMS136S UNABLE TO LOAD 'IDCAMS' RC=104
| DMSAMS228E NO DDNAME ENTERED RC=24
| DMSSTT062E INVALID CHARACTER 'char' IN FILEID {'fn1 AMSERV'|'fn2
| LISTING'} RC=20

ASSEMBLE

ASSEMBLE

Use the ASSEMBLE command to invoke the assembler to assemble a file containing source statements. Assembler processing and output is controlled by the options selected. The format of the ASSEMBLE command is:

```
Assemble | fn      [ (options...[]) ]
          |
          | listing control options:
          |
          |   [ ALOGIC ]   [ ESD ]   [ FLAG (nnn) ]   [ LINECOUN (nn) ]
          |   [ NOALOGIC ] [ NOESD ] [ FLAG (0) ]   [ LINECOUN (55) ]
          |
          |   [ LIST ]   [ MCALL ]   [ MLOGIC ]   [ RLD ]   [ LIBMAC ]
          |   [ NOLIST ] [ NOMCALL ] [ NOMLOGIC ] [ NORLD ] [ NOLIBMAC ]
          |
          |   [ XREF (FULL) ] [ PRINT ]
          |   [ XREF (SHORT) ] [ NOPRINT ]
          |   [ NOXREF ]       [ DISK ]
          |
          | output control options:
          |
          |   [ DECK ]   [ OBJECT ]   [ TEST ]
          |   [ NODECK ] [ NOOBJECT ] [ NOTEST ]
          |
          | SYSTEM options:
          |
          |   [ NUMBER ] [ STMT ] [ TERMINAL ]
          |   [ NONUM ] [ NOSTMT ] [ NOTERM ]
          |
          | other assembler options:
          |
          |   [ ALIGN ]   [ BUFSIZE (MIN) ] [ RENT ]
          |   [ NOALIGN ] [ BUFSIZE (STD) ] [ NORENT ]
          |
          |   [ YFLAG ]   [ SYSPARM (string) ]
          |   [ NOYFLAG ] [ SYSPARM ( ) ]
          |                   [ SYSPARM (?) ]
```

where:

fn is the filename of the source file to be assembled and/or the filename of assembler output files. The file must have fixed-length, 80-character records. By default, the assembler expects a CMS file with a filetype of ASSEMBLE.

Listing Control Options: The list below describes the assembler options you can use to control the assembler listing. The default values are underscored.

ALOGIC lists conditional assembly statements in open code.

NOALOGIC suppresses the ALOGIC option.

ESD lists the external symbol dictionary (ESD).

NOESD suppresses the printing of the ESD listing.

FLAG (nnn) does not include diagnostic messages and MNOTE messages below severity code nnn in the listing. Diagnostic messages can have severity codes of 4, 8, 12, 16, or 20 (20 is the most severe); and MNOTE message severity codes can be between 0 and 255. For example, FLAG (8) suppresses diagnostic messages with a severity code of 4 and MNOTE messages with severity codes of 0 through 7.

FLAG (0)

LINECOUN (nn) nn specifies the number of lines to be listed per page.

LINECOUN (55)

LIST produces an assembler listing.

NOLIST does not produce an assembler listing. This option overrides ESD, RLD, and XREF.

MCALL lists the inner macro instructions encountered during macro generation following their respective outer macro instructions. The assembler assigns statement numbers to these instructions. The MCALL option is implied by the MLOGIC option; NOMCALL has no effect if MLOGIC is specified.

NOMCALL suppresses the MCALL option.

MLOGIC lists all statements of a macro definition processed during macro generation after the macro instruction. The assembler assigns statement numbers to them.

NOMLOGIC suppresses the MLOGIC option.

RLD produces the relocation dictionary (RLD) as part of the listing.

NORLD does not print the relocation directory.

LIBMAC lists the macro definitions read from the macro libraries and any assembler statements following the logical END statement. The logical END statement is the first END statement processed during macro generation. It may appear in a macro or in open code; it may even be created by substitution. The assembler assigns statement numbers to the statements that follow the logical END statement.

NOLIBMAC suppresses the LIBMAC option.

XREF (FULL) includes in the assembler listing a cross-reference table of all symbols used in the assembly. This includes symbols that are defined but never referenced. The assembler listing also contains a cross-reference table of literals used in the assembly.

ASSEMBLE

XREF (SHORT) includes in the assembler listing a cross-reference table of all symbols that are referenced in the assembly. Any symbols defined but not referenced are not included in the table. The assembler listing contains a cross-reference table of literals used in the assembly.

NOXREF does not print the cross-reference tables.

PRINT writes the LISTING file to the printer.
PR

NOPRINT suppresses the printing of the LISTING file.
NOPR

DISK places the LISTING file on a virtual disk.
DI

Output Control Options: The output control options are used to control the object module output of the assembler.

DECK writes the object module on the device specified on the FILEDEF statement for PUNCH. If this option is specified together with the OBJECT option, the object module is written both on the PUNCH and TEXT files.

NODECK suppresses the DECK option.

OBJECT writes the object module on the device which is specified by the FILEDEF statement for TEXT. If this option is specified together with the DECK option, the object module is written on the two devices specified in the FILEDEF statement for TEXT and PUNCH.
OBJ

NOOBJECT does not create the object module.
NOOBJ

TEST includes the special source symbol table (SYM cards) in the object module.

NOTEST Does not produce SYM cards.

SYSTEM Options: The SYSTEM options are used to control the SYSTEM file associated with your assembly.

NUMBER writes the line number field (columns 73-80 of the input records) in the SYSTEM listing for statements for which diagnostic information is given. This option is valid only if TERMINAL is specified.
NUM

NONUM suppresses the NUMBER option.

STMT writes the statement number assigned by the assembler in the SYSTEM listing for statements for which diagnostic information is given. This option is valid only if TERMINAL is specified.

NOSTMT suppresses the STMT option.

TERMINAL writes the diagnostic information on the SYSTEM data set. The diagnostic information consists
TERM

of the diagnosed statement followed by the error message issued.

NOTERM suppresses the **TERMINAL** option.

Other Assembler Options: The following options allow you to specify various functions and values for the assembler.

ALIGN aligns all data on the proper boundary in the object module; for example, an F-type constant is aligned on a fullword boundary. In addition, the assembler checks storage addresses used in machine instructions for alignment violations.

NOALIGN does not align data areas other than those specified in CCW instructions. The assembler does not skip bytes to align constants on proper boundaries. Alignment violations in machine instructions are not diagnosed.

BUFSIZE (MIN) uses the minimum buffer sizes (790 bytes) for each of the utility data sets (SYSUT1, SYSUT2, and SYSUT3). Storage normally used for buffers is allocated to work space. Because more work space is available, more complex programs can be assembled in a given virtual storage size; but the speed of the assembly is substantially reduced.

BUFSIZE (STD) chooses the buffer size that gives optimum performance. The buffer size depends on the amount of virtual storage. Of the assembler working storage in excess of minimum requirements, 37% is allocated to the utility data set buffers and the rest to macro generation dictionaries.

RENT checks your program for a possible violation of program reenterability. Code that makes your program nonreenterable is identified by an error message.

NORENT suppresses the **RENT** option.

YFLAG does not suppress the warning messages that indicate that relocatable Y-type address constants have been declared.

NOYFLAG suppresses the warning messages that indicate relocatable Y-type constants have been declared.

SYSPARM { (string) }
 { () }
 { (?) }

passes a character value to the system variable symbol, **SYSPARM**. The variable (string) cannot be greater than 8 characters. If you want to enter a string of more than 8 characters, use the **SYSPARM (?)** format. With the **SYSPARM (?)** form, CMS prompts you with the message:

ENTER SYSPARM:

You can enter up to 100 characters. You can also enter parentheses and embedded blanks from the terminal. **SYSPARM ()** enters a null string of characters.

ASSEMBLE

Usage Notes

1. When you issue the ASSEMBLE command, default FILEDEF commands are issued for assembler data sets. You may want to override these with explicit FILEDEF commands. The ddnames used by the assembler are:

```
ASSEMBLE      (SYSIN input to the assembler)
TEXT          (SYSLIN output of the assembler)
LISTING       (SYSPRINT output of the assembler)
PUNCH         (SYSPUNCH output of the assembler)
CMSLIB        (SYSLIB input to the assembler)
```

The default FILEDEF commands issued by the assembler for these ddnames are:

```
FILEDEF ASSEMBLE DISK fn ASSEMBLE fm (RECFM FB LRECL 80 BLOCK 800)
FILEDEF TEXT DISK fn TEXT fm
FILEDEF LISTING DISK fn LISTING fm (RECFM FBA BLOCK 1210)
FILEDEF PUNCH PUNCH
FILEDEF CMSLIB DISK CMSLIB MACLIB * (RECFM FB LRECL 80 BLOCK 800)
```

2. If you want to use any CMS macro or copy libraries during an assembly, you must issue the GLOBAL command to identify the macro libraries before issuing the ASSEMBLE command. For example,

```
global maclib cmslib osmacro testlib
```

identifies the MACLIB files named CMSLIB, OSMACRO, and TESTLIB.

3. In order to use OS macro libraries during an assembly, you must issue the FILEDEF command for the OS data set using a ddname of CMSLIB, and assigning a CMS file identifier; the filetype must be MACLIB, and you must use the filename on the GLOBAL command line, for example,

```
filedef cmslib disk oldtest maclib c dsn oldtest macros
global maclib oldtest
```

assigns the OS data set OLDTEST.MACROS on the disk accessed as mode C, a CMS fileid of OLDTEST MACLIB and identifies it as the macro library to be used during assembly.

4. You cannot assemble programs using DOS macros from the DOS/VSE source statement libraries under CMS/DOS. You should use the SSERV, ESERV, and MACLIB commands to create CMS MACLIBS to contain DOS macros for assembly under CMS/DOS. See the VM/370: CMS User's Guide for examples.
5. You do not need to make any logical assignments for input or output files when you use the assembler under CMS/DOS. File definitions are assigned by default under CMS, as described in Usage Note 1.
6. Usage information about the VM/370 Assembler Language and assembler options can be found in OS/VSE and VM/370 Assembler Programmer's Guide and OS/VSE, DOS/VSE, and VM/370 Assembler Language.

Messages and Return Codes

For the messages and return codes associated with the ASSEMBLE command, see the OS/VSE and VM/370 Assembler Programmer's Guide.

| ASSGN

| Use the ASSGN command in CMS/DOS to assign or unassign a system or programmer logical unit for a virtual I/O device. The format of the ASSGN command is:

```
|
| ASSGN | SYSxxx ( Reader      [ (options...[]) ]
|         |         PUnch
|         |         PRinter
|         |         TermInal
|         |         {
|         |         TAP[n]
|         |         |1|
|         |         | |
|         |         mode
|         |         IGN
|         |         UA
|         |         }
|         |
|         |         options:
|         |         [UPCASE] [7TRACK] [TRTCH a]
|         |         [LOWCASE] [9TRACK]
|         |         [DEN den]
```

| where:

| SYSxxx specifies the system or programmer logical unit to be assigned to a particular physical device. SYS000 through SYS241 are valid programmer logical units in CMS/DOS; they may be assigned to any valid device. The system logical units you may assign, and the devices to which they may be assigned, are:

<u>SYSxxx</u>	<u>Valid assignments</u>
SYSRDR	Reader,disk,tape
SYSIPT	Reader,disk,tape
SYSIN	Reader,disk,tape
SYSpch	Punch,disk,tape
SYSLST	Printer,disk,tape
SYSLOG	Terminal,printer
SYSOUT	Tape
SYSsLB	Disk
SYSRLB	Disk
SYSCLB	Disk
SYSsCAT	Disk

| READER is the spooled card reader (card reader I/O must not be blocked).

| PUNCH is the spooled punch.

| PRINTER is the spooled printer.

| TERMINAL is your terminal (terminal I/O must not be blocked).

| TAP[n] is a magnetic tape. n is the symbolic number of the tape drive. It is either 1, 2, 3, or 4, representing virtual addresses 181, 182, 183, and 184, respectively. If n is omitted, TAP1 is assumed.

| mode specifies the 1-character mode letter of the disk being assigned to the logical unit (SYSxxx). The disk must be accessed when the ASSGN command is issued.

| IGN (ignore) specifies that any attempt to read from the specified device results in an end-of-file indication; any attempt to write to the device is ignored. IGN is not valid when associated with SYSRDR, SYSIPT, SYSIN, or SYSCLB.

ASSGN

UA indicates that the logical unit is to be unassigned. When you release a disk for which an assignment is active, it is automatically unassigned.

Options:

UPCASE translates all terminal input data to uppercase.

LOWCASE retains all terminal input data as keyed in.

7TRACK is the tape setting.

9TRACK

TRTCH a refers to the tape recording technique for 7-track tapes. Use the following chart to determine the value of a.

a	Parity	Converter	Translator
O	odd	off	off
OC	odd	on	off
OT	odd	off	on
E	even	off	off
ET	even	off	on

DEN den is tape density: den can be 200, 556, 800, 1600, or 6250 bits per inch (bpi). If 200 or 556 are specified, 7TRACK is assumed. If 800, 1600, or 6250 are specified, 9TRACK is assumed. (See Usage Note 8.)

Usage Notes

1. When you enter the CMS/DOS environment with the command SET DOS ON, SYSLOG is assigned by default to TERMINAL. If you specify the mode letter of the DOS/VS system residence on the SET DOS ON command line, SYSRES is assigned to that disk mode.

2. You cannot assign any of the following DOS/VS system logical units with the ASSGN command:

SYSRES SYSLNK SYSVIS
SYSUSE SYSREC

3. If you assign the logical unit SYSIN to a virtual device, SYSRDR and SYSIPT are also assigned to that device. If you make a logical assignment for SYSOUT, both SYSLST and SYSPCH are assigned.

4. To obtain a list of current assignments, use the LISTIO command.

5. To cancel all current assignments (that is, to unassign them), you can enter, in succession, the commands

set dos off
set dos on [mode]

6. If you want to access DOS/VS private libraries, you must assign the logical units SYSSLB (source statement library), SYSRLB (relocatable library), and SYSLB (core image library), and you must issue the DLBL command to establish a file definition.

| 7. An assignment to disk (mode) should be accompanied by a DLBL
| command that provides the disk file identification.

| You cannot make an assignment to a 3350 disk in native mode.

| 8. If no tape options are specified on the command line, the default
| for a seven-track tape is 800 bpi, data converter off, translator
| off, and odd parity. If the tape is 9-track, the density defaults
| to the density of the tape drive. 1600 bpi is the reset condition
| for 9-track dual density tapes. If the tape drive is phase
| encoded, density defaults to the density of the tape. If the tape
| drive is NRZI, the reset condition is 800 bpi.

| Responses

| None.

| Messages and Return Codes

| DMSASN003E INVALID OPTION 'option' RC=24
| DMSASN027E INVALID DEVICE 'device' RC=24
| DMSASN028E NO LOGICAL UNIT SPECIFIED RC=24
| DMSASN029E INVALID PARAMETER 'parameter' IN THE OPTION 'option'
| FIELD RC=24
| DMSASN035E INVALID TAPE MODE RC=24
| DMSASN050E PARAMETER MISSING AFTER SYSxxx RC=24
| DMSASN065E 'option' OPTION SPECIFIED TWICE RC=24
| DMSASN066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
| DMSASN069E DISK 'mode' NOT ACCESSED RC=36
| DMSASN070E INVALID PARAMETER 'parameter' RC=24
| DMSASN087E INVALID ASSIGNMENT of 'SYSxxx' TO DEVICE 'device' RC=24
| DMSASN090E INVALID DEVICE CLASS 'deviceclass' FOR 'device' RC=36
| DMSASN099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSASN113S '{TAPn|mode|READER|PUNCH|PRINTER} (cuu)' NOT ATTACHED RC=100
| DMSASN366E NO CMS/DOS SUPPORT FOR NATIVE 3350 DISK RC=36

CMSBATCH

CMSBATCH

The system operator uses the CMSBATCH command to invoke the CMS Batch Facility. Instead of compiling or executing a program interactively, you can transfer a job to an active CMS batch virtual machine to free up your terminal for other work. The format of the CMSBATCH command is:

```
CMSBATCH
```

Usage Notes

1. The CMSBATCH command may be invoked immediately after an IPL of the CMS system. Alternatively, BATCH may be specified following the PARM operand on the IPL command line.
2. You should not issue the CMSBATCH command if you use a virtual disk at address 195; the CMS batch virtual machine erases all files on the disk at address 195.
3. For a description of how to send jobs to the CMS batch virtual machine, see the VM/370: CMS User's Guide. For an explanation of setting up a batch virtual machine see the VM/370: Operator's Guide.

Error Messages and Return Codes

```
DMSBTB100E NO BATCH PROCESSOR AVAILABLE RC=40
DMSBTB101E BATCH NOT LOADED RC= 88
DMSBTP105E NO JOB CARD PROVIDED RC=None
DMSBTP106E JOB CARD FORMAT INVALID RC=None
DMSBTP107E CP/CMS COMMAND 'command, (device)' NOT ALLOWED RC=88
DMSBTP108E /SET CARD FORMAT INVALID RC=None
DMSBTP109E {CPU|PRINTER|PUNCH} LIMIT EXCEEDED RC=None
```


COMPARE

Other Messages and Return Codes

DMSCMP002E FILE 'fn ft fm' NOT FOUND RC=28
DMSCMP003E INVALID OPTION 'option' RC=24
DMSCMP005E NO COLUMN SPECIFIED RC=24
DMSCMP009E COLUMN 'col' EXCEEDS RECORD LENGTH RC=24
DMSCMP010E PREMATURE EOF ON FILE 'fn ft fm' RC=40
DMSCMP011E CONFLICTING FILE FORMATS RC=32
DMSCMP019E IDENTICAL FILEIDS RC=24
DMSCMP029E INVALID PARAMETER 'parameter' IN THE OPTION 'COL' FIELD
RC=24
DMSCMP054E INCOMPLETE FILEID SPECIFIED RC=24
DMSCMP062E INVALID * IN FILEID RC=20
DMSCMP104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSCMP209W FILES DO NOT COMPARE RC=4

COPYFILE

Options:

TYPE displays, at the terminal, the names of the files being copied.

NOTYPE suppresses the display of the names of the files being copied.

NEWDATE uses the current date as the creation date of the new file(s).

OLDDATE uses the date on the first input file as the creation date of the new file(s).

NEWFILE checks that files with the same fileid as the output file do not already exist. If one or more output files do exist, an error message is displayed and the COPYFILE command terminates. This option is the default so that existing files are not inadvertently destroyed.

REPLACE causes the output file to replace an existing file with the same file identifier. REPLACE is the default option when only one fileid is entered or when the output fileid is specified as " = = ."

PROMPT displays the messages which request specification or translation lists.

NOPROMPT suppresses the display of prompting messages for specification and translation lists.

COPY Extent Options:

FROM recno is the starting record number for each input file in the copy operation.

FRLABEL xxxxxxxx

xxxxxxx is a character string which appears at the beginning of the first record to be copied from each input file. Up to 8 nonblank characters may be specified.

FOR numrec is the number of records to be copied from each input file.

TOLABEL xxxxxxxx

xxxxxxx is a character string which, if at the beginning of a record, stops the copy operation for that input file. The record containing the given character is not copied. Up to 8 nonblank characters may be specified.

SPECS indicates that you are going to enter a specification list to define how records should be copied. See "Entering a COPYFILE Specification List" for information on how you can define output records in a specification list.

NOSPECS indicates that no specification list is to be entered.

OVLY overlays the data in an existing output file with data from the input file. You can use OVLY in conjunction with the SPECS option to overlay data in particular columns.

APPEND appends the data from the input file at the end of the output file.

| Data Modification Options: The following options can be used to
| change the record format of a file. See "Modifying Record Formats"
| for more details.

RECFM { F } is the record format of the output files. If not
 { V } specified, the output record format is the same as that
 of the input file.

| LRECL nnnnn is the logical record length of the output file(s) if it
 is to be different from that of the input file(s). The
 maximum value of nnnnn is 65535.

TRUNC removes trailing blanks (or fill characters) when
 converting fixed-length files to variable-length format.

NOTRUNC suppresses the removal of trailing blanks (or fill
 characters) when converting fixed-length files to
 variable-length format.

PACK compresses records in a file, so that they can be stored
 in packed format.

Caution: A file in packed format should not be modified
 in any way. If such a file is modified, the UNPACK
 routines are unable to reconstruct the original file.

| UNPACK reverses the PACK operation. If a file is inadvertently
| packed twice, you can restore the file to its original
| unpacked form by issuing the COPYFILE command twice.

FILL c is the padding and truncation character for the TRUNC
FILL hh option or the principal packing character for the PACK
FILL 40 option. The fill character may be specified as a single
 character, c, or by entering a 2-digit hexadecimal
 representation of a character. The default is 40 (the
 hexadecimal representation for a blank in EBCDIC).

Character Translation Options:

EBCDIC converts a file that was created with 026 keypunch
 characters (BCD), to 029 keypunch characters (EBCDIC).
 The following conversions are made:

```

{ to )
& to +
% to (
# to =
@ to '
' to :
```

UPCASE converts all lowercase characters in each record to
 uppercase before writing the record to the output file.

LOWCASE converts all uppercase characters in each record to
 lowercase before writing the record to the output file.

TRANS indicates that you are going to enter a list of character
 translations to be made as the file is copied. See
 "Entering Translation Specifications" for details on
 entering a list of characters to be translated.

COPYFILE

Incompatible Options

Figure 4 shows combinations of options which should not be specified together in the same COPYFILE command. If the option in the first column is specified, none of the options in the second column can be coded.

Option	Incompatible Options
APPEND	LRECL, NEWDATE, NEWFILE, OLDDATE, OVLY, PACK, RECFM, REPLACE, UNPACK
EBCDIC	PACK, UNPACK
FOR	PACK, TOLABEL, UNPACK
FRLABEL	FROM, PACK, UNPACK
FROM	FRLABEL, PACK, UNPACK
LOWCASE	PACK, UNPACK
LRECL	APPEND, PACK, UNPACK
NEWDATE	APPEND, OLDDATE
NEWFILE	APPEND, OVLY, REPLACE
NOPROMPT	PROMPT
NOSPECS	PACK, SPECS, UNPACK
NOTRUNC	PACK, TRUNC, UNPACK
NOTYPE	TYPE
OLDDATE	APPEND, NEWDATE
OVLY	APPEND, NEWFILE, PACK, REPLACE, UNPACK
PACK	APPEND, EBCDIC, FOR, FRLABEL, FROM, LOWCASE, LRECL, OVLY, RECFM, SPECS, TOLABEL, TRANS, TRUNC, UNPACK, UPCASE
PROMPT	NOPROMPT
RECFM	APPEND, PACK, UNPACK
REPLACE	APPEND, NEWFILE, OVLY
SPECS	NOSPECS, PACK, UNPACK
TOLABEL	FOR, PACK, UNPACK
TRANS	PACK, UNPACK
TRUNC	NOTRUNC, PACK, UNPACK
TYPE	NOTYPE
UNPACK	APPEND, EBCDIC, FOR, FRLABEL, FROM, LOWCASE, LRECL, OVLY, PACK, RECFM, SPECS, TOLABEL, TRANS, TRUNC, UPCASE
UPCASE	PACK, UNPACK

Figure 4. COPYFILE Option Incompatibilities

| *Using the COPYFILE Command*

| The simplest use of the COPYFILE command is for copying a single CMS file from one disk to another, or making a duplicate copy of the file on the same disk. For example,

```
|      copyfile test1 assemble a test2 assemble a
```

| makes a copy of the file TEST1 ASSEMBLE A and names it TEST2 ASSEMBLE A. For those portions of the file identifier that you want to stay the same, you may code an equal sign in the output fileid. Thus, the command line above can be entered:

```
|      copyfile test1 assemble a test2 = =
```

| When you copy a file from one virtual disk to another, you specify the old and new filemodes, and any filename or filetype change you want

| to make, for example,

```
|      copyfile test3 assemble c good = a
```

| This command makes a copy of the file TEST3 ASSEMBLE C, and names it
| GOOD ASSEMBLE A.

| If you want to copy only particular records in a file, you can use
| the FROM/FOR FRLABEL/TOLABEL options. For example,

```
|      copyfile old test a new test a (frlabel start for 41
```

| copies 41 records from the file OLD TEST A1, beginning with the record
| beginning with the character string START into the file NEW TEST A1.

| Multiple Input and Output Files

| You can combine two or more files into a single file with the COPYFILE
| command. For example,

```
|      copyfile test data1 a test data2 = test data3 b
```

| copies the files TEST DATA1 and TEST DATA2 from your A-disk and combines
| them into a file, TEST DATA3, on your B-disk.

| If you want to combine two more files without creating a new file,
| use the APPEND option. For example,

```
|      copyfile new list a old list a (append
```

| appends the file NEW LIST A to the bottom of the existing file OLD LIST
| A.

| Whenever you code an asterisk (*) in an input fileid, you may cause
| one or more files to be copied, depending on the number of files that
| satisfy the remaining conditions. For example,

```
|      copyfile * test a combined test a
```

| copies all files with a filetype of TEST on your A-disk into a single
| file named COMBINED TEST. If only one file with a filetype of TEST
| exists, only that file is copied.

| If you want to copy all the files on a particular disk to another
| disk, you could enter

```
|      copyfile * * b = = a
```

| All the files on the B-disk are copied to the A-disk. The filenames and
| filetypes remain unchanged.

| You can also copy a group of files and change all the filenames or
| all the filetypes. For example,

```
|      copyfile * assemble b = test a
```

| copies all ASSEMBLE files in the B-disk into files with a filetype of
| TEST on the A-disk. The filenames are not changed.

| Whenever an asterisk appears it indicates "all;" whenever an equal
| sign appears, it indicates "the same." For example

```
|      copyfile x * a1 = file =
```

COPYFILE

| combines all files with a filename of X on the A-disk into a single file
| named X FILE A1.

| Whenever an equal sign appears in the output fileid in a position
| corresponding to an asterisk in an input fileid, multiple input files
| produce multiple output files. When you perform copy operations of this
| nature you might wish to use the TYPE option, which displays the names
| of files being copied. For example,

```
| copyfile * test a = output a = summary = (type
```

| might result in the display

```
| COPY 'ALPHA TEST A1' TO 'ALPHA SUMMARY A1' (NEW FILE)
```

```
| COPY 'ALPHA OUTPUT A'
```

```
| COPY 'BETA TEST A1' TO 'BETA SUMMARY A1' (NEW FILE)
```

```
| COPY 'BETA OUTPUT A.'
```

| which indicates that files ALPHA TEST A and ALPHA OUTPUT A were copied
| into a file named ALPHA SUMMARY A and that files BETA TEST A and BETA
| OUTPUT A were copied into a file named BETA SUMMARY A.

| Modifying Record Formats

| You can use the RECFM and LRECL options to change the record format of a
| file as you copy it. For example,

```
| copyfile data file a (recfm f lrecl 130
```

| converts the file DATA FILE A1 to fixed-length 130-character records.
| If you specify an output fileid, for example,

```
| copyfile data file a fixdata file a (recfm f lrecl 130
```

| the original file remains unchanged. The file FIXDATA FILE A contains
| the converted records.

| If the records in a file being copied are variable-length, each
| output record is padded with blanks to the specified record length. If
| any records are longer than the record length, they are truncated.

| When you convert files from fixed-length records to variable-length
| records, you can specify the TRUNC option to ensure that all trailing
| blanks are truncated:

```
| copyfile data file a (recfm v trunc
```

| If you specify the LRECL option and RECFM V, the LRECL option is
| ignored; the output record length is taken from the longest record in
| the input file.

| When you convert a file from variable-length to fixed-length records,
| you may also specify a fill character to be used for padding instead of
| a blank. If you specify

```
| copyfile short recs a (recfm f fill *
```

| then each record in the file SHORT RECS is padded with asterisks to the
| record length. Assuming that SHORT RECS was originally a
| variable-length file, the record length is taken from the longest
| existing record. Note that if SHORT RECS is already fixed-length, it is
| not altered.

| Similarly, when you are converting back to variable-length a file
| that was padded with a character other than a blank, you must specify
| the FILL option to indicate the pad character, so that character is
| truncated.

| The FILL option can also be used to specify the packing character
| used with the PACK option. When you use the PACK option, a file is
| compressed as follows: all occurrences of two or more blanks are
| encoded as 1 character, and 4 or more occurrences of any other character
| are written as 3 characters. If you use the FILL option to specify a
| fill character, then that character is treated as a blank when records
| are compressed. You must, of course, specify the FILL option to unpack
| any files packed in this way. Since most fixed-length files are
| blank-padded to the record length, you do not need to specify the FILL
| option unless you know that some other character appears more
| frequently.

| When you convert record formats on packed files with the COPYFILE
| command you can specify single or multiple output files, in accordance
| with the procedures outlined under "Modifying Record Formats." For
| example,

```
| copyfile * assemble a (pack
```

| compresses all ASSEMBLE files in the A-disk without changing any file
| identifiers. The command

```
| copyfile * assemble a = script = (recfm trunc
```

| converts all ASSEMBLE files to variable-length, and changes their
| filetypes to SCRIPT.

| Entering a COPYFILE Specification List

| When you use the COPYFILE command, you can specify particular columns of
| data to be manipulated or particular characters to be translated.
| Again, how you specify the file identifier determines how many files are
| copied or modified.

| When you use the SPECS option on the COPYFILE command, you receive
| the message:

```
| DMSCPY601R ENTER SPECIFICATION LIST:
```

| and a read is presented to your virtual machine and you may enter a
| specification list. If you do not wish to receive this message, use the
| NOPROMPT option. The specification list you enter may consist of one or
| more pairs of operands in the following format:

```
| { nn-mm } col  
| { /string/ }  
| { hxx... }
```

| where:

| nn-mm specifies the start and end columns of the input file that are to
| be copied to the output file. If mm exceeds the length of the
| input record, the end of the record is the assumed ending
| position.

| string is any string of uppercase and lowercase characters or numbers
| delimited by any non-alphameric character.

COPYFILE

| hxx... is an even number of hexadecimal digits prefixed with an h.
| col is the column in the output file at which the copy operation is
| to begin.

| You can enter as many pairs of specifications as you wish. If you
| want to enter more than one line of specifications, enter the characters
| ++ as continuation indicators.

| A specification list may contain any combination of specification
| pairs, for example:

```
| copyfile sorted list a (specs  
| DMSCPY601R ENTER SPECIFICATION LIST:  
| /|/ 1 1-8 3 /|/ 12 .***. 14 ++  
| 9-80 18
```

| After this command is executed, each record in the file SORTED LIST
| will look like the following:

```
| | ooooooooo | *** oooo....
```

| where the o's in columns 3 through 10 indicate information originally in
| columns 1 through 8; the o's following the asterisks indicate the
| remainder of each record, columns 9 through 80.

| When you enter a specification list, you are actually constructing a
| file column by column. If you specify multiple input or output files,
| the same copy operation is performed for each record in each output
| file.

| Those columns for which you do not specify any data are filled with
| blanks or, if you use the FILL option, the fill character of your
| choice. For example,

```
| copyfile sorted list a (specs noprompt lrecl 20 fill $  
| 1-15 6
```

| copies columns 1 through 15 beginning in column 6 and writes dollar
| signs(\$) in columns 1 through 5.

| If you do want to modify data in particular columns of a file but
| want to leave all of the rest of each record unchanged, you can use the
| OVLY (overlay) option. For example, the sequence

```
| COPYFILE * bracket a (specs ovly noprompt  
| had 1 hbd 80
```

| overlays the characters [(X'AD) and] (X'BD') in columns 1 and 80 of
| all the files with a filetype of BRACKET on your A-disk.

| When you copy fixed-length files, records are padded or truncated to
| the record length; variable-length files are always written as
| specified.

| Entering Translation Specifications

| You can perform conversion on particular characters in CMS files or
| groups of files with the TRANS option of the COPYFILE command.

| When you enter the TRANS option, you receive the message

```
| DMSCPY602R ENTER TRANSLATION LIST:
```


| and a read is presented to your virtual machine. You may enter the
| translation list. If you do not wish to receive this message, use the
| NOPROMPT option.

| A translation list consists of one or more pairs of characters or hex
| digits, each pair representing the character you want to translate and
| the character you want to translate it to, respectively. For example,

```
|      copy test file a (trans
|      DMSCPY602R ENTER TRANLATION LIST:
|      * - A f0 00 ff
```

| specifies that all occurrences of the character * are to be translated
| to -, all character A's are to be translated to X'F0' and all X'00's are
| to be translated to X'FF's.

| If any translation specifications you enter conflict with the
| LOWCASE, EBCDIC, or UPCASE options specified on the same command line,
| the translation list takes precedence. In the preceding example, if
| LOWCASE had also been specified, all A's would be translated to X'F0's,
| not to a's.

| You can enter translation pairs on more than one line if you enter a
| ++ as a continuation indicator.

Responses

DMSCPY601R ENTER SPECIFICATION LIST:

This message prompts you to enter a specification list when you use
the SPECS option.

DMSCPY602R ENTER TRANSLATION LIST:

This message prompts you to enter a translation list when you use
the TRANS option.

DMSCPY721I COPY 'fn ft fm' [TO |APPEND| OVLY] 'fn ft fm' [OLD|NEW] FILE

This message appears for each file copied with the TYPE option. It
indicates the names of the input file and output file. When you
have multiple input files, the output fileid is displayed only
once.

Other Messages and Return Codes

```
DMSCPY002E {INPUT|OVERLAY} FILE 'fn ft fm' NOT FOUND RC=28
DMSCPY003E INVALID OPTION 'option' RC=24
DMSCPY024E FILE 'fn ft fm' ALREADY EXISTS -- SPECIFY 'REPLACE' RC=28
DMSCPY029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD
RC=24
DMSCPY030E FILE 'fn ft fm' ALREADY ACTIVE RC=28
DMSCPY037E DISK 'mode' IS READ/ONLY RC=36
DMSCPY042E NO FILEID(S) SPECIFIED RC=24
DMSCPY048E INVALID MODE 'mode' RC=24
DMSCPY054E INCOMPLETE FILEID 'fn [ft'] SPECIFIED RC=24
DMSCPY062E INVALID CHAR '[=*|char]' IN FILEID '[fn ft fm]' RC=20
DMSCPY063E NO {TRANSLATION|SPECIFICATION} LIST ENTERED RC=40
DMSCPY064E INVALID [TRANSLATE] SPECIFICATION AT OR NEAR '.....'
RC=24
```

COPYFILE

DMSCPY065E 'option' OPTION SPECIFIED TWICE RC=24
DMSCPY066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
DMSCPY067E COMBINED INPUT FILES ILLEGAL WITH PACK OR UNPACK OPTIONS
RC=24
DMSCPY068E INPUT FILE 'fn ft fm' NOT IN PACKED FORMAT RC=32
DMSCPY101S 'SPECS' TEMP STRING STORAGE EXHAUSTED AT '.....' RC=88
DMSCPY102S TOO MANY FILEIDS RC=88
DMSCPY103S NUMBER OF SPECS EXCEEDS MAX 20 RC=88
DMSCPY156E 'FROM nnn' NOT FOUND --FILE 'fn ft fm' HAS ONLY 'nnn' RECORDS
RC=32
DMSCPY157E LABEL 'label' NOT FOUND IN FILE 'fn ft fm' RC=32
DMSCPY172E TO LABEL 'label' {EQUALS| IS AN INITIAL SUBSTRING OF} FRLABEL
'label' RC=24
DMSCPY173E NO RECORDS WERE COPIED TO OUTPUT FILE 'fn ft fm' RC=40
DMSCPY901T UNEXPECTED ERROR AT 'addr': PLIST 'plist' AT 'addr', BASE
'addr', RC 'nn' RC=256
DMSCPY903T IMPOSSIBLE PHASE CODE 'xx' RC=256
DMSCPY904T UNEXPECTED UNPACK ERROR AT 'addr', BASE 'addr' RC=256

CP

Use the CP command to transmit commands to the VM/370 control program environment without leaving the CMS environment. The format of the CP command is:

```
CP | [ commandline ]
```

where:

commandline is any CP command valid for your CP command privilege class. If this field is omitted, you are placed in the CP environment and may enter CP commands without preceding each command with CP. To return to CMS, issue the CP command BEGIN.

Usage Notes

1. You must use the CP command to invoke a CP command:
 - Within an EXEC procedure.
 - If the implied CP (IMPCP) function is set to OFF for your virtual machine.
 - In a job you send to the CMS Batch Facility.
2. To enter a CP command from the CMS environment without CMS processing the command line, use the #CP function.
3. When you enter an invalid CP command following the CP command, you receive a return code of -1. In an EXEC, this return code is +1.

Responses

All responses are from the CP command that was issued, and are followed by the CMS Ready message.

DDR

DDR

Use the DASD Dump Restore (DDR) program to dump, restore, copy, or print VM/370 user minidisks. The DDR program may run as a standalone program, or under CMS via the DDR command.

The DDR program has five functions:

1. Dumps part or all of the data from a DASD device to tape.
2. Transfers data from tapes created by the DDR dump function to a direct access device. The direct access device must be the same as that which originally contained the data.
3. Copies data from one device to another of the same type. Data may be reordered, by cylinder, when copied from disk to disk. In order to copy one tape to another, the original tape must have been created by the DDR DUMP function.
4. Prints selected parts of DASD and tape records in hexadecimal and EBCDIC on the virtual printer.
5. Displays selected parts of DASD and tape records in hexadecimal and EBCDIC on the terminal.

The format of the DDR command is:

```
DDR      | [fn ft [fm] ]  
         | [* ]  
         | [ ]
```

where:

fn ft [fm] is the identification of the file containing the control statements for the DDR program. If no file identification is provided, the DDR program attempts to obtain control statements from the console. The filemode defaults to * if a value is not provided.

Note: If you use the CMS DDR command, CMS ignores the SYSPRINT control statement and directs the output to the CMS printer 00E.

| Note: Be aware that DDR when run as a standalone program does not have error recovery support. However, when DDR is invoked in CMS, in a virtual machine environment, the I/O operation is performed by CP (CP has built-in error recovery facilities).

DDR Control Statements

DDR control statements describe the intended processing and the needed I/O devices. I/O definition statements must be specified first.

All control statements may be entered from either the console or the card reader. Only columns 1 to 71 are inspected by the program. All data after the last operand in a statement is ignored. An output tape must have the DASD cylinder header records in ascending sequences; therefore, the extents must be entered in sequence by cylinder. Only

one type of function — dump, restore, or copy — may be performed in one execution, but up to 20 statements describing cylinder extents may be entered. The function statements are delimited by an INPUT or OUTPUT statement, or by a null line if the console is used for input. If additional functions are to be performed, the sequence of control cards must be repeated. If you do not use INPUT or OUTPUT control statements to separate the functions you specify when the input is read from a card reader or CMS file, an error message (DMKDDR702E) is displayed. However, the remainder of the input stream will be checked for proper syntax, but no further DDR operations will be performed. Only those statements needed to redefine the I/O devices are necessary for subsequent steps. All other I/O definitions remain the same.

To return to CMS, enter a null line (carriage return) in response to the prompting message (ENTER:). To return directly to CP, key in #CP.

The PRINT and TYPE statements work differently from other DDR control statements in that they operate on only one data extent at a time. If the input is from a tape created by the dump function, it must be positioned at the header record for each step. The PRINT and TYPE statements have an implied output of either the console (TYPE) or system printer (PRINT). Therefore, PRINT and TYPE statements need not be delimited by an INPUT or OUTPUT statement.

I/O Definition Statements

The I/O definition statements describe the tape, DASD, and printer devices used while executing the DASD Dump Restore program.

INPUT/OUTPUT Control Statement

An INPUT or OUTPUT statement describes each tape and DASD unit used. The format of the INPUT/OUTPUT statement is:

```

Input  | cuu type [volser] [(options...)]
Output |      [altape]
       |      [
       |      Options:
       |      [SKip nn] [Mode 6250] [REWind]
       |      [SKip 0]  [Mode 1600] [UNload]
       |      [          ] [Mode 800] [LEave]
       |      [          ] [          ] [          ]

```

where:

INPUT indicates that the device described is an input device.

OUTPUT indicates that the device described is an output device.

cuu is the unit address of the device.

type is the device type (2314, 2319, 3330, 3330-11, 3340-35, 3340-70, 3350, 2305-1, 2305-2, 2400, 2420, or 3420) (no

7-track support for any tape devices). Specify a 3410 device as a 3420, a 3340-70F as a 3340-70, and a 3333 as a 3330. Specify a 3350 that is in 3330-1 or 3330-11 compatibility mode as a 3330 or 3330-11. Specify a 3344 as a 3340-70, and specify 3350 for a 3350 operating in native mode (as opposed to compatibility mode).

Note: The DASD Dump Restore (DDR) program, executing in a virtual machine, uses I/O DIAGNOSE 20 to perform I/O operations on tape and DASD devices. DDR under CMS requires that the device type entered agree with the device type of the real device as recognized by VM/370. If there is a conflict with device types, the following message is issued:

DMKDDR708E INVALID OPTION

However, if DDR executes standalone in a virtual machine, DDR uses DIAGNOSE 20 to perform the I/O operation if the device types agree. If the device types do not agree, error message DMKDDR708E is issued.

volser is the volume serial number of a DASD device. If the keyword "SCRATCH" is specified instead of the volume serial number, no label verification is performed.

altape is the address of an alternate tape drive.

Note: If multiple reels of tape are required and "altape" is not specified, DDR types the following at the end of the reel:

END OF VOLUME CYL xxx HD xxx, MOUNT NEXT TAPE

After the new tape is mounted, DDR continues automatically.

Options:

SKIP nn forward spaces nn files on the tape. nn is any number up to 255. The SKIP option is reset to zero after the tape has been positioned.

MODE [6250] causes all output tapes that are opened for the first [1600] time and at the load point to be written or read in [800] the specified density. All subsequent tapes mounted are also set to the specified density. If no mode option is specified, then no mode set is performed and the density setting remains as it previously was.

REWIND rewinds the tape at the end of a function.

UNLOAD rewinds and unloads the tape at the end of a function.

LEAVE leaves the tape positioned at the end of the file at the end of a function.

Note: When the wrong input tape is mounted, the message DMKDDR709E is displayed and the tape will rewind and unload regardless of options REWIND, UNLOAD, or LEAVE being specified.

SYSPRINT Control Statement

Use the SYSPRINT control statement (in the standalone DDR virtual machine only) to describe the printer that is to print data extents specified by the PRINT statement. It also can print a map of the

cylinder extents from the DUMP, RESTORE, or COPY statement. If the SYSPRINT statement is not provided, the printer assignment defaults to 00E. CMS ignores the SYSPRINT statement when you invoke DDR as a command under CMS, and CMS always directs the output to 00E. The format of the SYSPRINT control statement is:

```

SYSprint | cuu

```

where:

cuu specifies the unit address of the device.

Function Statements

The function statements tell the DDR program what action to perform. The function commands also describe the extents to be dumped, copied, or restored. The format of the DUMP/COPY/RESTORE control statement is:

```

Dump      | [ cyl1 [To] [cyl2 [Reorder] [To] [cyl3]] ]
Copy      | [ CPvol ]
REstore   | [ ALL ]
           | [ NUCleus ]

```

where:

DUMP requests the program to move data from a direct access volume onto a magnetic tape or tapes. The data is moved cylinder by cylinder. Any number of cylinders may be moved. The format of the resulting tape is:

Record 1: a volume header record, consisting of data describing the volumes.

Record 2: a track header record, consisting of a list of count fields to restore the track, and the number of data records written on tape. After the last count field the record contains key and data records to fill the 4K buffer.

Record 3: track data records, consisting of key and data records packed into 4K blocks, with the last record truncated.

Record 4: either the end-of-volume (EOV) or end-of-job (EOJ) trailer label. The end-of-volume label contains the same information as the next volume header record, except that the ID field contains EOV. The end-of-job trailer label contains the same information as record 1 except that the cylinder number field contains the disk address of the last record on tape and the ID field contains EOJ.

COPY requests the program to copy data from one device to another device of the same or equivalent type. Data may be recorded on a cylinder basis from input device to output device. A tape-to-tape copy can be accomplished only with data dumped by this program.

RESTORE requests the program to return data that has been dumped by this program. Data can be restored only to a DASD volume of

DDR

the same or equivalent device type from which it was dumped. It is possible to dump from a real disk and restore to a minidisk as long as the device types are the same.

cyl1 [TO] [cyl2 [REORDER] [TO] [cyl3]]

Only those cylinders specified are moved, starting with the first track of the first cylinder (cyl1), and ending with the last track of the second cylinder (cyl2). The REORDER operand causes the output to be reordered, that is, moved to different cylinders, starting at the specified cylinder (cyl3) or at the starting cylinder (cyl1) if "cyl3" is not specified. The REORDER operand must not be specified unless specified limits are defined for the operation; the starting and, if required, ending cylinders (cyl1 and cyl2) must be specified.

CPVOL specifies that cylinder 0 and all active directory and permanent disk space are to be copied, dumped, or restored. This indicates that both source and target disk must be in CP format, that is, the CP Format/Allocate program must have formatted them.

ALL specifies that the operation is to be performed on all cylinders.

NUCLEUS specifies that record 2 on cylinder 0, track 0 and the nucleus cylinders are dumped, copied, or restored.

Restrictions:

- Each track must contain a valid home address, containing the real cylinder and track location.
- Record zero must not contain more than eight key and/or data characters.
- Flagged tracks are treated just as any other track for all 2314, 2319, 3340, and 2305 devices. That is, no attempt is made to substitute the alternate track data when a defective primary track is read. In addition, tracks are not inspected to determine whether they were previously flagged when written. Therefore, volumes containing flagged tracks should be restored to the same cylinders of the volume from which they were dumped. The message DMKDDR715E occurs each time a defective track is dumped, copied or restored, and the operation continues.
- Flagged tracks for 3330 and 3350 devices are handled automatically by the control unit and may never be detected by the program. The program may detect a flagged track if, for example, no alternate track is assigned to the defective primary track. If a flagged track is detected by the program, the message DMKDDR715E occurs and the operation terminates.

Example:

```

INPUT 191 3330 SYSRES
OUTPUT 180 2400 181 (MODE 800
SYSPRINT 00F
DUMP CPVOL
INPUT 130 3330 MINI01
DUMP 1 TO 50 REORDER 51
60 70 101

```

This example sets the density to 800 bpi, then dumps all pertinent data from the volume labeled SYSRES onto the tape that is mounted on unit 180. If the program runs out of space on the first tape, it continues dumping onto the alternate device (181). A map of the dumped cylinders is printed on unit 00F while the program is dumping. When the first function is complete, the volume labeled MINI01 is dumped onto a new tape. Its cylinder header records are labeled 51 to 100. A map of the dumped cylinders is printed on unit 00F. Next, cylinders 60 to 70 are dumped and labeled 101 to 111. This extent is added to the cylinder map on unit 00F. When the DDR processing is complete, the tapes are unloaded and the program stops.

If cylinder extents are being defined from the console, the following is displayed:

```

ENTER CYLINDER EXTENTS
ENTER:

```

For any extent after the first extent, the message

```

ENTER NEXT EXTENT OR NULL LINE
ENTER:

```

is displayed.

You may then enter additional extents to be dumped, restored, or copied. A null line causes the job step to start.

| Note: When a cylinder map is printed on the virtual printer (00F as in
| the previous example) a heading precedes the map information. Module
| DMKDDR controls the disk, time and zone printed in the heading. Your
| installation must apply a local modification to DMKDDR to insure that
| local time, rather than GMT (Greenwich Meridian Time), is printed in the
| heading.

PRINT/TYPE Function Statement

Use the PRINT and TYPE function statement to print or type (display) a hexadecimal and EBCDIC translation of each record specified. The input device must be defined as direct access or tape. The output is directed to the system console for the TYPE function, or to the SYSPRINT device for the PRINT function. (This does not cause redefinition of the output unit definition.) The format of the PRINT/TYPE control statement is:

```

| Print      | cyl1 [hh1 [rr1]] [To cyl2 [hh2 [rr2 ]]] [(options...[ ])] |
| Type      | |
|           |           options:
|           |           [Hex] [Graphic] [Count]
|

```

DDR

where:

cyl1 is the starting cylinder.

hh1 is the starting track. If present, it must follow the cyl1 operand. The default is track zero.

rr1 is the starting record. If present, it must follow the hh1 operand. The default is home address and record zero.

TO cyl2 is the ending cylinder. If more than one cylinder is to be printed or typed "TO cyl2" must be specified.

hh2 is the ending track. If present, it must follow the cyl2 operand. The default is the last track on the ending cylinder.

rr2 is the record ID of the last record to print. The default is the last record on the ending track.

Options:

HEX prints or displays a hexadecimal representation of each record specified.

GRAPHIC prints or displays an EBCDIC translation of each record specified.

COUNT prints or displays only the count field for each record specified.

Examples:

PRINT 0 TO 3

Prints all of the records from cylinders 0, 1, 2, and 3.

PRINT 0 1 3

Prints only one record, from cylinder 0, track 1, record 3.

PRINT 1 10 3 TO 1 15 4

Prints all records starting with cylinder 1, track 10, record 3, and ending with cylinder 1, track 15, record 4.

The example in Figure 5 shows the information displayed at the console (TYPE function) or system printer (PRINT function) by the DDR program. The listing is annotated to describe some of the data fields.

Responses

DMKDDR711R VOLID READ IS volid2 [NOT volid1]
DO YOU WISH TO CONTINUE? RESPOND YES NO OR REREAD:




Figure 5. An Annotated Sample of Output from the TYPE and PRINT Functions of the DDR Program

DDR

where:

volid2 is the volume serial number from the VOL1 label on the DASD unit.

volid1 is the volume serial number from the INPUT or OUTPUT control card.

The volume serial number read from the device at cuu is not the same as that specified on the INPUT or OUTPUT control card.

DMKDDR716R NO VOL1 LABEL FOUND FOR volser
DO YOU WISH TO CONTINUE? RESPOND YES NO OR REREAD:

where:

volser is the volume serial number of the DASD device from the INPUT or the OUTPUT control card.

The DASD device at cuu contains no volume serial number.

DMKDDR717R DATA DUMPED FROM volid1 TO BE RESTORED TO volid2
DO YOU WISH TO CONTINUE? RESPOND YES NO OR REREAD:

where:

volid1 is the volume serial number from the input tape header record (volume dumped).

volid2 is the volume serial number from the output DASD device.

The above message is printed to verify the input parameters.

ENTER CYLINDER EXTENTS
ENTER:

This message is received only if you are entering input from your terminal.

END OF VOLUME CYL xxx HD xx, MOUNT NEXT TAPE

DDR continues processing, after the mounting of the next tape reel.

| RESTORING volser

where:

volser is the volume serial number of the disk dumped.

The RESTORE operation has begun.

COPYING volser

where:

volser is the volume serial number described by the input unit.

The COPY operation has begun.

DUMPING volser

where:

volser is the volume serial number described by the input unit.
The DUMP operation has begun.

PRINTING volser

where:

volser is the volume serial number described by the input unit.
The PRINT operation has begun.

END OF DUMP

The DUMP operation has ended.

END OF RESTORE

The RESTORE operation has ended.

END OF COPY

The COPY operation has ended.

END OF PRINT

The PRINT operation has ended.

END OF JOB

All specified operations have completed.

ENTER:

Prompts input from the terminal. A null line (that is, pressing the Enter key or equivalent) causes control to return to CMS, if the virtual machine is in the CMS environment.

DMKDDR725R ORIGINAL INPUT DEVICE WAS (IS) LARGER THAN OUTPUT DEVICE.
DO YOU WISH TO CONTINUE? RESPONSE YES OR NO:

Explanation:

RESTORE function - The number of cylinders on the original DASD input unit is compared with the number of cylinders on the output device.

COPY function - The input device contains more cylinders than the output device.

Operator Action: The operator must determine if the COPY or RESTORE function is to continue. The response is either yes or no.

DDR

| Other Messages and Return Codes

| Note: There is no return code returned for the following messages,
| unless otherwise noted.

| DMKDDR700E INPUT UNIT IS NOT A CPVOL
| DMKDDR701E INVALID OPERAND - operand
| DMKDDR702E CONTROL STATEMENT SEQUENCE ERROR
| DMKDDR703E OPERAND MISSING
| DMKDDR704E DEV cuu NOT OPERATIONAL
| DMKDDR705E IO ERROR cuu CSW csw SENSE sense INPUT bbcchh OUTPUT bbcchh
| CCW ccw
| DMKDDR707E MACHINE CHECK RUN SEREP AND SAVE OUTPUT FOR CE
| DMKDDR708E INVALID INPUT OR OUTPUT DEFINITION
| DMKDDR709E WRONG INPUT TAPE MOUNTED
| DMKDDR710A DEV cuu INTERVENTION REQUIRED
| DMKDDR712E NUMBER OF EXTENTS EXCEEDS 20
| DMKDDR713E OVERLAPPING OR INVALID EXTENTS
| DMKDDR714E RECORD bbcchh NOT FOUND ON TAPE
| DMKDDR715E LOCATION bbcchh IS A FLAGGED TRACK RC=3
| DMKDDR718E OUTPUT UNIT IS FILE PROTECTED RC=1
| DMKDDR719E INVALID FILENAME OR FILE NOT FOUND
| DMKDDR720E ERROR IN routine RC=varies
| DMKDDR721E RECORD cchhr NOT FOUND
| DMKDDR722E OUTPUT UNIT NOT PROPERLY FORMATTED FOR THE CP NUCLEUS
| DMKDDR723E NO VALID CP NUCLEUS ON THE INPUT UNIT
| DMKDDR724E INPUT TAPE CONTAINS A CP NUCLEUS DUMP
| DMKDDR756E PROGRAM CHECK PSW=psw

DEBUG

Use the DEBUG command to enter the debug environment from the CMS environment. In the debug environment you can use a variety of DEBUG subcommands that allow you to test and debug your programs. The DEBUG subcommands are described in "Section 4. DEBUG Subcommands." For tutorial information, including examples, see the VM/370: CMS User's Guide. The format of the DEBUG subcommand is:

```
DEBUG |
```

Usage Notes

1. The debug environment is also entered as a result of an external interrupt or the result of a breakpoint (address stop) encountered during program execution.
2. Once you are in the debug environment, you can enter only DEBUG subcommands and CP commands via the #CP function.
3. To return to the CMS environment, enter the DEBUG subcommand RETURN.

Responses

```
DMSDBG728I DEBUG ENTERED
```

This message indicates that you are in the debug environment.

DISK

DISK

Use the DISK command to:

- Punch CMS disk files to the virtual spooled card punch in a special format which allows the punched deck to be restored to disk in the form of the original disk file.
- Restore punched decks created by the DISK DUMP command to a disk file.

The format of the DISK command is:

```
DISK | { DUMP  fn ft [fm]  }  
      | { LOAD
```

where:

DUMP fn ft fm

punches the specified file (fn ft fm). The file may have either fixed- or variable-length records. After all data is punched, an end-of-file card is created with an N in column 5. This card contains directory information, and must remain in the deck. The original disk file is retained.

LOAD

loads a file or files from the spooled card reader and writes them as CMS files on your A-disk. The filename and filetype are obtained from the card stream. If a file exists with the same filename and filetype as one of those in the card stream, it is replaced.

Usage Notes

1. To read files with the DISK LOAD command, they must have been created by the DISK DUMP command. To load spooled reader files created in any other manner, you should use the READCARD command.
2. To load reader files created by DISK DUMP, you must issue the DISK LOAD command for each spool file. For example, if you enter

```
disk dump source1 assemble  
disk dump source2 assemble
```

the virtual machine that receives the files must issue the DISK LOAD command twice to read the files onto disk. If you use the CP SPOOL command to spool continuous, for example,

```
cp spool punch cont  
disk dump source1 assemble  
disk dump source2 assemble  
cp spool punch nocont close
```

then you only need to issue the DISK LOAD command once to read both files.

Responses

There is no response to the DISK DUMP command. The file identifiers of each file loaded are displayed when you issue the DISK LOAD command:


```
fn ft fm
. . .
. . .
. . .
```

Other Messages and Return Codes

```
DMSDSK002E FILE 'fn ft fm' NOT FOUND RC=28
DMSDSK014E INVALID FUNCTION 'function' RC=24
DMSDSK037E DISK 'A' IS READ/ONLY RC=36
DMSDSK047E NO FUNCTION SPECIFIED RC=24
DMSDSK048E INVALID MODE 'mode' RC=24
DMSDSK054E INCOMPLETE FILEID SPECIFIED RC=24
DMSDSK062E INVALID * IN FILEID ['fn ft fm'] RC=20
DMSDSK070E INVALID PARAMETER 'parameter' RC=24
DMSDSK077E END CARD MISSING FROM INPUT DECK RC=32
DMSDSK078E INVALID CARD IN INPUT DECK RC=32
DMSDSK104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSDSK105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSDSK118S ERROR PUNCHING FILE RC=100
DMSDSK124S ERROR READING CARD FILE RC=100
DMSDSK205W READER EMPTY OR NOT READY RC=8
```

DLBL

DLBL

Use the DLBL command:

- In CMS/DOS, to define DOS and CMS sequential disk files for program input/output, and to identify DOS files and libraries; and to define and identify VSAM catalogs, clusters, and data spaces, and to identify VSAM, DOS, or CMS files used for VSAM program input/output, and Access Method Services functions.
- In CMS, to define and identify VSAM catalogs, clusters, and data spaces; to identify VSAM files used for program input/output; and to identify input/output files for AMSERV.

The format of the DLBL command is:

```
DLBL ddname {mode } [CMS fn ft ] [(optionA optionB [ ])]
      {DUMMY} [CMS FILE ddname ]
      ddname {mode } [DSN qual1 [qual2...qualn] ]
      {DUMMY} [DSN ? ]
                                     [(optionA optionB optionC [ ])]
      ddname CLEAR
      *
      optionA:      optionB:      optionC:
      [SYSxxx]      [PERM]      [VSAM ]
                  [CHANGE ]      [EXTENT]
                  [NOCHANGE]     [MULT ]
                                     [CAT catdd]
                                     [BUFSP nnnnnn]
```

Note: The operands and options of the DLBL command are described below. Usage notes are provided for general usage, followed by additional notes for CMS/DOS users, and then additional notes for OS VSAM users.

where:

ddname specifies a 1- to 7-character program ddname (OS) or filename (DOS), or dname (as specified in the FILE parameter of an Access Method Services control statement). An asterisk (*) entered with the CLEAR operand indicates that all DLBL definitions, except those that are entered with the PERM option, are to be cleared.

mode specifies a valid CMS disk mode letter and optionally, filemode number. A letter must be specified; if a number is not specified, it defaults to 1. The disk must be accessed when the DLBL command is issued.

DUMMY specifies that no real I/O is to be performed. A read operation results in an end-of-file condition and a write operation results in a successful return code. DUMMY should not be used for OS VSAM data sets (see Usage Note 3).

| CLEAR removes any existing definitions for the specified ddname. Clearing a ddname before defining it ensures that a file definition does not exist and that any options previously defined with that ddname no longer have any effect.

| CMS fn ft indicates that this is a CMS file, and the file identifier (fn ft) that follows is a CMS filename and filetype.

| FILE ddname is the default CMS file identifier associated with all non-CMS data sets. (See Usage Note 3 for CMS/DOS users.)

| DSN indicates that this is a non-CMS file.

| ? indicates that you are going to enter the data set name interactively. When prompted, you enter the data set name or fileid in its exact form, including embedded blanks, hyphens, or periods.

| qual1 [qual2...qualn] is an OS data set name or DOS file-id. Only data sets named according to standard OS conventions may be entered this way; you must omit the periods between qualifiers. (See Usage Note 2.)

| Options:

| SYSxxx (CMS/DOS only.) indicates the system or programmer logical unit that is associated with the disk on which the disk file resides. The logical unit must have been previously assigned with the ASSGN command. If a DLBL definition is already in effect for the specified ddname, SYSxxx may be omitted; otherwise, it is required.

| PERM indicates that this DLBL definition can be cleared only with an explicit CLEAR request. It will not be cleared when the DLBL * CLEAR command line is entered.

| All DLBL definitions, including those entered with the PERM option, are cleared as a result of a program abend or HX (halt execution) Immediate command.

| CHANGE indicates that any existing DLBL for this ddname is not be canceled, but that conflicting options are to be overridden and new options merged into the old definition. Both the ddname and the file identifier must be the same in order for the definitions to be merged.

| NOCHANGE does not alter any existing DLBL definition for the specified ddname, but creates a definition if none existed.

| VSAM indicates that the file is a VSAM data set. This option must be specified for VSAM functions unless the EXTENT, MULT, CAT, or BUFSP options are entered, or the ddnames IJSYSCT or IJSYSUC are used.

| EXTENT indicates that you are going to use Access Method Services to define a VSAM catalog, data space, or unique cluster and you want to enter extent information.

| MULT indicates that you are going to reference an existing multivolume data set and you want to enter the volume specifications.

DLBL

CAT catdd identifies the VSAM catalog (defined by a previous DLBL definition) which contains the entry for this data set. You must use the CAT option when the VSAM data set you are creating or identifying is not cataloged in the current job catalog. catdd is the ddname in the DLBL definition for the catalog.

BUFSP nnnnnn specifies the number of bytes (in decimal) to be used for I/O buffers by VSAM data management during program execution, overriding the BUFSP value in the ACB for the file. The maximum value for nnnnnn is 999999; embedded commas are not permitted.

Usage Notes

1. To display all of the current DLBL definitions, enter the DLBL command with no operands:

```
dlbl
```

2. To enter an OS or DOS file identification on the DLBL command line, it must consist of 1- to 8-character qualifiers separated by periods, with a maximum length of 44 characters, including periods. For example, the file TEST.INPUT.SOURCE.D could be identified as follows:

```
dlbl dd1 c dsn test input source d (options...
```

Or, it may be entered interactively, as follows:

```
dlbl dd1 c dsn ? (options
DMSDLB220R ENTER DATA SET NAME:
test.input.source.d
```

Note that when the data set name is entered interactively, the data set name must be entered in its exact form; when entered on the DLBL command line, the periods must be omitted.

You must use the interactive form to enter a DOS file-id that contains embedded blanks or hyphens.

3. In DOS/VS, a VSAM data set that has been defined as DUMMY is opened with an error code of X'11'. CMS supports the DUMMY operand of the DLBL command in the same manner. OS users should not use the DUMMY operand in CMS, since a dummy data set does not return, on open, an end-of-file indication.

Additional Notes for CMS/DOS Users

1. Each DLBL definition must be associated with a system or programmer logical unit assignment, previously made with an ASSGN command. Specify the SYSxxx option on the first, or only, DLBL definition for a particular ddname. Many DLBL definitions may be associated with the same logical unit. For example,

```
assgn sys100 b
dlbl dd1 b cms test file1 (sys100
dlbl dd2 b cms test file2 (sys100
dlbl dd1 cms test file3
```

is a valid command sequence.

2. The following special ddnames must be used to define DOS private libraries, and must be associated with the indicated logical units:

<u>ddname</u>	<u>Logical Unit</u>	<u>Library</u>
IJSYSSL	SYSSLB	Source statement
IJSYSRL	SYSRLB	Relocatable
IJSYSCL	SYSCLB	Core image

These libraries must be identified in order to perform librarian functions (with the SSERV, ESERV, DSERV, or RSERV commands) for private libraries; or to link-edit or fetch modules or phases from private relocatable or core image libraries (with the DOSLKED and FETCH commands).

3. Each DOS file has a CMS file identifier associated with it by default; the filename is always FILE and the filetype is always the same as the ddname. For example, if you enter a DLBL command for an DOS file MOD.TEST.STREAM as follows

```
dlbl test c dsn mod test stream
```

then you can refer to this OS data set as FILE TEST when you use the STATE command:

```
state file test
```

When you enter a DLBL command specifying only a ddname and mode, as follows:

```
dlbl junk a
```

CMS assigns a file identifier of FILE JUNK A1 to the ddname JUNK.

4. The FILEDEF command performs a function similar to that of the DLBL command; you need to use the FILEDEF command in CMS/DOS only:

- When you want to override a default ddname for an assembler input or output file.
- When you want to use the MOVEFILE command to process a file.

5. If you use the DUMMY operand, you must have issued an ASSGN command specifying a device type of IGN, or ignore, for the SYSxxx unit specified in the DLBL command, for example,

```
assgn sys003 ign
dlbl test dummy (sys003
```

SPECIFYING VSAM EXTENT INFORMATION: You must specify extent information when you use the Access Method Services control statements DEFINE SPACE, DEFINE MASTERCATALOG, DEFINE USERCATALOG, DEFINE CLUSTER (UNIQUE); or when you use the IMPORT or IMPORTRA functions for a unique file.

When you enter the EXTENT option of the DLBL command, you are prompted to enter the disk extents for the specified file. You must enter extent information in accordance with the following rules:

- You must specify the starting track number and number of tracks for each extent, as follows:

19 38

DLBL

| This extent allocates 38 tracks, beginning with the 19th track, on a
| 3330 device.

| • All extents must begin and end on cylinder boundaries, regardless of
| whether the AMSERV file contains extent information in terms of
| cylinders, tracks, or records.

| • Multiple extents for the same volume must be entered in numerically
| ascending order, for example

| 20 400, 600 80

| These extents are valid for a 2314 device.

| • Multiple extent entries may be entered on a single line, separated by
| commas (as above), or on different lines. Commas at the end of a line
| are ignored.

| • The maximum track value for starting or ending track is 2147483647.

| • When you enter multivolume extents, you must specify the mode letter
| and logical unit associated with each disk that contains extents;
| extents for each disk must be entered consecutively. For example,

```
|      assgn sys001 b  
|      assgn sys002 c  
|      assgn sys003 d  
|      dlbl file1 b (extent sys001  
|      DMSDLB331R ENTER EXTENT SPECIFICATIONS:  
|      100 60, 400 80, 60 40 d sys003  
|      200 100 c sys002  
|      400 100 c sys002  
|      (null line)
```

| specifies extents on disks accessed at modes B, C, and D. These
| disks are assigned to the logical units SYS001, SYS002, and SYS003.
| Since B is the mode specified on the DLBL command line, it does not
| need to be respecified along with the extent information.

| • A DASD volume must be mounted, accessed, and assigned for each disk
| mode referenced in an extent.

| When you are finished entering extent information, you must enter a
| null line to terminate the DLBL command sequence. If you do not, an
| error may result and you will have to reenter the DLBL command. If you
| make any error entering the extents, you must reenter all the extent
| information.

| The DLBL command does not check the extents to see if they are on
| cylinder boundaries or that they are entered in the proper sequence. If
| you do not enter them correctly, the Access Method Services DEFINE
| function will terminate with an error.

| CMS assigns sequence numbers to the extents according to the order in
| which they were entered. These sequence numbers are listed when you use
| the LISTDS command with the EXTENT option.

| IDENTIFYING MULTIVOLUME VSAM EXTENTS: When you want to execute a program
| or use Access Method Services to reference an existing multivolume VSAM
| data set, you must use the MULT option on the DLBL command that
| identifies the file.

| When you use the MULT option, you are prompted to enter additional
| disk mode letters, as follows:

```

|   assgn sys001 c
|   assgn sys002 d
|   assgn sys003 e
|   assgn sys004 f
|   assgn sys005 g
|   dlbl infile c (mult sys001
|   DMSDLB330R ENTER VOLUME SPECIFICATIONS:
|   d sys002, e sys003 , f sys004
|   g sys005
|   (null line)

```

| The above identifies a file that has extents on disks accessed at modes C, D, E, F, and G. These disks have been assigned to the logical units SYS001, SYS002, SYS003, SYS004, and SYS005. The rules for entering multiple extents are:

- | • All disks must be mounted, accessed, and assigned when you issue the DLBL command.
- | • You must not repeat the mode letter and logical unit of the disk that is entered on the DLBL command line (C, in the above example).
- | • If you enter more than one mode letter and logical unit on a line, they must be separated by commas; trailing commas on a line are ignored.
- | • A maximum of nine disks may be specified; you do not need to specify them in alphabetical order.

| You must enter a null line to terminate the command when you are finished entering extents; if not, an error may result and you must reenter the entire command sequence.

| USING VSAM CATALOGS: There are two special ddnames you must use to identify a VSAM master catalog and job catalog:

| IJSYSCT identifies the master catalog when you initially define it (using AMSERV), and when you begin a terminal session. You should use the PERM option when you define it.

| You must assign the logical unit SYSCAT to the disk on which the master catalog resides. If you are redefining a master catalog that has already been identified, you may omit the SYSCAT option on the DLBL command line.

| IJSYSUC identifies a job catalog to be used for subsequent AMSERV jobs or VSAM programs.

| Any programmer logical unit may be used to assign a job catalog.

| Only one VSAM catalog is ever searched when a VSAM function is performed. If a job catalog is defined, you may override it by using the CAT option on the DLBL command for a data set. The following DLBL command sequence illustrates the use of catalogs:

```

|   assgn syscat c
|   dlbl ijsysct c dsn mastcat (perm syscat

```

| identifies the master catalog, MASTCAT, for the terminal session.

```

|   assgn sys010 d
|   dlbl ijsysuc d dsn mycat (perm sys010

```

DLBL

| identifies the job (user) catalog, MYCAT, for the terminal session.

```
|   assign sys100 e
|   dlbl intest1 e dsn test case (vsam sys100
```

| identifies a VSAM file to be used in a program. It is cataloged in the job catalog, MYCAT.


```
|   assign sys101 f
|   dlbl cat3 f dsn testcat (cat ijsysct sys101
```

| identifies an additional user catalog, which has an entry in the master catalog. Since a job catalog is in use, you must use the CAT option to indicate that another catalog, in this case the master catalog, should be used.

```
|   dlbl infile f dsn test input (cat cat3 sys101
```

| identifies an input file cataloged in the user catalog TESTCAT, which was identified with a ddname of CAT3 on the DLBL command.

| The selection of a VSAM catalog for AMSERV jobs and VSAM programs running in CMS is summarized in Figure 6.



| Figure 6. Determining Which VSAM Catalog to Use

| Usage Notes for OS VSAM Users

| 1. You must use the DLBL command to identify all Access Method
| Services input and output files, and to identify all VSAM input and
| output files referenced in programs.

| For all other file definitions, including OS or CMS disk files
| referenced in programs that use VSAM data management, you must use
| the FILEDEF command.

| 2. A DLBL ddname may have a maximum of 7 characters. If you have
| ddnames in your programs that are 8 characters long, only the first
| 7 characters are processed when the programs are executed in CMS.
| If you have two ddnames with the same first 7 characters and you
| attempt to execute this program in CMS, you will receive an open
| error when the second file is opened. You should recompile these
| programs providing unique 7-character ddnames.

| 3. If you release a disk for which you have a DLBL definition in
| effect, you should clear the DLBL definition before you execute a
| VSAM program or an AMSERV command. CMS checks that all disks for
| which there are DLBL definitions are accessed, and issues error
| message DMSSTT069E if any are not.

| SPECIFYING VSAM EXTENT INFORMATION: You must specify extent information
| when you use the Access Method Services control statements DEFINE SPACE,
| DEFINE MASTERCATALOG, DEFINE USERCATALOG, DEFINE CLUSTER (UNIQUE); or
| when you use the IMPORT or IMPORTRA functions for a unique file. Space
| allocation is made only for primary allocation amounts.

| When you enter the EXTENT option of the DLBL command, you are
| prompted to enter the disk extents for the specified file. You must
| enter extent information in accordance with the following rules:

- | • You must specify the starting track number and number of tracks for
| each extent, as follows:

| 19 38

| This extent allocates 38 tracks, beginning with the 19th track, on a
| 3330 device.

- | • All extents must begin and end on cylinder boundaries, regardless of
| whether the AMSERV file contains extent information in terms of
| cylinders, tracks, or records.

- | • Multiple extents for the same volume must be entered in numerically
| ascending order, for example

| 20 400, 600 80

| These extents are valid for a 2314 device.

- | • Multiple extent entries may be entered on a single line, separated by
| commas (as above), or on different lines. Commas at the end of a line
| are ignored.

- | • The maximum track value for starting or ending track is 2147483647.

- | • When you enter multivolume extents, you must specify the mode letter
| for extents on additional disks; extents for each disk must be
| entered consecutively. For example,

DLBL

```
|      dlbl file1 b (extent
|      DMSDLB331R ENTER EXTENT SPECIFICATIONS:
|      100 60, 400 80, 60 40 d
|      200 100 c
|      400 100 c
|      (null line)
```

| specifies extents on disks accessed at modes B, C, and D. Since B is the mode specified on the DLBL command line, it does not need to be respecified along with the extent information.

| • A DASD volume must be mounted and accessed for each mode referenced in an extent.

| When you are finished entering extent information, you must enter a null line to terminate the DLBL command sequence. If you do not, an error may result and you will have to reenter the entire DLBL command. If you make any error entering the extents, you must reenter all the extent information.

| The DLBL command does not check the extents to see if they are on cylinder boundaries or that they are entered in the proper sequence. If you do not enter them correctly, the Access Method Services DEFINE function terminates with an error.

| CMS assigns sequence numbers to the extents according to the order in which they were entered. These sequence numbers are listed when you use the LISTDS command with the EXTENT option.

| IDENTIFYING MULTIVOLUME VSAM EXTENTS: When you want to execute a program or use Access Method Services to reference an existing multivolume VSAM data set, you must use the MULT option on the DLBL command that identifies the file.

| When you use the MULT option, you are prompted to enter additional disk mode letters, as follows:

```
|      dlbl infile c (mult
|      DMSDLB330R ENTER VOLUME SPECIFICATIONS:
|      d, e, f
|      g
|      (null line)
```

| The above example identifies a file that has extents on disks accessed at modes C, D, E, F, and G. The rules for entering multiple extents are:

| • All disks must be mounted and accessed when you issue the DLBL command.

| • You must not repeat the mode letter of the disk that is entered on the DLBL command line (C, in the above example).

| • If you enter more than one mode letter on a line, they must be separated by commas; trailing commas on a line are ignored.

| • A maximum of nine disks may be specified; you do not need to specify them in alphabetical order.

| You must enter a null line to terminate the command when you are finished entering extents; if not, an error may result and you must re-enter the entire command sequence.

| USING VSAM CATALOGS: There are two special ddnames you must use to identify a VSAM master catalog and job catalog:

| IJSYSCT identifies the master catalog, both when you initially define it (using AMSERV), and when you begin a terminal session. You should use the PERM option when you define it.

| IJSYSUC identifies a job catalog to be used for subsequent AMSERV jobs or VSAM programs.

| Only one VSAM catalog is ever searched when a VSAM function is performed. If a job catalog is defined, you may override it by using the CAT option on the DLBL command for a data set. The following DLBL command sequence illustrates the use of catalogs:

| dlbl ijsysct c dsn mastcat (perm

| identifies the master catalog, MASTCAT, for the terminal session.

| dlbl ijsysuc d dsn mycat (perm

| identifies the job (user) catalog, MYCAT, for the terminal session.

| dlbl intest1 e dsn test case (vsam

| identifies a VSAM file to be used in a program. It is cataloged in the job catalog, MYCAT.

| dlbl cat3 dsn testcat (cat ijsysct

| identifies an additional user catalog, which has an entry in the master catalog. Since a job catalog is in use, you must use the CAT option to indicate that another catalog, in this case the master catalog, should be used.

| dlbl infile e dsn test input (cat cat3

| identifies an input file cataloged in the user catalog TESTCAT, which was identified with a ddname of CAT3 on the DLBL command.

| The selection of a VSAM catalog for AMSERV jobs and VSAM programs running in CMS is summarized in Figure 6.

| Responses

| If the DLBL command is issued with no operands, the current DLBL definitions are displayed at your terminal:

```
| ddname1 device1 [fn1 ft1 fm1 [datasetname1]]
|      .      .      .      .      .      .
|      .      .      .      .      .      .
| ddnamen devicen [fnn ftn fmn [datasetnamen]]
```

| DMSDLB220R ENTER DATA SET NAME:

| This message is displayed when you use the DSN ? form of the DLBL command. Enter the exact DOS or OS data set name.

| DMSDLB320I MAXIMUM NUMBER OF DISK ENTRIES RECORDED

| This message indicates that nine volumes have been specified for a VSAM data set, which is the maximum allowed under CMS.

DLBL

| DMSDLB321I MAXIMUM NUMBER OF EXTENTS RECORDED

| This message indicates that 16 extents on a single disk or minidisk
| have been specified for a VSAM data space, catalog, or unique data
| set. This is the maximum number of extents allowed on a minidisk
| or disk.

| DMSDLB322I DDNAME 'ddname' NOT FOUND; NO CLEAR EXECUTED

| This message indicates that the clear function was not performed
| because no DLBL definition is in effect for the ddname.

| DMSDLB232I {MASTER|JOB} CATALOG DLBL CLEARED

| This message indicates that either the master catalog or job
| catalog has been cleared as a result of a clear request.

| You also receive this message if you issue a DLBL * CLEAR command,
| and any DLBL definition is in effect for IJSYSCT or IJSYSUC that
| was not entered with the PERM option.

| DMSDLB330R ENTER VOLUME SPECIFICATIONS:

| This message prompts you to enter volume specifications for
| existing multivolume VSAM files. (See "Identifying Multivolume VSAM
| Extents" in the appropriate usage section.)

| DMSDLB331R ENTER EXTENT SPECIFICATIONS:

| This message prompts you to enter in the data set extent or extents
| of a new VSAM data space, catalog or unique data set. (See
| "Specifying VSAM Extent Information" in the appropriate usage
| section.)

| Other Messages and Return Codes

| DMSDLB001E NO FILENAME SPECIFIED, RC=24

| DMSDLB003E INVALID OPTION 'option' RC=24

| DMSDLB005E NO '{CAT|BUFSP}' SPECIFIED RC=24

| DMSDLB023E NO FILETYPE SPECIFIED, RC=24

| DMSDLB048E INVALID MODE 'mode' RC=24

| DMSDLB050E PARAMETER MISSING AFTER DDNAME RC=24

| DMSDLB065E 'option' OPTION SPECIFIED TWICE RC=24

| DMSDLB066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24

| DMSDLB070E INVALID PARAMETER 'parameter' RC=24

| DMSDLB086E INVALID DDNAME 'ddname' RC=24

| DMSDLB109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104

| DMSDLB221E INVALID DATA SET NAME RC=24

| DMSDLB301E 'SYSxxx' NOT ASSIGNED FOR DISK 'fm' RC=36

| DMSDLB302E NO SYSXXX OPERAND ENTERED RC=24

| DMSDLB304E INVALID OPERAND VALUE 'value' RC=24

| DMSDLB305E INCOMPLETE EXTENT RANGE RC=24

| DMSDLB306E SYSXXX NOT ASSIGNED FOR 'IGNORE' RC=36

| DMSDLB307E CATALOG DDNAME 'ddname' NOT FOUND RC=24

| DMSDLB308E 'mode' DISK IN {CMS|NON-CMS} FORMAT; INVALID FOR
| {NON-CMS|CMS} DATASET RC=24

| DOSLIB

| Use the DOSLIB command to delete, compact, or list information about the
| executable phases in a CMS/DOS phase library. The format of the DOSLIB
| command is:

```

| DOSLIB { DEL libname phasename1 [...phasenamen] }
|        { COMP libname }
|        { MAP libname [ (options...[]) ] }
|
|                               options:
|                               [ TERM ]
|                               [ DISK ]
|                               [ PRINT ]

```

| where:

| DEL deletes phases from a CMS/DOS phase library. The library is
| not erased when the last phase is deleted from the library.

| COMP compacts a CMS/DOS phase library.

| MAP lists certain information about the phases of a DOSLIB.
| Available information provided is phase name, size, and
| relative location in the library.

| libname is the filename of a CMS/DOS phase library. The filetype must
| be DOSLIB.

| phasename1...phasenamen
| is the name of one or more phases that exist in the CMS/DOS
| phase library.

| MAP Options: The following options specify the output device for the
| MAP function. If more than one option is specified, only the first
| option is used.

| TERM displays the MAP output at the terminal.

| DISK writes the MAP output to a CMS disk file with the file
| identifier of 'libname MAP A5'. If a file with that name
| already exists, the old file is erased.

| PRINT spools the MAP output to the virtual printer.

| Usage Notes

| 1. The CMS/DOS environment does not have to be active when you issue
| the DOSLIB command.

| 2. Phases may only be added to a DOSLIB by the CMS/DOS linkage editor,
| as a result of the DOSLKED command.

| 3. In order to fetch a program phase from a DOSLIB for execution, you
| must issue the GLOBAL command to identify the DOSLIB. When a FETCH

DOSLIB

| command or dynamic fetch from a program is issued, all current
| DOSLIBs are searched for the specified phases.

| 4. If DOSLIBs are very large, or there are many of them to search,
| program execution is slowed down accordingly. To avoid excessive
| execution times, you should keep your DOSLIBs small, and issue a
| GLOBAL command specifying only those libraries that you need.

| Responses

| When you use the TERM option on the DOSLIB MAP command line, the
| following is displayed:

PHASE	INDEX	BLOCKS
name1	loc	size
.	.	.
.	.	.
.	.	.

| Other Messages and Return Codes

| DMSDSL002E FILE 'fn DOSLIB' NOT FOUND RC=28
| DMSDSL003E INVALID OPTION 'option' RC=24
| DMSDSL013W PHASE 'phase' NOT FOUND IN LIBRARY 'fn DOSLIB fm' RC=4
| DMSDSL014E INVALID FUNCTION 'function' RC=24
| DMSDSL037E DISK 'mode' IS READ/ONLY RC=36
| DMSDSL046E NO LIBRARY NAME SPECIFIED RC=24
| DMSDSL047E NO FUNCTION SPECIFIED RC=24
| DMSDSL069E DISK 'mode' NOT ACCESSED RC=36
| DMSDSL070E INVALID PARAMETER 'parameter' RC=24
| DMSDSL098E NO PHASE NAME SPECIFIED RC=24
| DMSDSL104S ERROR 'nn' READING FILE 'fn DOSLIB fm' FROM DISK RC=100
| DMSDSL105S ERROR 'nn' WRITING FILE 'fn DOSLIB fm' ON DISK RC=100
| DMSDSL213W LIBRARY 'fn DOSLIB fm' NOT CREATED RC=4

DOSLKED

| TERM displays the linkage editor map at your terminal.

| Note: All error messages are sent to the terminal as well as to the
| specified device.

| Usage Notes

| 1. You can create a CMS file with a filetype of DOSLNK to contain
| DOS/V S linkage editor control statements, and optionally, CMS text
| files.

| 2. If you want to link-edit a module from a private relocatable
| library, you must issue an ASSGN command for the logical unit
| SYSRLB and enter a DLBL command using a ddname of IJSYSRL to
| identify the library:

```
|         assgn sysrlb c  
|         dlbl ijsysrl c dsn reloc lib (sysrlb
```

| If you have defined a private relocatable library, but do not want
| it to be searched, enter

```
|         assgn sysrlb ign
```

| to temporarily bypass it.

| 3. CMS TEXT files may also contain linkage editor control statements
| INCLUDE, PHASE, and ENTRY. The ACTION statement is ignored when a
| TEXT file is link-edited.

| 4. To access modules on the DOS/V S system residence volume, you must
| have specified the mode letter of the system residence on the SET
| DOS ON command line:

```
|         set dos on z
```

| 5. The search order that CMS uses to locate object modules to be
| link-edited is:

| a. The specified object module on the DOS/V S private relocatable
| library, if one is available.

| b. CMS disks for a file with the specified filename and with a
| filetype of TEXT.

| c. The specified object module on the DOS/V S system relocatable
| library, if it is available.

| 6. When a phase is added to an existing DOSLIB, it is always written
| at the end of the library. If a phase that is being added has the
| same name as an existing phase, the DOSLIB directory is updated to
| point to the new phase. The old phase is not deleted, however; you
| should issue the DOSLIB command with the COMP option to compress
| the space.

| If you run out of space in a DOSLIB while you are executing the
| DOSLKED command, you should reissue the DOSLKED command specifying
| a different DOSLIB, or compress the DOSLIB before attempting to
| reissue the DOSLKED command.

| LINKAGE EDITOR CONTROL STATEMENTS: The CMS/DOS linkage editor recognizes
| and supports the DOS/V S linkage editor control statements ACTION, PHASE,
| ENTRY, and INCLUDE. These control statements are described in DOS/V S
| System Control Statements. The CMS/DOS linkage editor ignores:

- | • The SVA operand of the PHASE statement.
- | • The F+address form for specifying origin on the PHASE statement.
- | • The BG, F1, F2, F3, or F4 operands of the ACTION statement.

| The S-form of specifying the origin on the PHASE statement corresponds to the CMS user area under CMS/DOS. If a default PHASE statement is required, the origin is assumed to be S. The PBDY operand of the PHASE statement indicates that the phase is link-edited on a 4K page boundary under CMS/DOS as opposed to a 2K page boundary for DOS/VS.

| In DOS/VS, an ACTION CLEAR control statement clears the unused portion of the core image library to binary zeros. In DOS/VS the core image library has a defined size, while in CMS/DOS the CMS phase library varies in size, depending on the number of phases cataloged. Therefore, in CMS/DOS an ACTION CLEAR control statement clears the current buffers to binary zeros before loading them; CMS/DOS cannot clear the entire unused portion of the CMS phase library because that portion varies as phases are added to and deleted from the CMS phase library. In CMS/DOS if you want your phases cleared you must issue an ACTION CLEAR control statement each time you add a phase to the CMS phase library.

| LINKAGE EDITOR CARD TYPES: The input to the linkage editor can consist of six card types, produced by a language translator or a programmer. These cards appear in the following order:

<u>Card Type</u>	<u>Definition</u>
ESD	External symbol dictionary
SYM	Ignored by linkage editor
TXT	Text
RLD	Relocation list dictionary
REP	Replacement of text made by the programmer
END	End of module

| CMS/DOS supports these six card types in the same manner that DOS/VS does. These card types are described in the DOS/VS System Control Statements.

| Responses

| When you use the TERM option of the DOSLKED command, the linkage editor map is displayed at the terminal.

| 2101I INVALID OPERATION IN CONTROL STATEMENT

| This message indicates that a blank card was encountered in the process of link-editing a relocatable module. This message also appears in the MAP file. The invalid card is ignored and processing continues.

| Other Messages and Return Codes

| DMSDLK001E NO FILENAME SPECIFIED RC=24
 | DMSDLK003E INVALID OPTION 'option' RC=24
 | DMSDLK006E NO READ/WRITE DISK ACCESSED RC=36
 | DMSDLK007E FILE 'fn ft fm' IS NOT FIXED, 80-CHAR. RECORDS RC=32
 | DMSDLK070E INVALID PARAMETER 'parameter' RC=24
 | DMSDLK099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
 | DMSDLK104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
 | DMSDLK105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
 | DMSDLK210E LIBRARY 'library' IS ON READ-ONLY DISK RC=36
 | DMSDLK245S ERROR 'nnn' ON PRINTER RC=100

DSERV

| DSERV

| Use the DSERV command in CMS/DOS to obtain information that is contained
| in DOS/VS private or system libraries. The format of the DSERV command
| is:

```
|-----|
| DSERV  | { CD [ PHASE { phasename } [nn] ] } [d2 ...dn] [(options[])]
|        | { RD                                     options:
|        | { SD                                     [DISK ]
|        | { PD                                     [TERM ]
|        | { TD                                     [PRINT]
|        | { ALL                                    [SORT ]
|-----|
```

| where:

| CD specifies that information concerning one or more types of
| RD directories is to be displayed or printed. The directory
| SD types that can be specified are: CD (core image library),
| PD RD (relocatable library), SD (source statement library),
| TD PD (procedure library), TD (transient directory), and
| ALL ALL (all directories).

| There is no default value. The private libraries take
| precedence over system libraries.

| PHASE phasename specifies the name of the phase to be listed. If the
| phasename ends with an asterisk, all phases that start with
| the letters preceding the asterisk are listed. This operand
| is only valid for CD.

| nn is the offset within the phase where the version and level
| are to be found (the default is 12).

| [d2...dn] indicates additional libraries whose directories are to be
| listed. (See Usage Note 1.)

| Options:

| DISK writes the output on your CMS A-disk to a file named DSERV MAP
| A5. This is the default value if TERM or PRINT is not
| specified.

| TERM displays the output at your terminal.

| PRINT spools the output to the system printer.

| SORT sorts the entries for each library alphanumerically; otherwise,
| the order is the order in which the entries were cataloged.

| Usage Notes

| 1. You may specify more than one directory on DSERV command line, for
| example,

```

|         dserv rd sd cd phase $$bopen (term
|
| displays the directories of the relocatable and source statement
| libraries, as well as the entry for the phase $$BOPEN from the core
| image directory.
|
| You can specify only one phasename or phasename* at a time,
| however. If you specify more than one PHASE operand, only the last
| one entered is listed. For example, if you enter
|
|         dserv cd phase cor* phase idc*
|
| the file DSERV MAP contains a list of all phases that begin with
| the characters IDC. The first phasename specification is ignored.
|
| 2. If you want to obtain information from the directories of private
| source statement, relocatable, or core image libraries, the
| libraries must be assigned and identified (via ASSGN and DLBL
| commands) when the DSERV command is issued. Otherwise, the system
| library directories are used. System directories are made
| available when you specify a mode letter on the SET DOS ON command
| line.
|
| 3. The current assignments for logical units are ignored by the DSERV
| command; output is directed only to the output device indicated by
| the option list.

```

| Responses

```

| When you use the TERM option of the DSERV command, the contents of the
| specified directory are displayed at your terminal.

```

| Other Messages and Return Codes

```

| DMSDSV003E INVALID OPTION 'option' RC=24
| DMSDSV021W NO TRANSIENT DIRECTORY RC=4
| DMSDSV022W NO CORE IMAGE DIRECTORY RC=4
| DMSDSV023W NO RELOCATABLE DIRECTORY RC=4
| DMSDSV024W NO PROCEDURE DIRECTORY RC=4
| DMSDSV025W NO SOURCE STATEMENT DIRECTORY RC=4
| DMSDSV026W 'phase' NOT IN LIBRARY RC=4
| DMSDSV027E INVALID DEVICE 'nn' RC=24
| DMSDSV027W NO PRIVATE CORE IMAGE LIBRARY RC=4
| DMSDSV028W NO {PRIVATE|SYSTEM} TRANSIENT DIRECTORY ENTRIES RC=4
| DMSDSV047E NO FUNCTION SPECIFIED RC=24
| DMSDSV065E 'option' OPTION SPECIFIED TWICE RC=24
| DMSDSV066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
| DMSDSV070E INVALID PARAMETER 'parameter' RC=24
| DMSDSV095E INVALID ADDRESS 'address' RC=24
| DMSDSV099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSDSV105S ERROR 'nn' WRITING FILE 'DSERV MAP A5' ON DISK RC=24
| DMSDSV245S ERROR 'nnn' ON PRINTER RC=100

```


Options:

LRECL nn is the record length of the file to be created or edited. Use this option to override the default values supplied by the editor, which are determined as follows:

Editing Existing Files: Existing record length is kept regardless of format. If the file has variable-length records and the existing record length is less than the default record length, the default record length is used.

Creating New Files: All new files have a record length of 80, with the following exceptions:

<u>Filetype</u>	<u>LRECL</u>
LISTING	121
SCRIPT, VSBDATA	132
FREEFORT	81

The maximum record length supported by the editor is 160 characters.

NODISP forces a 3270 display terminal into line (typewriter) mode. When the NODISP option is in effect, all subcommands that control the display as a 3270 terminal such as SCROLL, SCROLLUP, and FORMAT (and CHANGE and with no operands) are made invalid for the edit session.

Responses

NEW FILE:

The specified file does not exist.

EDIT:

The edit environment is entered. You may issue any valid EDIT subcommand or macro request.

INPUT:

The input environment is entered by issuing the EDIT subcommands REPLACE or INPUT with no operands. All subsequent input lines are accepted as input to the file.

Other Messages and Return Codes

```

DMSEDI003E INVALID OPTION 'option' RC=24
| DMSEDI024E FILE 'EDIT CMSUT1 fm' ALREADY EXISTS RC=28
DMSEDI029E INVALID PARAMETER 'parameter' IN THE OPTION 'LRECL' FIELD RC=24
DMSEDI044E RECORD LENGTH EXCEEDS ALLOWABLE MAXIMUM RC=32
DMSEDI054E INCOMPLETE FILEID SPECIFIED RC=24
DMSEDI076E ACTUAL RECORD LENGTH EXCEEDS THAT SPECIFIED RC=40
DMSEDI104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSEDI105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
| DMSEDI117S ERROR WRITING TO DISPLAY TERMINAL RC=100
DMSEDI132S FILE 'fn ft fm' TOO LARGE RC=88
| DMSEDI143S UNABLE TO LOAD SAVED SYSTEM OR LOAD MODULE RC=40
| DMSEDI144S REQUESTED FILE IS IN ACTIVE STATUS

```

ERASE

ERASE

Use the ERASE command to delete one or more CMS files from a read/write disk. The format of the ERASE command is:

ERASE	fn	ft	[fm]	[(options...[])]	<u>options:</u>
	*	*			
					[Type]
					[Notype]

where:

- fn is the filename of the file(s) to be erased. An asterisk coded in this position indicates that all filenames are to be used. fn must be specified, either with a name or an asterisk.
- ft is the filetype of the file(s) to be erased. An asterisk coded in this position indicates that all filetypes are to be used. This field must be specified, either with a name or an asterisk.
- fm is the filemode of the files to be erased. If this field is omitted, only the A-disk is searched.

Options:

TYPE displays at the terminal the file identifier of each file erased.

NOTYPE file identifiers are not displayed at the terminal.

Usage Notes

1. If you specify an asterisk for both filename and filetype you must specify both a filemode letter and number, for example,

```
erase * * a5
```

To erase all files on a particular disk, you can use the FORMAT command to reformat it or access the disk using the ACCESS command with the ERASE option.

Responses

If you specify the TYPE option, the file identification of each file erased is displayed. For example,

```
erase oldfile temp (type
```

results in the display:

```
OLDFILE TEMP A1  
R;
```

Other Messages and Return Codes

```
DMSERS002E FILE ['fn [ft [fm]]'] NOT FOUND RC=28
DMSERS003E INVALID OPTION 'option' RC=24
| DMSERS037E DISK 'mode' IS READ/ONLY RC=36
DMSERS048E INVALID MODE 'mode' RC=24
DMSERS054E INCOMPLETE FILEID SPECIFIED RC=24
DMSERS069E DISK 'mode' NOT ACCESSED RC=36
DMSERS070E INVALID PARAMETER 'parameter' RC=24
DMSERS071E ERASE * * [*|mode] NOT ALLOWED RC=24
| DMSERS109T VIRTUAL STORAGE CAPACITY EXCEEDED
```

Note: You can invoke the ERASE command from the terminal, from an EXEC file, or as a function from a program. If ERASE is invoked as a function or from an EXEC file that has the &CONTROL NOMSG option in effect, the DMSERS002E FILE fn ft fm NOT FOUND error message is not issued.

| **ESERV**

| Use the **ESERV EXEC** procedure in CMS/DOS to copy edited DOS/VS macros from system or private source statement E sublibraries to CMS disk files, or to list de-edited macros. The format of the **ESERV** command is:

```
| ┌──────────────────────────────────────────────────────────────────────────────────┐
| | ESERV | fn ───────────────────────────────────────────────────────────────────┘
| └──────────────────────────────────────────────────────────────────────────────────┘
```

| where:

| **fn** specifies the filename of the CMS file that contains the **ESERV** control statements; it must have a filetype of **ESERV**. The logical unit **SYSIPT** must be assigned to the disk on which the **ESERV** file resides. **fn** is also the filename of the **LISTING** and **MACRO** files produced by the **ESERV** program.

| Usage Notes

- | 1. The input file can contain any or all of the **ESERV** control statements as defined in Guide to the DOS/VS Assembler.
- | 2. You must have a read/write A-disk accessed when you use the **ESERV** command.
- | 3. To copy macros from the system source statement library, you must have entered the CMS/DOS environment specifying the mode letter of the DOS/VS system residence. To copy from a private source statement library, you must assign the logical unit **SYSSLB** and issue a **DLBL** command for the ddname **IJSYSSL**.
- | 4. The output of the **ESERV** program is directed (as in DOS/VS) to devices assigned to the logical units **SYSLST** and/or **SYSPCH**. If either **SYSLST** or **SYSPCH** is not assigned, the following files are created:

<u>Unit</u>	<u>Output File</u>
SYSLST	fn LISTING mode
SYSPCH	fn MACRO mode

| where mode is the mode letter of the disk on which the source file, **fn** **ESERV** resides. If **fn** **ESERV** is on a read-only disk, the files are written to your A-disk.

| You can override default assignments made by the **ESERV EXEC** as follows:

- | • If you assign **SYSIPT** to **TAPE** or **READER**, the source statements are read from that device.
 - | • If you assign **SYSLST** or **SYSPCH** to another device, the **SYSLST** or **SYSPCH** files are written to that device.
- | 5. The **ESERV EXEC** procedure clears all **DLBL** definitions, except those entered with the **PERM** option.
 - | 6. If you want to use the **ESERV** command in an **EXEC** procedure, you must use the **EXEC** command (because **ESERV** is also an **EXEC**).

| 7. When you use the ESERV control statements PUNCH or DSPCH, the ESERV
| program may generate CATAL.S, END, or /* records in the output
| file. When you add a MACRO file containing these statements to a
| CMS macro library using the MACLIB command, the statements are
| ignored and are not read into the MACLIB member.

| Responses

| None. The CMS Ready message indicates that the ESERV program completed
| execution successfully. You may examine the SYSLST output to verify the
| results of the ESERV program execution.

| Error Messages and Return Codes

| DMSERV001E NO FILENAME SPECIFIED RC=24
| DMSERV002E FILE 'fn ESERV' NOT FOUND RC=28
| DMSERV006E NO READ / WRITE DISK ACCESSED RC=36
| DMSERV027E INVALID DEVICE ' device ' FOR SYSxxx RC=28
| DMSERV037E DISK 'mode' IS READ ONLY RC=36
| DMSERV070E INVALID ARGUMENT ' argument ' RC=24
| DMSERV099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40

| Note: The ESERV EXEC calls other CMS commands to perform certain
| functions, and so you may, on occasion, receive error messages that
| occur as a result of those commands.

| Non-CMS error messages produced by the DOS/VS ESERV program are
| described in the Guide to the DOS/VS Assembler.

EXEC

EXEC

Use the EXEC command to execute one or more CMS commands or EXEC control statements contained in a specified EXEC file. The format of the EXEC command is:

```
[ [EXec] | fn [args...] ]
```

where:

[EXec] indicates that the EXEC command may be omitted if you are executing the EXEC procedure from the CMS command environment and have not issued the command SET IMPEX OFF.

fn is the filename of a file containing one or more CMS commands and/or EXEC control statements to be executed. The filetype of the file must be EXEC and the file can have either fixed- or variable-length records with a logical record length not exceeding 130 characters. EXEC files can be created with the EDIT command or by a user program. EXEC files created by the CMS Editor have, by default, variable-length, 80-character records.

args are any arguments you wish to pass to the EXEC. The arguments are assigned to the special variables &1 through &30 in the order in which they appear in the argument list.

"Section 5. EXEC Control Statements" contains complete descriptions of EXEC control statements, special variables, and built-in functions. For information on designing EXEC procedures and examples of control word usage, see the VM/370: CMS User's Guide.

Responses

The amount of information displayed during the execution of an EXEC depends on the setting of the &CONTROL control statement, which by default displays all CMS commands, responses and error messages. In addition, it displays nonzero return codes from CMS in the format

```
+++ R(nnnnn) +++
```

where nnnnn is the return code from the CMS command.

For details, see the description of the &CONTROL control statement in "Section 5. EXEC Control Statements."

Messages and Return Codes

If the EXEC interpreter finds an error, it displays the message:

```
DMSEXT072E ERROR IN EXEC FILE filename, LINE nnnn - description
```

The possible errors, and the associated return codes, are:

<u>Description</u>	<u>Return</u>
	<u>Code</u> ---
FILE NOT FOUND	801
&SKIP OR &GOTO ERROR	802
BAD FILE FORMAT	803
TOO MANY ARGUMENTS	804
MAX DEPTH OF LOOP NESTING EXCEEDED	805
ERROR READING FILE	806
INVALID SYNTAX	807
INVALID FORM OF CONDITION	808
INVALID ASSIGNMENT	809
MISUSE OF SPECIAL VARIABLE	810
ERROR IN &ERROR ACTION	811
CONVERSION ERROR	812
TOO MANY TOKENS IN STATEMENT	813
MISUSE OF BUILT-IN FUNCTION	814
EOF FOUND IN LOOP	815
INVALID CONTROL WORD	816
EXEC ARITHMETIC UNDERFLOW	817
EXEC ARITHMETIC OVERFLOW	818

Error Message and Return Code

DMSEXC001E NO FILENAME SPECIFIED RC=24

FETCH

| FETCH

| Use the FETCH command in CMS/DOS to load an executable phase into storage for execution. The format of the FETCH command is:

```
| -----  
| FETCh | phasename [(options...)] |  
|       |                               | options:  
|       |                               | [START]  
|       |                               | [COMP]  
|       |                               | [ORIGIN hexloc]  
| -----
```

| where:

| phasename is the name of the phase to be loaded into virtual storage.
| CMS searches for the phase:

- | 1. In a DOS/VS private core image library, if IJSYSCL has been defined.
- | 2. In CMS DOSLIBS that have been identified with the GLOBAL command.
- | 3. In the DOS/VS system core image library, if you specified the mode letter of the DOS/VS system residence on the SET DOS ON command line.

| Options:

| START specifies that once the phase is loaded into storage, execution should begin immediately.

| COMP specifies that when the phase is to be executed, register 1 should contain the address of its entry point. (See Usage Note 4.)

| ORIGIN hexloc fetches the program and loads it at the location specified by hexloc; this location must be in the CMS user area. The location, hexloc, is a hexadecimal number of up to 8 characters. (See Usage Note 5.)

| Usage Notes

| 1. If you do not use the START option, FETCH displays a message at your terminal indicating the name of the phase and the storage location of its entry point. At this time you can set address instruction stops for testing. To continue, issue the START command to initiate execution of the phase just loaded.

| 2. The fetch routine is also invoked by supervisor call (SVC) instructions 1, 2, 4, or 65. The search order for executable phases is the same as listed above.

| 3. If you want to fetch a phase from a private core image library, you must issue an ASSGN command for the logical unit SYSCLB and define the library in a DLBL command using the dname IJSSYCL. For example,

```
|     assgn sysclb c  
|     dlbl ijsyscl c dsn core image lib (sysclb perm
```

| 4. CMS uses the COMP option when it fetches the DOS PL/I compiler because that compiler expects register 1 to contain its entry point address. This option is not required when you issue the FETCH command to load your own programs.

| When CMS starts executing a phase that has COMP specified, the DMSLIO740I EXECUTION BEGINS... message is not displayed.

| 5. The ORIGIN option is used by the CMS/VSAM installation EXEC procedure to load nonshareable modules on a segment boundary. It is not required when you issue the FETCH command to load your own programs, unless you want to load them at a location other than 20000.

| Responses

| DMSFET710I PHASE 'phase' ENTRY POINT AT LOCATION xxxxxx

| This message is issued when the START option is not specified. It indicates the virtual storage address at which the phase was loaded.

| DMSLIO740I EXECUTION BEGINS...

| This message is issued when the START option is specified; it indicates that program execution has begun.

| Other Messages and Return Codes

| DMSFCH104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
 | DMSFCH109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
 | DMSFCH113S DISK (cuu) NOT ATTACHED RC=100
 | DMSFCH115E PHASE LOAD POINT LESS THAN 'address' RC=40
 | DMSFCH411S INPUT ERROR CODE "nn" ON '{SYSRES|SYSCLB}' RC=100
 | DMSFCH777S DOS PARTITION TOO SMALL TO ACCOMMODATE FETCH REQUEST RC=104
 | DMSFET003E INVALID OPTION 'option' RC=24
 | DMSFET004E PHASE 'phase' NOT FOUND RC=28
 | DMSFET029E INVALID PARAMETER 'parameter' IN THE OPTION 'ORIGIN' FIELD
 | RC=24
 | DMSFET070E INVALID PARAMETER 'parameter' RC=24
 | DMSFET098E NO PHASE NAME SPECIFIED RC=24
 | DMSFET099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
 | DMSLIO055E NO ENTRY POINT DEFINED RC=40

FILEDEF

FILEDEF

Use the FILEDEF command to establish data definitions for OS ddnames, to define files to be copied with the MOVEFILE command, or to override default file definitions made by the assembler and the OS language processors. The format of the FILEDEF command is:

```

Filedef {
  {ddname} Terminal      [ (optionA optionD() ) ]
  nn
  * }
  PPrinter
  PUnch      [ (optionD() ) ]
  Reader

  DISK [fn ft [fm]] [ (optionA optionB() ) ]
      [FILE ddname [A]]

  [ [DISK fn ft [fm]] { DSN ?
  [ [FILE ddname [A]] { DSN qual1 qual2 ... }
  [ ] ] ] ]

  [ (optionA optionB() ) ]

  DUMMY      [ (optionA() ) ]

  TAPn      [ (optionA optionC() ) ]

  CLEAR

  optionA:   optionB:   optionC:   optionD:
  [ PERM ]   [ KEYLEN nnn ] [ 7TRACK ] [ UPCASE ]
  [ CHANGE ] [ XTENT nnnnn ] [ 9TRACK ] [ LOWCASE ]
  [ NOCHANGE ] [ XTENT 50 ] [ TRTCH a ]
  [ RECFM a ] [ LIMCT nnn ] [ DEN den ]
  [ LRECL nnnnn ] [ OPTCD a ]
  [ BLOCK nnnnn ] [ DISP MOD ]
  [ BLKSIZE nnnnn ] [ MEMBER membername ]
  [ ] [ CONCAT ]
  [ ] [ DSORG ( PS ) ]
  [ ] [ PO ]
  [ ] [ DA ]
  [ ] [ IS ]

```

where:

ddname is the name by which the file is referred to in your program. OS ddname syntax rules should be followed. If a number nn is specified, it is translated to a FORTRAN data definition name of FTnnF001. An asterisk (*) may be specified with the CLEAR operand, to indicate that all file definitions not entered with the PERM option should be cleared.

Devices

| TERMINAL is your terminal (terminal I/O must not be blocked).

PRINTER is the spooled printer.

PUNCH is the spooled punch.

READER is the spooled card reader (card reader I/O must not be blocked).

DISK specifies that the virtual I/O device is a disk. As shown in the format, you can choose one of two forms for specifying the DISK operand. Both forms are described in "Using the FILEDEF DISK Operand."

DUMMY indicates that no real I/O takes place for a data set.

TAPn is a magnetic tape. The symbolic number of the tape drive, n, can be 1, 2, 3, or 4, representing virtual units 181, 182, 183, and 184 respectively.

CLEAR removes any existing definition for the specified ddname. Clearing a ddname before defining it ensures that a file definition does not exist and that any options previously defined with the ddname no longer have effect.

Options: Whenever an invalid option is specified for a particular device type, an error message is issued. Figure 7 shows valid options for each device type.

Option	Unit Record		TAPn	DISK DUMMY ¹
	READER, PUNCH PRINTER	TERMINAL		
BLOCK, BLKSIZE	X	X	X	X
CHANGE, NOCHANGE	X	X	X	X
CONCAT				X
DEN			X	
DISP MOD				X
DSORG				X
KEYLEN				X ²
LIMCT				X ²
LOWCASE, UPCASE		X		
LRECL	X	X	X	X
MEMBER				X
OPTCD				X ²
PERM	X	X	X	X
RECFM	X	X	X	X
TRTCH			X ³	
XTENT				X ²
7TRACK, 9TRACK			X	

¹No options may be necessary but all disk options are accepted.

²This option is meaningful only for BDAM files.

³This option is for 7-track tapes only.

Figure 7. Valid File Characteristics for Each Device Type of the FILEDEF Command

FILEDEF

PERM retains the current definition until it either is explicitly cleared or is changed with a new FILEDEF command with the CHANGE option. If PERM is not specified, the definition is cleared when a FILEDEF *CLEAR command is executed.

CHANGE merges the file definitions whenever a file definition already exists for a ddname and a new FILEDEF command specifying the same ddname is issued; the options associated with the two definitions are merged. Options from the original definition remain in effect unless duplicated in the new definition. New options are added to the option list.

NOCHANGE retains the current file definition, if one exists, for the specified ddname.

RECFM a is the record format of the file, where 'a' can be one of the following:

<u>a</u>	<u>Meaning</u>
F	fixed length
FB	fixed blocked ¹
V	variable length
VB	variable blocked ¹
U	undefined
FS,FBS	fixed length, standard blocks
VS,VBS	variable length, spanned records
A	ASA print control characters ²
M	machine print control codes ²

LRECL nnnnn is the logical record length (nnnnn) of the file, in bytes. LRECL should not exceed 32,767 bytes because of OS restrictions.

BLOCK nnnnn
BLKSIZE nnnnn

is the logical block size (nnnnn) of the file, in bytes. BLOCK should not exceed 32,767 bytes because of OS restrictions. If both BLOCK and BLKSIZE options are specified, the value of nnnnn for BLOCK is used and BLKSIZE is ignored.

If a CMS file is fixed and has 80-byte CMS records, you should specify RECFM FB BLOCK 800 LRECL 80 and a filemode number of 1. (BLOCK can also be expressed as 80*10.) There can be significant performance improvement for CMS fixed files if the block size is a multiple of 800.

KEYLEN nnn is the size (nnn) of the key (in bytes). The maximum value accepted is 256.

XTENT nnnnn is the number of records (nnnnn) in the extent for the file. The default is 50. The maximum value is 65535.

LIMCT nnn is the maximum number of extra tracks or blocks (nnn) to be searched. The maximum value is 256.

¹FB and VB should not be used with TERMINAL or READER devices.

²A and M may be used in conjunction with any of the valid RECFM settings (for example, FA, FBA, VA, VBA, etc.)

OPTCD a is the direct access search processing desired. The variable 'a' may be any combination of up to three of the following: (A and R are mutually exclusive.)

Code	DASD Search
A	Actual device addressing
E	Extended search
F	Feedback addressing
R	Relative block addressing

Note: The KEYLEN, XTENT, LIMCT, and OPTCD options should only be used with BDAM files.

DISP MOD positions the read/write pointer after the last record in the disk file.

MEMBER membername allows you to specify the name of a member of an OS partitioned data set; membername is the name of the PDS member.

CONCAT allows you to assign the same ddname to two or more OS macro libraries so that you can refer to them in a single GLOBAL command.

Any file format options you specify in the first FILEDEF command line remain in effect for subsequently concatenated libraries.

DSORG { PS } is the data set organization: physical sequential (PS),
 { PO } partitioned (PO), direct access (DA), or indexed
 { DA } sequential (IS).
 { IS }

[7TRACK] is the tape setting.
 [9TRACK]

| TRTCH a is the tape recording technique for 7-track tapes. Use
 | the following chart to determine the value of 'a' for
 | 7-track tapes.

a	Parity	Converter	Translator
O	odd	off	off
OC	odd	on	off
OT	odd	off	on
E	even	off	off
ET	even	off	on

The default value of TRTCH is OC.

DEN den is tape density: den can be 200, 556, 800, 1600, or 6250 bpi (bits per inch). If 200 or 556 are specified, 7TRACK is assumed. If 800, 1600, or 6250 are specified 9TRACK is assumed.

UPCASE translates all terminal input data to uppercase.

LOWCASE retains all terminal input data as typed in.

FILEDEF

Usage Notes

1. If you do not issue a FILEDEF command for an OS input or output file, CMS uses the ddname on the DCB macro to issue the following default file definition:

FILEDEF ddname DISK FILE ddname A1

See "Usage Notes" under the discussion of the ASSEMBLE command for information on the default file definitions made by the assembler.

2. To identify DOS files for DOS program execution, or to identify VSAM data sets for either OS or DOS program execution, you must use the DLBL command.
3. A file definition established with the FILEDEF command remains in effect until explicitly changed or cleared. The system clears file definitions under the following circumstances:
 - When the assembler or any of the language processors are invoked (FILEDEF definitions entered with the PERM option are not cleared).
 - When a program abends or when you issue the Immediate command HX to halt command or program execution.
4. The FILEDEF command does not supply default values for LRECL and BLKSIZE. As under OS, if DCB information is unavailable when a file is opened, an open error is issued for the file. The following chart summarizes the results of specifying LRECL and BLKSIZE options.

BLKSIZE	LRECL	Results
Not Specified	Not Specified	If the input file exists on disk, the item length becomes the BLKSIZE (or BLKSIZE +4 for variable-length records).
Specified	Not Specified	LRECL=BLKSIZE (or LRECL=BLKSIZE-4, for variable-length records).
Not Specified	Specified	BLKSIZE=LRECL (or BLKSIZE=LRECL+4, for variable-length records).
Specified	Specified	The values specified are used.

If V or VB is specified for RECFM, LRECL must be at least 4 bytes less than BLKSIZE.

DOS sequential (SAM) files do not contain BLKSIZE, LRECL, or RECFM specifications. These options must be specified by a FILEDEF command or DCB statement if OS macros are used to access DOS files. Otherwise the defaults, BLKSIZE=32760 and RECFM=U, are assumed. LRECL is not used for RECFM=U files.

5. There is an auxiliary processing option for FILEDEF that is only valid when FILEDEF is executed by an internal program call: this option cannot be entered on a terminal command. The option, AUXPROC addr, allows an auxiliary processing routine to receive control during I/O operations.

Using the FILEDEF DISK Operand

There are two general forms for specifying the DISK operand in a FILEDEF command. If you specify the first form:

```
FILEDEF ddname DISK fn ft [fm]
```

fn and ft (filename and filetype) are assumed to be a CMS fileid. If fm is the filemode of an OS disk, fn and ft are assumed to be the only two qualifiers of an OS data set name.

You cannot use this form unless the OS data set name or DOS file-id conforms to the OS naming convention (1- to 8-byte qualifiers separated by periods, to a maximum of 44 characters, including periods). Also, the data set name can have only two qualifiers; otherwise, you must use the DSN ? or DSN qual1... form. For example, if the data set name or file-id is TEST.SAMPLE.MAY, you enter:

```
FILEDEF MINE B1 DSN TEST SAMPLE MAY
```

```
-- or --
```

```
FILEDEF MINE B1 DSN ?
TEST.SAMPLE.MAY
```

If the data set name or file-id is TEST.SAMPLE, then you may enter:

```
FILEDEF MINE DISK TEST SAMPLE B1
```

The second form of the DISK operand is used only with OS data sets and DOS files:

```
FILEDEF ddname [DISK fn ft ] [fm] { DSN ?
| FILE ddname| |A1| { DSN qual1 [qual2...]}
[ ]
```

This form allows you to enter OS and DOS file identifications that do not conform to OS data set naming conventions. The DSN operand corresponds to the DSN parameter on the OS DD (data definition) statement. There are three ways you can specify this form:

- FILEDEF ddname DISK fn ft fm DSN qual1 [qual2...]

This form of the FILEDEF command associates the CMS filename and filetype you specify with the OS data set name or DOS file-id specified following the DSN operand. Once it is defined, you can refer to the OS data set name or DOS file-id by using the CMS filename and filetype. If you omit DISK, filename, filetype, and filemode, the default values are FILE ddname A1.

- FILEDEF ddname DSN ?

This form of the FILEDEF command allows you to specify the OS data set name or DOS file-id interactively. Using this form, you can enter an OS data set name or DOS file-id containing embedded special characters such as blanks and hyphens. If you use this form, the default filename and filetype for your file, FILE ddname, is the CMS filename and filetype associated with the OS data set name or DOS file-id. The filemode for this form is always the default, A1.

To use the interactive DSN operand, you key in DSN ?; CMS then requests that you enter the OS data set name or DOS file-id exactly

FILEDEF

as it appears in the data set or file. Do not omit the periods that separate the qualifiers of an OS data set name, but do not insert periods where they do not appear.

qual1[.qual2...]

where qual1.qual2... are the qualifiers of the OS data set name or DOS file-id. When you use this form, you must code the periods separating the qualifiers.

- FILEDEF ddname mode DSN qual1 [qual2...]

This form allows you to specify the OS data set name or DOS file-id explicitly. (This form can be used for DOS file-ids only if they comply with the OS naming convention of 1- to 8-byte qualifiers separated by periods, to a maximum of 44 characters, including periods.) Again, the default value for the filename and filetype is FILE ddname. When you use this form, you must omit the periods that separate the qualifiers of the OS data set name. For example, for an OS data set or DOS file named MY.FILE.IN, you enter

```
FILEDEF ddname B1 DSN MY FILE IN
```

All of these forms have many variations, as is apparent from the command format.

Responses

```
| ddname1  device1  [filename1  filetype1  filemode1  [datasetname]]
| .        .        .        .        .        .
| .        .        .        .        .        .
| ddnameN  deviceN  [filenameN  filetypeN  filemoden  [datasetname]]
```

```
| A list of current definitions is displayed if the FILEDEF command
| is entered with no operands.
```

```
| DMSFLD069I DISK 'mode' NOT ACCESSED
```

```
| The specified disk is not accessed; the file definition remains in
| effect. You should access the disk before you attempt to read or
| write the file.
```

```
| DMSFLD220R ENTER DATA SET NAME:
```

```
| A FILEDEF command with the DSN ? operand was entered. Enter the
| exact OS or DOS file identification, including embedded periods and
| blanks.
```

```
| DMSFLD704I INVALID CLEAR REQUEST
```

```
| A CLEAR request was entered for a file definition that does not
| exist; no action is taken.
```

```
| DMSSTT228I USER LABELS BYPASSED ON DATA SET 'data set name'
```

```
| This message is displayed when you issue a FILEDEF command for an
| OS data set that contains user labels. The message is displayed the
| first time you issue the FILEDEF command after accessing the disk
| on which the data set resides.
```

Error Messages and Return Codes

DMSFLD003E INVALID OPTION 'option' RC=24
DMSFLD023E NO FILETYPE SPECIFIED RC=24
DMSFLD027E INVALID DEVICE 'device name' RC=24
DMSFLD029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD
RC=24
DMSFLD035E INVALID TAPE MODE RC=24
DMSFLD050E PARAMETER MISSING AFTER DDNAME RC=24
DMSFLD065E 'option' OPTION SPECIFIED TWICE RC=24
DMSFLD066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
DMSFLD070E INVALID PARAMETER 'parameter' RC=24
DMSFLD221E INVALID DATA SET NAME 'data set name' RC=24
DMSFLD224E FILEID ALREADY IN USE RC=24

FORMAT

FORMAT

Use the FORMAT command to:

- Initialize a virtual disk (minidisk) for use with CMS files.
- Count or reset the number of cylinders on a virtual disk.
- Write a label on a virtual disk.

The format of the FORMAT command is:

```
FORMAT | cuu mode [nocyl] [(options...[ ])]
        |
        |           options:
        |           [Label ]
        |           [Recomp]
        |
```

where:

cuu is the virtual device address of the virtual disk to be formatted.

Valid addresses are 001 through 5FF for a virtual machine in basic control mode and 001 through FFF for a virtual machine in extended control mode.

mode is the filemode letter to be assigned to the specified device address. Valid filemode letters are A, B, C, D, E, F, G, Y, and Z. This field must be specified. If any other disk is accessed at mode, it is released.

nocyl is the number of cylinders to be made available for use. All available cylinders on the disk are used if the number specified exceeds the actual number available.

Options:

LABEL writes a label on the disk without formatting the disk. A 6-character label is written on cylinder 0, track 0, record 3 of the virtual disk. A prompting message requests a 6-character disk label (fewer than 6 characters are left-justified and blank padded).

RECOMP changes the number of cylinders on the disk which are available to the user to the actual number of minidisk cylinders or to the number specified by nocyl, whichever is less. If nocyl is not specified, all cylinders are used.

Usage Notes

1. You can use the FORMAT command with any virtual 3330, 3340, 3350, or 2319 device.
2. When you do not specify either the RECOMP or LABEL option, the disk area is initialized by writing a device-dependent number of records (containing binary zeros) on each track. Any previous data on the

disk is erased. A read after write check is made as the disk is formatted. For example,

```
format 191 a 25
```

initializes 25 cylinders of the disk located at virtual address 191 in CMS format. The command

```
format 192 b 25 (recomp)
```

changes the number of cylinders available at virtual address 192 to 25 cylinders, but does not erase any existing data. To change only the label on a disk, you can enter:

```
format 193 c (label)
```

Respond to the prompting message with a 6-character label.

3. If you want to format a minidisk for VSAM files, you must use the IBCDASDI program. If you want to format an entire disk, you may use any OS or DOS disk initialization program.
4. You should try not to use the FORMAT command when there are many users on the system; system performance may be degraded.

Responses

```
DMSFOR603R FORMAT WILL ERASE ALL FILES ON DISK 'mode(cuu)'. DO YOU WISH
TO CONTINUE? (YES|NO):
```

You have indicated that a disk area is to be initialized: all existing files are erased. This message gives you the option of canceling the execution of the FORMAT command. Reply yes or no.

```
DMSFOR605R ENTER DISK LABEL:
```

You have requested that a label be written on the disk. Enter a 1- to 6-character label.

```
DMSFOR705I DISK REMAINS UNCHANGED.
```

The response to message, DMSFOR603R, was 'NO', or a null line was entered.

```
DMSFOR732I 'nnn' CYLINDERS FORMATTED ON DISK 'mode(ccu)'
```

The format operation is complete.

```
DMSFOR733I FORMATTING DISK 'mode'
```

The disk represented by mode letter 'mode' is being formatted.

```
mode (cuu): nnnn FILES, nnnnn REC IN USE, nnnnn LEFT (of nnnnn), nn%
FULL (nnn CYL), type, R/W
```

This message provides the status of a disk when you use the RECOMP option. The response is the same as when you issue the QUERY command with the DISK operand.

FORMAT

Other Messages and Return Codes

DMSFOR003E INVALID OPTION 'option' RC=24
DMSFOR017E INVALID DEVICE ADDRESS 'cuu' RC=24
DMSFCR028E NO DEVICE SPECIFIED RC=24
DMSFOR037E DISK 'mode[(cuu)]' IS READ/ONLY RC=36
DMSFOR048E INVALID MODE 'mode' RC=24
DMSFOR069E DISK 'mode' NOT ACCESSED RC=36
DMSFOR070E INVALID PARAMETER 'parameter' RC=24
DMSFOR113S DEVICE 'cuu' NOT ATTACHED RC=100
DMSFOR114S 'cuu' IS AN UNSUPPORTED DEVICE TYPE RC=88
DMSFOR125S PERMANENT UNIT CHECK ON DISK 'mode(cuu)' RC=100
DMSFOR126S ERROR {READ|WRIT}ING LABEL ON DISK 'mode(cuu)' RC=100
DMSFOR214W CANNOT RECOMPUTE WITHOUT LOSS OF DATA. NO CHANGE RC=8

GENDIRT

Use the GENDIRT command to fill in a CMS auxiliary directory. The auxiliary directory contains the name and location of modules which would otherwise significantly increase the size of the resident directory, thus increasing search time and storage requirements. By using GENDIRT to fill in an auxiliary directory, the file entries for the given command are loaded only when the command is invoked. The format of the GENDIRT command is:

```
GENDIRT | directoryname [targetmode]
```

where:

directoryname

is the entry point of the auxiliary directory.

targetmode

is the filemode letter of the disk containing the modules referred to in the directory. The letter is the filemode of the disk containing the modules at execution time, not the filemode of the disk at creation of the directory. The default value for targetmode is S (system disk). It is your responsibility to determine the usefulness of this operand at your installation, and to inform all users whose programs are in auxiliary directories exactly what filemode to specify on the ACCESS command.

Note: For information on creating auxiliary directories and for further requirements for using the targetmode option, see the VM/370: System Programmer's Guide.

Messages and Return Codes

```
DMSGND002W FILE 'fn ft fm' NOT FOUND RC=4
DMSGND021E ENTRY POINT 'name' NOT FOUND RC=40
DMSGND022E NO DIRECTORY NAME SPECIFIED RC=24
DMSGND070E INVALID PARAMETER 'parameter' RC=24
```


STR	invokes the CMS storage initialization routine when the MODULE file is subsequently loaded (see the LOADMOD command description). This routine frees any storage remaining from a previous program. STR is the default setting if the MODULE is to be loaded at the beginning of available user storage.
NOSTR	indicates that, when the MODULE is loaded, free storage pointers are not reset for any storage currently in use. NOSTR is the default setting if the MODULE file is to be loaded at a location other than the default load address.
SYSTEM	indicates that when the MODULE file is subsequently loaded, it is to have a storage protect key of zero.
OS	indicates that the program may contain OS macros, and, therefore, should be executed only when CMS/DOS is not active.
DOS	indicates that the program contains DOS macros; CMS/DOS must be active (that is, SET DOS ON must have been previously invoked) in order for this program to execute (See Usage Note 2).
ALL	indicates that the program: <ul style="list-style-type: none"> • Contains CMS macros and must be capable of running regardless of whether CMS/DOS is active or not. • Contains no DOS or OS macros. • Preserves and resets the DOS flag in the CMS nucleus. • Does its own setting of the DOS flags. <p><u>Note:</u> The ALL option is primarily for use by CMS system programmers. CMS system routines are aware of which environment is active, and will preserve and reset the DOS flag in the CMS nucleus.</p>

Usage Notes

1. The GENMOD command is usually invoked following the LOAD, and possibly INCLUDE commands. For example, the sequence

```
load myprog
genmod testprog
```

loads the file MYPROG TEXT into virtual storage and creates a nonrelocatable load module named TESTPROG MODULE. TESTPROG may now be invoked as a user-written command from the CMS environment.
2. It is not recommended that general users create MODULE files of DOS programs. In order for a MODULE file to execute properly under CMS/DOS, storage must be properly initialized.
3. Before the file is written, undefined symbols are set to location zero and the common reference control section is initialized. The undefined symbols are not retained as unresolved symbols in the MODULE file. Therefore, once the MODULE file is generated, those references cannot be resolved and may cause unpredictable results during execution.
4. If you load a program into the transient area you should issue the GENMOD command with the STR option. Be careful if the program uses OS GETMAIN or FREEMAIN macros because your program, plus the amount

GENMOD

of storage obtained via GETMAIN, cannot exceed two pages (8192 bytes). It is recommended that you do not use GETMAIN macros in programs that execute in the transient area.

- | 5. A transient module (loaded with the ORIGIN TRANS option) that was
| generated with the SYSTEM option is written on disk as a
| fixed-length record with a maximum length of 8192 bytes.

Responses

None.

Messages and Return Codes

```
DMSMOD003E INVALID OPTION 'option' RC=24
DMSMOD005E NO {FROM|TO} ENTRY SPECIFIED RC=24
DMSMOD021E ENTRY POINT 'name' NOT FOUND RC=40
DMSMOD032E INVALID FILETYPE 'ft' RC=24
DMSMOD037E DISK 'mode' IS READ/ONLY RC=36
DMSMOD040E NO FILES LOADED RC=40
DMSMOD070E INVALID PARAMETER 'parameter' RC=24
DMSMOD084E INVALID USE OF 'FROM' AND 'TO' OPTIONS RC=24
DMSMOD105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
| DMSSTT048E INVALID MODE 'mode' RC=24
| DMSSTT069E DISK 'mode' NOT ACCESSED RC=36
```

GLOBAL

Use the GLOBAL command to identify which CMS or CMS/DOS libraries are to be searched for macros, copy files, subroutines, or DOS executable phases when processing subsequent CMS commands. The format of the GLOBAL command is:

```
Global | { MACLIB } [libname1 ... libname8]
        | { TXTLIB }
        | { DOSLIB }
```

where:

MACLIB precedes the specification of macro libraries that are to be searched for macros and copy files during the execution of language processor commands. The macro libraries may be CMS files or OS data sets. If you specify an OS data set, a FILEDEF command must be issued for the data set before you issue the GLOBAL command.

TXTLIB precedes the specification of text libraries to be searched for missing subroutines when the LOAD or INCLUDE command is issued, or when a dynamic load occurs (that is, when an OS SVC 8 is issued).

Note: Subroutines that are called by dynamic load should (1) contain only VCONS that are resolved within the same text library member or (2) be resident in storage throughout the processing of the original CMS LOAD or INCLUDE command. Otherwise, the entry point is unpredictable.

DOSLIB precedes the specification of DOS simulated core image libraries (that is, CMS/DOS phase libraries) to be searched for missing phases. This operand does not apply to system or private core image libraries residing on DOS/VS disks. DOSLIB can be specified regardless of whether the CMS/DOS environment is active or not.

libname1... is the filename of up to eight libraries. Filetypes must be MACLIB, TXTLIB, and DOSLIB, accordingly. The libraries are searched in the order in which they are named. If no library names are specified, the command cancels the effect of any previous GLOBAL command.

Usage Notes

1. A GLOBAL command remains in effect for an entire CMS session unless it is explicitly canceled or reissued. If a program failure forces you to re-IPL CMS, you must reissue the GLOBAL command.
2. There are no default libraries; if you wish to use the same libraries during every terminal session, place the GLOBAL command(s) in your PROFILE EXEC.
3. If you want to use an OS library during the execution of a language processor, you can issue a GLOBAL command to access the library, as long as you have defined the library via the FILEDEF command. If you want to use that library for more than one job, however, you should use the PERM option on the FILEDEF command, since the language processors clear nonpermanent file definitions.

GLOBAL

4. You can find out what libraries have been specified by issuing the QUERY command with the MACLIB, TXTLIB, DOSLIB or LIBRARY operands. (The LIBRARY operand requests a display of all libraries.)
5. For information on creating and/or manipulating CMS libraries, see the discussion of the MACLIB, TXTLIB and DOSLIB commands.

Responses

None.

Messages and Return Codes

DMSGLE002W FILE 'fn ft' NOT FOUND RC=28
DMSGLE014E INVALID FUNCTION 'function' RC=24
DMSGLE047E NO FUNCTION SPECIFIED RC=24
DMSGLE108S MORE THAN 8 LIBRARIES SPECIFIED RC=88

INCLUDE

Use the INCLUDE command to read one or more TEXT files (containing relocatable object code) from disk and to load them into virtual storage, establishing the proper linkages between the files. A LOAD command must have been previously issued for the INCLUDE command to produce desirable results. For information on the CMS loader and the handling of unresolved references, see the description of the LOAD command. The format of the INCLUDE command is:

```

Include | fn... [ (options...[]) ]
        | options:
        |   [ CLEAR ]   [ RESET {entry} ] [ ORIGIN {hexloc} ]
        |   [ NOCLEAR ] [ * ]           [ TRANS ]
        |
        |   [ MAP ]     [ TYPE ]     [ INV ]     [ REP ]     [ AUTO ]
        |   [ NOMAP ]  [ NOTYPE ]   [ NOINV ]  [ NOREP ]  [ NOAUTO ]
        |
        |   [ LIBE ]    [ START ]    [ SAME ]    [ DUP ]
        |   [ NOLIBE ] [          ] [          ] [ NODUP ]
  
```

where:

fn... are the names of the files to be loaded into storage. Files must have a filetype of TEXT and consist of relocatable object code such as that produced by the OS language processor. If a GLOBAL TXTLIB command has identified one or more TXTLIBS, fn may indicate the name of a TXTLIB member.

Options: If options were specified with a previous LOAD or INCLUDE command, these options (with the exception of CLEAR and ORIGIN) remain set if SAME is specified when INCLUDE is issued. Otherwise, the options assume their default settings. If conflicting options are specified, the last one entered is in effect.

CLEAR clears the load area in storage to binary zeros before the files are loaded.

NOCLEAR does not clear the load area before loading.

RESET {entry} resets the execution starting point previously set by a LOAD or INCLUDE command. If entry is specified, the starting execution address is reset to the specified location. If an asterisk (*) is specified, the starting address is reset to the default entry point.

ORIGIN {hexloc}
 { TRANS }
 | begins loading the program at the location specified
 | by hexloc. The variable, hexloc, is a hexadecimal
 | number of up to 6 characters. If this option is not
 | specified, loading begins at the next available
 | storage location. INCLUDE does not overlay any
 | previously loaded files unless this option is

INCLUDE

specified and the address given indicates a location within a previously loaded object module. TRANS indicates that the file is loaded into the transient area.

<u>MAP</u>	adds information to the load map.
NOMAP	does not add any information to the load map.
TYPE	displays the load map of the files at the terminal, as well as writing it on the A-disk. This option is valid only if MAP is specified or implied.
<u>NCTYPE</u>	does not display the load map at the terminal.
<u>INV</u>	writes invalid card images in the LOAD MAP file.
NOINV	does not write invalid card images in the LOAD MAP file.
<u>REP</u>	writes Replace (REP) statement images in the LOAD MAP file. See the explanation of the CMS LOAD command for a description of the Replace (REP) statement.
NOREP	suppresses the writing of Replace (REP) statements in the LOAD MAP file.
<u>AUTO</u>	searches your disks for TEXT files to resolve undefined references.
NOAUTO	suppresses automatic searching for TEXT files.
<u>LIBE</u>	searches the text libraries defined by the GLOBAL command for missing subroutines.
NOLIBE	does not search any text libraries for unresolved references.
START	begins execution after loading is completed.
SAME	retains the same options (except ORIGIN and CLEAR) that were used by a previous INCLUDE or LOAD command. Otherwise, the default setting of unspecified options is assumed. If other options are specified with SAME, they override previously specified options. (See Usage Note 1.)
<u>DUP</u>	displays warning messages at your virtual console when a duplicate CSECT is encountered during processing. The duplicate CSECT is not loaded.
NODUP	does not display warning messages at your virtual console when duplicate CSECTs are encountered during processing. The duplicate CSECT is not loaded.

Usage Notes

1. If you have specified several non-default options on the LOAD command, and you want those options to remain in effect, you should use the SAME option when you issue the INCLUDE command, for example,

include main subi data (reset main map start)

brings the files named MAIN TEXT, SUBI TEXT, and DATA TEXT into virtual storage and appends them to files which were previously loaded. Information about these loaded files is added to the LOAD MAP file. Execution begins at entry point MAIN.

```
load myprog (nomap nolibe norep)
```

```
include mysub (map same)
```

During execution of the LOAD command, the file named MYPROG TEXT is brought into real storage. The following options are in effect: NOMAP, NOLIBE, NOREP, NOTYPE, INV, AUTO. During execution of the INCLUDE command, the file named MYSUB TEXT is appended to MYPROG TEXT. The following options are in effect:

```
MAP, NOLIBE, NOREP, NOTYPE, INV, AUTO
```

- For additional information on the CMS loader, see the discussion of the LOAD command, or consult VM/370: CMS User's Guide.

Responses

DMSLIO740I EXECUTION BEGINS...

START was specified with INCLUDE and the loaded program has begun execution. Any further responses are from the program.

INVALID CARD - xxx...xxx

INV was specified with LOAD and an invalid card has been found. The message and the contents of the invalid card (xxx...xxx) are listed in the LOAD MAP file. The invalid card is ignored and loading continues.

Other Messages and Return Codes

```
| DMSLGT002I FILE 'fn' TXTLIB NOT FOUND RC=0
DMSLIO001E NO FILENAME SPECIFIED RC=24
DMSLIO002E FILE 'fn ft' NOT FOUND RC=28
DMSLIO003E INVALID OPTION 'option' RC=24
DMSLIO005E NO 'option' SPECIFIED RC=24
DMSLIO021E ENTRY POINT 'name' NOT FOUND RC=40
DMSLIO029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD
RC=24
DMSLIO055E NO ENTRY POINT DEFINED RC=40
DMSLIO056E FILE 'fn ft' CONTAINS INVALID [NAME|ALIAS|ENTRY|ESD] RECORD
FORMATS RC=32
| DMSLIO099E CMS/DOS ENVIRONMENT ACTIVE RC=40
DMSLIO104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSLIO105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSLIO109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
DMSLIO116S LOADER TABLE OVERFLOW RC=104
DMSLIO168S PSEUDO REGISTER TABLE OVERFLOW RC=104
DMSLIO169S ESDID TABLE OVERFLOW RC=104
DMSLIO201W THE FOLLOWING NAMES ARE UNDEFINED: RC=4
DMSLIO202W DUPLICATE IDENTIFIER 'identifier' RC=4
DMSLIO203W "SET LOCATION COUNTER" NAME 'name' UNDEFINED RC=4
DMSLIO206W PSEUDO REGISTER ALIGNMENT ERROR RC=4
DMSLIO907T I/O ERROR ON FILE 'fn ft fm' RC=256
```

LISTDS

LISTDS

Use the LISTDS command to list, at your terminal, information about the data sets or files residing on accessed OS or DOS disks, or to display extent or free space information when you want to allocate space for VSAM files. The format of the LISTDS command is:

```
LISTDS [ ? ] { fm } [ (options...[ ] ) ]          options:
        | dsname | { * }                          [ FORMAT ]
        | [ ? ] |                                  [ PDS   ]
        | { fm } (FREE)                            [ EXTENT ]
        | { * } |
```

where:

? indicates that you want to enter the OS data set name, DOS file-id, or VSAM data space name interactively. When you enter a question mark (?), CMS prompts you to enter the OS data set name, DOS file-id, or VSAM data space name exactly as it appears on the disk. This form allows you to enter names that contain embedded blanks or hyphens.

dsname is the OS data set name or DOS file-id or VSAM data space name and takes the form:

qual1 [qual2 qualn]

where qual1, qual2 through qualn are 1- to 8-character qualifiers normally separated by periods. Each qualifier must be separated from other qualifiers by blanks when you enter them this way. (See Usage Note 1.)

fm is the filemode of the disk to be searched for the specified file. If a dsname is not specified, a list of all the files or data sets on the specified disk is displayed.

* indicates that you want all of your accessed DOS or OS disks searched for the specified data set or file. If a dsname is not specified, a list of all files on all accessed OS and DOS disks is displayed.

Options: The FREE and EXTENT options are mutually exclusive; the FORMAT and PDS options cannot be specified with either FREE or EXTENT.

FREE requests a display of all free space extents on a specific minidisk or on all accessed DOS and OS disks. If you enter the FREE option, you cannot specify a dsname.

EXTENT requests a display of allocated extents for a single file, or for an entire disk or minidisk. If a dsname is specified, only the extents for that particular file or data set are listed; if fm is specified as *, all disks are searched for extents occupied by that file.

If a dsname is not specified, then a list of all currently allocated extents on the specified disk, or on all disks, is displayed.

FORMAT requests a display of the date, disk label, filemode, and data set name for an OS data set as well as RECFM, LRECL, BLKSIZE, and DSORG information. For a DOS file, LISTDS displays the date, disk label, filemode, and file-id, but gives no information about the RECFM, LRECL, and BLKSIZE (two blanks appear for each); DSORG is always PS.

PDS displays the member names of referenced OS partitioned data sets.

For examples of the displays produced as a result of each of these options, see the "Responses" section, below.

Usage Notes

1. If you want to enter an OS or DOS file identification on the LISTDS command line, it must consist of 1- to 8-character qualifiers separated by periods. For example, the file TEST.INPUT.SOURCE.D could be listed as follows:

```
listds test input source d *
```

Or, you can enter the name interactively, as follows:

```
listds ? *
DMSLDS220R ENTER DATA SET NAME:
test.input.source.d
```

Note that when the data set name is entered interactively, it must be entered in its exact form; when entered on the LISTDS command line, the periods must be omitted.

You must use the interactive form to enter a DOS file-id that contains embedded blanks or hyphens.

2. You should use the FREE option to determine what free space is available for allocation by VSAM when you are using Access Method Services. For example,

```
listds * (free

requests a display of unallocated extents on all accessed OS or DOS disks. You can then use the EXTENT option on the DLBL command when you define the file for AMSERV.
```

Responses

DMSLDS220R ENTER DATA SET NAME:

This message prompts you to enter the data set name when you use the ? operand on the LISTDS command. Enter the file identification in its exact form. A sample sequence might be:

```
listds ? c
DMSLDS220R ENTER DATA SET NAME:
my.file.test
FM DATA SET NAME
C MY.FILE.TEST
R;
```

The response shown above following the entry of the data set name is the same as the response given when you enter a data set name on the LISTDS command line.

LISTDS

DMSLDS229I NO MEMBERS FOUND

This message is displayed when you use the PDS option and the data set has no members.

DMSLDS233I NO FREE SPACE AVAILABLE ON 'fm' DISK

This message is displayed when you use the FREE option and there is no free space available on the specified disk.

| Responses to the EXTENT Option: A sample response to the EXTENT option is shown below. The headers and the type of information supplied are the same when you request information for a specific file only, or for all disks.

```
| listds g (extent
|
| EXTENT INFORMATION FOR 'VTOC' ON 'G' DISK:
| SEQ TYPE CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 000 VTOC 099 00 1881 099 18 1899 19
|
| EXTENT INFORMATION FOR 'PRIVAT.CORE.IMAGE.LIB' ON 'G' DISK:
| SEQ TYPE CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 000 DATA 000 01 1 049 18 949 949
|
| EXTENT INFORMATION FOR 'SYSTEM.WORK.FILE.NO.6' ON 'G' DISK:
| SEQ TYPE CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 000 DATA 050 00 950 051 18 987 38
|
| EXTENT INFORMATION FOR 'COBOL TEST PROGRAM' ON 'G' DISK:
| SEQ TYPE CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 000 DATA 052 02 990 054 01 1027 38
|
| EXTENT INFORMATION FOR 'DKSQ01A' ON 'G' DISK:
| SEQ TYPE CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 000 DATA 080 01 1521 081 00 1539 19
```

| where:

| SEQ indicates the sequence number assigned this extent when the extents were defined via the DLBL command. CMS assigns the sequence numbers for VSAM data sets; the first extent set has a sequence of 000, the second extent has a sequence of 001, and so on.

| TYPE can be DATA, VTOC, SPLIT, LABEL, INDEX or OVFL0.

| DATA refers to a data area extent.
| VTOC refers to the VTOC extent of the disk.
| SPLIT refers to a split cylinder extent.
| LABEL refers to a user label extent.
| INDEX refers to an ISAM index area extent.
| OVFL0 refers to an ISAM independent overflow area extent.

| CYL-HD (RELTRK) TO CYL-HD (RELTRK)
| indicates the cylinder, head, and relative track numbers of the start and end tracks of this extent.

| TRACKS indicates the number of tracks in the extent.

| Response to the FREE Option: A sample response to the FREE option is shown below. The same headers and type of information is shown when you request free information for all accessed disks.

```

| listds g (free
| FREESPACE EXTENTS FOR 'G' DISK:
| CYL-HD (RELTRK) TO CYL-HD (RELTRK) TRACKS
| 052 00 988 052 01 989 2
| 054 02 1028 080 00 1520 493
| 081 01 1540 098 18 1880 341

```

| where:

| CYL-HD (RELTRK) TO CYL-HD (RELTRK)
| indicates the cylinder, head and relative track numbers of the
| starting and ending track in the free extent.

| TRACKS indicates the total number of free tracks in the extent.

Response to the FORMAT and PDS Options: If you enter the FORMAT and PDS options, you receive information similar to the following:

```

listds d (fo pds)

RECFM LRECL BLKSI DSORG DATE LABEL FM DATA SET NAME
FB 80 800 PO 01/31/75 OSSYS1 D SYS1.MACLIB
MEMBER NAMES:
ABEND ATTACH BLDL BSP CLOSE DCB DETACH DEVTYPE
FIND PUT READ WRITE XDAP
RECFM LRECL BLKSI DSORG DATE LABEL FM DATA SET NAME
F 80 80 PS 01/10/75 OSSYS1 D SAMPLE

```

Other Messages and Return Codes

```

DMSLDS002E DATA SET NOT FOUND RC=28
DMSLDS003E INVALID OPTION 'option' RC=24
DMSLDS048E INVALID MODE 'mode' RC=24
DMSLDS069E DISK 'mode' NOT ACCESSED RC=36
| DMSLDS117E INVALID EXTENT FOUND FOR 'data set name' ON 'fm' DISK RC=24
DMSLDS221E INVALID DATA SET NAME RC=24
| DMSLDS222E I/O ERROR READING 'data set name' FROM {fm|OS|DOS} DISK
RC=28
DMSLDS223E NO FILEMODE SPECIFIED RC=24
| DMSLDS226E NO DATA SET NAME ALLOWED WITH FREE OPTION RC=24
| DMSLDS227W INVALID EXTENT FOUND FOR 'datasetname' ON {fm|OS|DOS} DISK
| RC=4
| DMSLDS231E I/O ERROR READING VTOC FROM {fm|OS|DOS} DISK RC=28

```

LISTFILE

LISTFILE

Use the LISTFILE command to obtain specified information about CMS files residing on accessed disks. The format of the LISTFILE command is:

listfile	[fn	[ft	[fm]]	[(options...[])]			
		[*		[*		[*]]				
		[[[]]				
		<u>options:</u>									
			[Header]	[Exec]	[FName]
			[NOHeader]	[APPend]	[FType]
									[FMode]
									[FOrmat]
									[ALloc]
									[Date]
									[Label]

where:

- fn is the filename of the files for which information is to be collected. If an asterisk is coded in this field, all filenames are used. If you code an asterisk preceded by any number of characters, then files that begin with the specified characters are listed.
- ft is the filetype of the files for which information is to be collected. If an asterisk is coded in this field, all filetypes are used. If you code an asterisk preceded by any number of characters, then files that begin with the specified characters are listed.
- fm is the filemode of the files for which information is to be collected. If this field is omitted, only the A-disk is searched. If an asterisk is coded, all disks are searched.

Output Format Options:

HEADER includes column headings in the listing. HEADER is the default if any of the supplemental information options (FORMAT, ALLOCATE, DATE, LABEL) are specified. The format of the heading is:

```
FILENAME FILETYPE FM FORMAT RECS BLOCKS DATE TIME LABEL
```

NOHEADER does not include column headings in the list. NOHEADER is the default if only filename, filetype, or filemode information is requested.

Output Disposition Options:

EXEC creates a CMS EXEC file of 80-character records (one record for each of the files which satisfies the given file identifier) on your A-disk. If a CMS EXEC already exists, it is replaced. The header is not included in the file.

APPEND creates a CMS EXEC and appends it to the existing CMS EXEC file. If no CMS EXEC file exists, one is created.

Information Request Options: Only one of these options need be specified. If one is specified, any options with a higher priority are also in effect. If none of the following options are specified, the default information request options are in effect.

Default Information Request Options:

FNAME creates a list containing only filenames. Option priority is 7.

FTYPE creates a list containing only filenames and filetypes. Option priority is 6.

FMODE creates a list containing filenames, filetypes, and filemodes. Option priority is 5.

Supplemental Information Options:

FORMAT includes the record format and logical record length of the of each file in the list. Option priority is 4.

ALLOC includes the amount of disk space that CMS has allocated to the specified file in the list. The quantities given are the number of 800-byte blocks and the number of logical records in the file. Option priority is 3.

DATE includes the date the file was last written in the list. The form of the date is:

month/day/year hour:minute

Option priority is 2.

LABEL includes the label of the disk on which the file resides in the list. Option priority is 1.

Usage Notes

1. If you enter the LISTFILE command with no operands, a list of all files on your A-disk is displayed at the terminal. If you enter

```
listfile a* f* c
```

you might see the display

```
AARDVARK  FILE      C5
ANNA      FILEDATA  C1
AUTHOR    FLINDEX   C1
```

2. If you request any additional information with the supplemental information options, that information is also displayed, along with the header.
3. When you use the EXEC or APPEND option, the CMS EXEC A1 that is created is in the format

```
&1 &2 filename filetype fm ...
```

where column 1 is blank.

LISTFILE

If you use any of the supplemental information options, that information is included in the EXEC file. For information on using CMS EXEC files, VM/370: CMS User's Guide.

Responses

If the EXEC or APPEND option is not specified, the requested information is displayed at the terminal. Depending on the options specified, or discussed above, the information displayed is:

FILENAME	FILETYPE	FM	FORMAT	RECS	BLOCKS	DATE	TIME	LABEL	
fn	ASSEMBLE	fm	$\left. \begin{matrix} F \\ V \end{matrix} \right\}$	lrecl	norecs	noblks	mm/dd/yy	hh:mm	valid
:	:	:	:	:	:	:	:	:	:
:	:	:	:	:	:	:	:	:	:
:	:	:	:	:	:	:	:	:	:

One entry is displayed for each file listed.

where:

fn is the filename of the file.

ft is the filetype of the file.

fm is the filemode of the file

$\left. \begin{matrix} F \\ V \end{matrix} \right\}$ is the file format: F is fixed-length, V is variable-length.

lrecl is the logical record length of the largest record in the file.

norecs is the number of logical records in the file.

noblks is the number of physical blocks that the file occupies on disk.

mm/dd/yy is the date (month/day/year) that the file was created.

hh:mm is the time (hours:minutes) that the file was created.

valid is the volume serial number of the virtual disk on which the file resides.

Other Messages and Return Codes

```
DMSLST002E FILE NOT FOUND RC=28
DMSLST003E INVALID OPTION 'option' RC=24
DMSLST037E DISK 'mode' IS READ/ONLY RC=36
DMSLST048E INVALID MODE 'mode' RC=24
DMSLST066E 'option' and 'option' ARE CONFLICTING OPTIONS RC=24
DMSLST069E DISK 'mode' NOT ACCESSED RC=36
DMSLST070E INVALID PARAMETER 'parameter' RC=24
DMSLST105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
```

Note: You can invoke the LISTFILE command from the terminal, from an EXEC file, or as a function from a program. If LISTFILE is invoked as a function or from an EXEC file that has the &CONTROL NOMSG option in effect, the DMSLST002E FILE NOT FOUND error message is not issued.

| LISTIO

| Use the LISTIO command in CMS/DOS to display a list of current assignments for system and/or programmer logical units in your virtual machine. The format of the LISTIO command is:

```
| LISTIO | { SYS
|         | { PROG
|         | { SYSxxx } [ (options...[]) ]
|         | { A
|         | { UA
|         | { ALL }
|         |
|         | options:
|         | [ EXEC ] [ STAT ]
|         | [ APPEND ]
```

| where:

| SYS requests a list of the physical devices assigned to all system logical units.

| PROG requests a list of the physical devices assigned to programmer logical units SYS000 through SYS241.

| SYSxxx requests a display of the physical device assigned to the particular logical unit specified.

| A requests a list of only those logical units that have been assigned to physical devices.

| UA requests a list of only those logical units that have not been assigned to physical devices, that is, that are unassigned.

| ALL requests a list of the physical units assigned to all system and programmer logical units. If no operand is specified, ALL is the default.

| Options: The EXEC and APPEND options are mutually exclusive; if both are entered on the command line, the last one entered is in effect.

| EXEC erases the existing \$LISTIO EXEC file, if one exists, and creates a new one.

| APPEND adds new entries to the end of an existing \$LISTIO EXEC file. If no \$LISTIO EXEC file exists, a new one is created.

| STAT lists the status (read-only or read/write) of all disk devices current assigned.

| Usage Notes

| 1. Logical units are assigned and unassigned with the ASSGN command. For a list of logical units and valid device types, see the discussion of the ASSGN command.

| 2. The \$LISTIO EXEC contains one record for each logical unit listed. The format is:

```
|      &1 &2 SYSxxx { device
|                    { mode [status] }
```

| where column 1 is blank.

LISTIO

| Responses

| Depending on the operands specified, the following is displayed for each
| unit requested in the LISTIO command:

```
|     SYSxxx {device  
|             {mode [status]}}
```

| where device is the device type (READER, PRINTER, PUNCH, TERMINAL, TAPn,
| IGN, or UA). If the device is a disk, the 1-character mode letter is
| displayed. If the STAT option is specified, the status (R/O or R/W) is
| also displayed.

| Other Messages and Return Codes

```
| DMSLLU003E INVALID OPTION 'option' RC=24  
| DMSLLU006E NO READ/WRITE 'A' DISK ACCESSED RC=36  
| DMSLLU070E INVALID PARAMETER 'parameter' RC=24  
| DMSLLU099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40  
| DMSLLU105S ERROR 'nn' WRITING FILE '$LISTIO EXEC A1' ON DISK RC=100
```

LOAD

Use the LOAD command to read one or more CMS or OS TEXT files (containing relocatable object code) from disk and to load them into virtual storage, establishing the proper linkages between the files. The format of the LOAD command is:

```

LOAD |  fn ...  [ (options...[]) ]
      |
      |  options:  [ CLEAR ]   [ RESET {entry} ]   [ ORIGIN {hexloc} ]
      |              [ NOCLEAR ] [ { * } ]         [ TRANS ]
      |
      |  [ MAP ]   [ TYPE ]   [ INV ]   [ REP ]   [ AUTO ]
      |  [ NOMAP ] [ NOTYPE ] [ NOINV ] [ NOREP ] [ NOAUTO ]
      |
      |  [ LIBE ]   [ START ] [ DUP ]
      |  [ NOLIBE ] [ NODUP ]

```

where:

fn... specifies the names of the files to be loaded into storage. The files must have a filetype of TEXT and consist of relocatable object code such as that produced by the OS language processors. If a GLOBAL TXTLIB command has been issued, fn may indicate the name of a TXTLIB member.

Options: If conflicting options are specified, the last one entered is in effect. Options may be overridden or added when you use the INCLUDE command to load additional TEXT files.

CLEAR clears the load area in storage before the object files are loaded. Whole page frames are released; the remainder of storage that is not on a page boundary is set to binary zeros.

NOCLEAR does not clear the load area before loading.

RESET {entry}
 *
 sets the starting location for the programs currently loaded. The operand, entry, must be an external name (for example, CSECT or ENTRY) in the loaded programs. If RESET is not specified, the default entry point is used. (See Usage Note 4.) If * is entered the results are the same as if the RESET option were omitted.

ORIGIN {hexloc}
 TRANS
 loads the program beginning at the location specified by hexloc; this location must be in the CMS nucleus transient area or in the user area. The location, hexloc, is a hexadecimal number of up to 6 characters. If TRANS is specified, the file is loaded into the CMS nucleus transient area. If ORIGIN is not specified, loading begins at the first available storage location in the user program area.

LOAD

Note: Any program loaded into the transient area must have a starting address of X'E000'. See the discussion of the GENMOD command for information on loading programs in the transient area.

- MAP writes a load map on your A-disk, named LOAD MAP A5.
- NOMAP does not create the LOAD MAP file.
- TYPE displays the load map at your terminal, as well as writing it on the A-disk. This option is valid only if the MAP option is in effect.
- NOTYPE does not display the load map at the terminal.
- INV includes invalid card images in the load map.
- NOINV does not include invalid card images in the load map.
- REP includes Replace (REP) statements in the load map.
- NOREP does not include the Replace (REP) statements in the load map.
- AUTO searches your virtual disks for TEXT files to resolve undefined references.
- NOAUTO suppresses automatic searching for TEXT files.
- LIBE searches the text libraries for missing subroutines. If text libraries are to be searched for TEXT files, they must previously have been defined by a GLOBAL command.
- NCLIBE does not search the text libraries for unresolved references.
- START executes the program being loaded when loading is completed. LOAD does not normally begin execution of the loaded files. To begin execution immediately upon successful completion of loading, specify START. Execution begins at the default entry point (See Usage Note 4).
- DUP displays warning messages at your terminal when a duplicate CSECT is encountered during processing. The duplicate CSECT is not loaded. (See Usage Note 3.)
- NODUP does not display warning messages at your terminal when duplicate CSECTs are encountered during processing. The duplicate CSECT is not loaded.

Usage Notes

1. You must have a read/write CMS A-disk accessed when you issue the LOAD command; the loader creates a temporary workfile named DMSLDR SYSUT1 and writes it on the A-disk.

2. Unless the NOMAP option is specified, a load map is created on the A-disk each time the LOAD command is issued. A load map is a file that contains the location of control sections and entry points of files loaded into storage. This load map is named LOAD MAP A5. Each time LOAD is issued, a new LOAD MAP file replaces any previous LOAD MAP file.

If invalid card images exist in the file or files that are being loaded, they are listed with the message INVALID CARD in the LOAD MAP file. To suppress this listing in the load map, use the NOINV option.

If replace (REP) statements exist in the file being loaded, they are included in the LOAD MAP file. To suppress this listing of REP statements, specify the NOREP option.

If the ENTRY or LIBRARY control cards are encountered in the file, the load map contains an entry

CONTROL CARD- ...

listing the card that was read.

3. Duplicate CSECTs (control sections) are bypassed by the loader. Only the first CSECT encountered is physically loaded. The duplicates are not loaded. A warning message is displayed at your terminal if you specified the DUP option.
4. The loader selects the entry point for the loaded program according to the following hierarchy:
 - From the parameter list on the START command.
 - From the last RESET operand in a LOAD or INCLUDE command.
 - From the last ENTRY statement in the input.
 - From the last LDT statement in the input.
 - From the first assembler- or compiler-produced END statement that specifies an entry point if no ENTRY statement is in the input.
 - From the first byte of the first control section of the loaded program if there is no ENTRY statement and no assembler- or compiler-produced END statement specifying an entry point.
5. The LOAD command should not be used to execute programs containing DOS macros. To link-edit and execute programs in the CMS/DOS environment, use the DOSLKED and FETCH commands.
6. See Figure 8 for an illustration of the loader search order. The loader uses this search order to locate the filename on the LOAD and INCLUDE command lines, as well as in the handling of unresolved references.
7. The CMS loader also loads routines called dynamically by OS LINK, LOAD, and XCTL macros. Under certain circumstances, an incorrect entry point may be returned to the calling program. See the VM/370: CMS User's Guide for more details.




Figure 8. Loader Search Order

Loader Control Statements

You can add loader control statements to TEXT files either by editing them, or by punching real cards and adding them to a punched text deck before reading it into your virtual machine. The five control cards recognized by the CMS loader are discussed below.

The ENTRY and LIBRARY cards, which are discussed first, are similar to the OS linkage editor control statements ENTRY and LIBRARY. The CMS ENTRY and LIBRARY statements must be entered beginning in column 1.

ENTRY Statement: The ENTRY statement specifies the first instruction to be executed. It can be placed before, between, or after object modules or other control statements. The format of the ENTRY statement is shown in Figure 9. The external name is the name of a control section or an entry name in the input deck. It must be the name of an instruction, not of data.

```

| ENTRY | external name |

```

Figure 9. ENTRY Statement Format

LIBRARY Statement: The LIBRARY statement can be used to specify the never-call function. The never-call function (indicated by an asterisk, *, as the first operand) specifies those external references that are not to be resolved by the automatic library call during any loader step. It is negated when a deck containing the external name referred to is included as part of the input to the loader. The format of the LIBRARY statement is shown in Figure 10. The external reference refers to an external reference that may be unresolved after input processing. It is not to be resolved. Multiple external references within the parentheses must be separated by commas. The LIBRARY statement can be placed before, between, or after object decks or other control statements.

```

| LIBRARY | * (external reference) |

```

Figure 10. LIBRARY Statement Format

LOAD

Loader Terminate (LDT) Statement: The LDT statement is used in a text library as the last record of a member. It indicates to the loader that all records for that member were processed. The LDT statement can contain a name to be used as the entry point for the loaded member. The LDT statement has the format shown in Figure 11.

Column	Contents
1	X'02' (12-2-9 punch). Identifies this as a loader control statement.
2-4	LDT — identifies type of statement.
5-16	Not used.
17-24	Blank or entry name (left justified and padded with blanks to 8 characters).
25	Blank
26-33	May contain information specified on a SETSS1 card processed by the TXTLIB command.
34-80	Not used.

Figure 11. LDT Statement Format

Include Control Section (ICS) Statement: The ICS statement changes the length of a specified control section or defines a new control section. It should be used only when REP statements cause a control section to be increased in length. The format of an ICS statement is shown in Figure 12. An ICS statement must be placed at the front of the file or TEXT file.

Column	Contents
1	X'02' (12-2-9 punch). Identifies this as a loader control statement.
2-4	ICS — identifies the type of load statement.
5-16	Blank.
17-22	Control section name — left-justified in these columns.
23	Blank.
24	, (comma).
25-28	Hexadecimal length in bytes of the control section. This must not be less than the actual length of the previously specified control section. It must be right-justified in columns with unused leading columns filled with zeros.
29	Blank.
30-72	May be used for comments or left blank.
73-80	Not used by the loader. You may leave these columns blank or insert program identification for your own convenience.

Figure 12. ICS Statement Format

Set Location Counter (SLC) Statement: The SLC statement sets the location counter used with the loader. The file loaded after the SLC statement is placed in virtual storage beginning at the address set by this SLC statement. The SLC statement has the format shown in Figure 13. It sets the location counter in one of three ways:

1. With the absolute virtual address specified as a hexadecimal number in columns 7-12.
2. With the symbolic address already defined as a program name or entry point. This is specified by a symbolic name punched in columns 17-22.
3. If both a hexadecimal address and a symbolic name are specified, the absolute virtual address is converted to binary and added to the address assigned to the symbolic name; the resulting sum is the address to which the loader's location counter is set. For example, if 0000F8 was specified in columns 7-12 of the SLC card image and GAMMA was specified in columns 17-22, where GAMMA has an assigned address of 006100 (hexadecimal), the absolute address in columns 7-12 is added to the address assigned to GAMMA giving a total of 0061F8. Thus, the location counter would be set to 0061F8.

Column	Contents
1	X'02' (12-2-9 punch). Identifies this as a loader control statement.
2-4	SLC -- identifies the type of load statement.
5-6	Blank.
7-12	Hexadecimal address to be added to the value of the symbol, if any, in columns 17-22. It must be right-justified in these columns, with unused leading columns filled with zeros.
13-16	Blank.
17-22	Symbolic name whose assigned location is used by the loader. Must be left-justified in these columns. If blank, the address in the absolute field is used.
23	Blank.
24-72	May be used for comments or left blank.
73-80	Not used by the loader. You may leave these columns blank or insert program identification for your own convenience.

Figure 13. SLC Statement Format

LOAD

Replace (REP) Statement: A REP statement allows instructions and constants to be changed and additions made. The REP statement must be punched in hexadecimal code. The format of a REP statement is shown in Figure 14. The data in columns 17-70 (excluding the commas) replaces what has already been loaded into virtual storage, beginning at the address specified in columns 7-12. REP statements are placed in the file either (1) immediately preceding the last statement (END statement) if the text deck does not contain relocatable data such as address constants, or (2) immediately preceding the first RLD (relocatable dictionary) statement if there is relocatable data in the text deck. If additions made by REP statements increase the length of a control section, an ICS statement, which defines the total length of the control section, must be placed at the front of the deck.

Column	Contents
1	X'02' (12-2-9 punch). Identifies this as a loader control statement.
2-4	REP -- identifies the type of load statement.
5-6	Blank.
7-12	Hexadecimal starting address of the area to be replaced as assigned by the assembler. It must be right-justified in these columns with unused leading columns filled with zeros.
13-14	Blank.
15-16	ESID (External Symbol Identification) -- the hexadecimal number assigned to the control section in which replacement is to be made. The LISTING file produced by the compiler or assembler indicates this number.
17-70	A maximum of 11 four-digit hexadecimal fields, separated by commas, each replacing one previously loaded halfword (two bytes). The last field must not be followed by a comma.
71-72	Blank.
73-80	Not used by the loader. This field may be left blank or program identification may be inserted.

Figure 14. REP Statement Format

Responses

DMSLI0740I EXECUTION BEGINS...

START was specified with LOAD and the loaded program starts execution. Any further responses are from the program.

INVALID CARD - xxx...xxx

INV was specified with LOAD and an invalid statement was found. The message and the contents of the invalid statement (xxx...xxx) are listed in the file LOAD MAP. The invalid statement is ignored and loading continues.

Other Messages and Return Codes

| DMSLGT002I FILE 'fn TXTLIB' NOT FOUND RC=0
DMSLIO001E NO FILENAME SPECIFIED RC=24
DMSLIO002E FILE 'fn ft' NOT FOUND RC=28
DMSLIO003E INVALID OPTION 'option' RC=24
DMSLIO005E NO 'option' SPECIFIED RC=24
DMSLIO021E ENTRY POINT 'name' NOT FOUND RC=40
DMSLIO029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD RC=24
DMSLIO055E NO ENTRY POINT DEFINED RC=40
DMSLIO056E FILE 'fn ft' CONTAINS INVALID [NAME|ALIAS|ENTRY|ESD] RECORD
FORMATS RC=32
| DMSLIO099E CMS/DOS ENVIRONMENT ACTIVE RC=40
DMSLIO104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSLIO105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSLIO109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
DMSLIO116S LOADER TABLE OVERFLOW RC=104
DMSLIO168S PSEUDO REGISTER TABLE OVERFLOW RC=104
DMSLIO169S ESDID TABLE OVERFLOW RC=104
DMSLIO201W THE FOLLOWING NAMES ARE UNDEFINED: RC=4
DMSLIO202W DUPLICATE IDENTIFIER 'identifier' RC=4
DMSLIO203W "SET LOCATION COUNTER" NAME 'name' UNDEFINED RC=4
DMSLIO206W PSEUDO REGISTER ALIGNMENT ERROR RC=4
DMSLIO907T I/O ERROR ON FILE 'fn ft fm' RC=256
DMSSTT062E INVALID * IN FILEID RC=20

LOADMOD

LOADMOD

Use the LOADMOD command to load a MODULE file into storage. The file must be in nonrelocatable format as created by the GENMOD command. The format of the LOADMOD command is:

```
LOADMod | fn [MODULE [fm]]
```

where:

fn is the filename of the file to be loaded into storage. The filetype must be MODULE.

fm is the filemode of the module to be loaded. If not specified, or specified as an asterisk, all your disks are searched for the file.

Usage Notes

1. You can use the LOADMOD command when you want to debug a CMS MODULE file. After the file is loaded, you may set address stops or breakpoints before you begin execution with the START command, for example:

```
loadmap prog1
cp adstop 210ae
start
```

2. If a MODULE file was created using the DOS option of the GENMOD command, the CMS/DOS environment must be active when it is loaded. If it was created using the OS option (the default), the CMS/DOS environment must not be active when it is loaded.

MODULE files created with the ALL option, or with SYSTEM option and loaded into the transient area, may be loaded regardless of whether the CMS/DOS environment is active. If the LOADMOD command is called from a program, the loading is also done regardless of whether the CMS/DOS environment is active.

Responses

None.

Messages and Return Codes

```
DMSMOD001E NO FILENAME SPECIFIED RC=24
DMSMOD002E FILE 'fn ft' NOT FOUND RC=28
DMSMOD032E INVALID FILETYPE 'ft' RC=24
DMSMOD070E INVALID PARAMETER 'parameter' RC=24
DMSMOD104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSMOD109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
| DMSMOD114E 'fn ft fm' NOT LOADED; CMS/DOS ENVIRONMENT [NOT] ACTIVE
  RC=40 or -5
DMSMOD116S LOADER TABLE OVERFLOW RC=104
| DMSSTT048E INVALID MODE 'mode' RC=24
```


MACLIB

| DISK writes the MAP output on a CMS disk with the file
| identifier of 'libname MAP A1'. If a file with that name
| already exists, the old file is erased. If no option is
| specified, DISK is the default.

| PRINT writes the file 'libname MAP A1' to your A-disk and
| spools a copy to the virtual printer.

Usage Notes

1. When a MACRO file is added to a MACLIB, the membername is taken from the macro prototype statement. If there is more than one macro definition in the file, each macro is written into a separate MACLIB member.

If the filetype is COPY and the file contains more than one macro, each macro must be preceded by a control statement of the following format:

*COPY membername

The name on the control statement is the name of the macro when it is placed in the macro library. If there is only one macro in the COPY file and it is not preceded by a COPY control statement, its name (in the macro library) is the same as the filename of the COPY file. If there are several macro definitions in a COPY file and the first one is not preceded by a COPY control statement the entire file is treated as one macro.

2. If any MACRO file contains invalid records between members the MACLIB command display an error message and terminates. Any members read up until the invalid card is encountered are already in the MACLIB. The MACLIB command ignores CATAL.S, END, and /* records when it reads MACRO files created by the ESERV program.
3. If you want a macro library searched during an assembly or compilation, you must identify it using the GLOBAL command before you begin compiling.
4. The MACLIBS distributed with the CMS system are: CMSLIB, OSMACRO, OSMACRO1, TSOMAC, and DOSMACRO.

Responses

When you enter the MACLIB MAP command with the TERM option, the names of the library members, their sizes, and locations in the library are displayed.

MACRO	INDEX	SIZE
name	loc	size
.	.	.
:	:	:
.	.	.

Other Messages and Return Codes

DMSLBM001E NO FILENAME SPECIFIED RC=24
| DMSLBM002E FILE 'fn ft' NOT FOUND RC=28
| DMSLBM002W FILE 'fn ft [fm]' NOT FOUND RC=4
DMSLBM003E INVALID OPTION 'option' RC=24
DMSLBM013W MEMBER 'name' NOT FOUND IN LIBRARY 'fn ft fm' RC=4
DMSLBM014E INVALID FUNCTION 'function' RC=24

| DMSLBM037E DISK 'mode' IS READ/ONLY RC=36
DMSLBM046E NO LIBRARY NAME SPECIFIED RC=24
DMSLBM047E NO FUNCTION SPECIFIED RC=24
DMSLBM056E FILE 'fn ft fm' CONTAINS INVALID RECORD FORMATS RC=32
DMSLBM070E INVALID PARAMETER 'parameter' RC=24
DMSLBM104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSLBM105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSLBM109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
DMSLBM157S MACLIB LIMIT EXCEEDED[, LAST MEMBER NAME ADDED WAS
'membername'] RC=88
DMSLBM167S PREVIOUS MACLIB FUNCTION NOT FINISHED RC=88
DMSLBM213W LIBRARY 'fn ft fm' NOT CREATED RC=4
DMSLBM907T I/O ERROR ON FILE 'fn ft fm' RC=256

MODMAP

MODMAP

Use the MODMAP command to display the load map associated with the specified MODULE file. The format of the MODMAP command is:

```
MODmap | fn
```

where:

fn is the filename of the MODULE file whose load map is to be displayed. The filetype of the file must be MODULE; all of your accessed disks are searched for the specified file.

Usage Note

1. You cannot issue a MODMAP command for modules that are CMS transient area modules or that have been created with the NOMAP option of the GENMOD command.

Responses

The load map associated with the file is displayed at the terminal, in the format:

name	location
.	.
.	.
.	.

Error Messages and Return Codes

```
DMSMDP001E NO FILENAME SPECIFIED RC=24
DMSMDP002E FILE 'fn ft' NOT FOUND RC=28
DMSMDP018E NO LOAD MAP AVAILABLE RC=40
DMSMDP070E INVALID PARAMETER 'parameter' RC=24
```


MOVEFILE

Use the MOVEFILE command to move data from any device supported by VM/370 to any other device supported by VM/370. The format of the MOVEFILE command is:

```

|-----|
| MOVEfile | [ inddname [ outddname ] ] [ (PDS[ ]) ]
|          | [ INMOVE [ OUTMOVE ] ]
|-----|

```

where:

inddname is the ddname representing the input file definition. If ddname is not specified, the default input ddname, INMOVE, is used.

outddname is the ddname representing the output file definition. If ddname is not specified, the default output ddname, OUTMOVE, is used.

Option:

PDS moves each of the members of the CMS MACLIB or TXTLIB or of an OS partitioned data set into a separate CMS disk file, with a filename equal to the member name and a filetype equal to the filetype of the output file definition.

Usage Notes

1. Use the FILEDEF command to provide file definitions for the ddnames used in the MOVEFILE command. If you use the ddnames INMOVE and OUTMOVE on the FILEDEF commands, then you do not need to specify them on the MOVEFILE command line. For example:

```

filedef inmove disk sys1 maclib b (member stow
filedef outmove disk stow macro
movefile

```

copies the member STOW from the OS partitioned data set SYS1.MACLIB into the CMS file STOW MACRO.

If you enter

```

filedef indd reader
fileder outdd printer
movefile indd outdd

```

a file is moved from your virtual card reader to your virtual printer.

2. To copy an entire OS partitioned data set into individual CMS files, you could enter

```

filedef test2 disk sys1 maclib b
filedef macro disk
movefile test2 macro (pds

```

These commands copy members from the OS partitioned data set SYS1.MACLIB or the CMS file SYS1 MACLIB into separate files, each

MOVEFILE

with a filename equal to the membername and a filetype of MACRO. Note that the output ddname was not specified in full, so that CMS assigned the default file definition (FILE ddname).

3. You cannot copy VSAM data sets with the MOVEFILE command.
4. The MOVEFILE command does not support data containing spanned records. Use of spanned records results in the error message DMSSOP036E and an error code of 7.

Default Device Attributes

If a record format (RECFM), blocksize (BLOCK), and logical record length (LRECL) are specified on the FILEDEF command, these values are used in the data control block (DCB) defining the characteristics of the move operation. If the FILEDEF was issued without the record format specification, that specification is taken from the default list shown in Figure 15. If the blocksize was not specified, the default blocksize is used. If the logical record length was not specified, the default logical record length is determined as follows: if the record format is F or U, the logical record length equals the blocksize; if the record format is V, the logical record length equals the blocksize minus 4.

Device	Input ddname		Output ddname	
	RECFM	Blocksize	RECFM	Blocksize
Card Reader	F	80	NA ²	NA ²
Card Punch	NA ²	NA ²	F	80
Printer	NA ²	NA ²	U	132
Terminal	U	130	U	130
Tape ¹	U	3600	RECFM of input ddname	Blocksize of input ddname
Disk file	RECFM of file	Blocksize of file	RECFM of input ddname	Blocksize of input ddname
Dummy	NA ²	NA ²	RECFM of input ddname	Blocksize of input ddname

¹If the default record format and blocksize are used in a tape-to-tape move operation and an input record is greater than 3600 bytes, it is truncated to 3600 bytes on the output tape.
²Not applicable.

Figure 15. Default Device Attributes for MOVEFILE Command

Responses

DMSMVE225I PDS MEMBER 'membername' MOVED

The specified member of an OS partitioned data set was moved successfully to a CMS file. This response is issued for each member moved when you use the PDS option.

DMSMVE226I END OF PDS MOVE

The last member of the partitioned data set was moved successfully to a CMS file.

DMSMVE706I TERM INPUT -- TYPE NULL LINE FOR END OF DATA

The input ddname in the MOVEFILE specified a device type of terminal. This message requests the input data; a null line terminates input.

DMSMVE708I DISK FILE 'FILE ddname A1' ASSUMED FOR DDNAME 'ddname'

No file definition is in effect for a ddname specified on the MOVEFILE command. The MOVEFILE issues the default FILEDEF command:

FILEDEF ddname DISK FILE ddname A1

If file ddname does not exist for the input file, MOVEFILE terminates processing.

Other Messages and Return Codes

DMSMVE002E FILE 'fn ft fm' NOT FOUND RC=28
 DMSMVE003E INVALID OPTION 'option' RC=24
 DMSMVE037E OUTPUT DISK 'mode' IS READ/ONLY RC=36
 DMSMVE041E INPUT AND OUTPUT FILES ARE THE SAME RC=40
 DMSMVE070E INVALID PARAMETER 'parameter' RC=24
 DMSMVE073E UNABLE TO OPEN FILE ddname RC=28
 DMSMVE075E DEVICE 'device name' ILLEGAL FOR {INPUT|OUTPUT} RC=40
 DMSMVE086E INVALID DDNAME 'ddname' RC=24
 DMSMVE127S UNSUPPORTED DEVICE FOR ddname RC=100
 DMSMVE128S I/O ERROR ON INPUT AFTER READING nnnn RECORDS: INPUT ERROR
 code ON ddname RC=100
 DMSMVE129S I/C ERROR ON OUTPUT WRITING RECORD NUMBER nnnn: OUTPUT ERROR
 code ON ddname RC=100
 DMSMVE130S BLOCKSIZE ON V FORMAT FILE ddname IS LESS THAN 8 RC=88

OPTION

| OPTION

| Use the OPTION command to change any or all of the options in effect for the DOS/VS COBOL compiler in CMS/DOS. The format of the OPTION command is:

```
| OPTION [options...]  
|  
| options:  
| [DUMP ] [DECK ] [LIST ] [LISTX ] [SYM ]  
| [NODUMP] [NODECK] [NOLIST] [NOLISTX] [NOSYM]  
|  
| [XREF ] [ERRS ] [48C]  
| [NOXREF] [NOERRS] [60C]
```

| Options: If an invalid option is specified on the command line, an error message is issued for that option; all other valid options are accepted. Only those options specified are altered, and all other options remain unchanged.

| **DUMP** dumps the registers and the virtual partition on the virtual SYSLST device in the case of abnormal program end.

| **NODUMP** suppresses the DUMP option.

| **DECK** punches the resulting object module on the virtual SYSPCH device. If you do not issue an ASSGN command for the logical unit SYSPCH before invoking the compiler, the text deck is written to your CMS A-disk.

| **NODECK** suppresses the DECK option.

| **LIST** writes the output listing of the source module on the SYSLST device.

| **NCLIST** suppresses the LIST option. This option overrides the XREF option as it does in DOS/VS.

| **LISTX** produces a procedure division map on the SYSLST device.

| **NOLISTX** suppresses the LISTX option.

| **SYM** prints a Data Division map on SYSLST.

| **NOSYM** suppresses the SYM option.

| **XREF** writes the output symbolic cross-reference list on SYSLST.

| **NOXREF** suppresses the XREF option.

| **ERRS** writes an output listing of all errors in the source program on SYSLST.

| **NOERRS** suppresses the ERRS option.

| **48C** Uses the 48-character set.

| **60C** Uses the 60-character set.

| Usage Notes

- | 1. If you enter the OPTION command with no options, all options are reset to their default values, that is, the default settings that are in effect when you enter the CMS/DOS environment. CMS/DOS defaults are not necessarily the same as the defaults generated on the DOS/VS system being used and do not include additional options that are available with some DOS compilers.
- | 2. The OPTION command has no effect on the DOS/VS PL/I compiler nor on any of the OS language compilers in CMS.

| Responses

| None. To display a list of options currently in effect, use the QUERY command with the OPTION operand.

| Error Messages and Return Codes

| DMSOPT070E INVALID PARAMETER 'parameter' RC=24
| DMSOPT099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40

PRINT

PRINT

Use the PRINT command to print a CMS file on the spooled virtual 1403 or 3211 printer. The format of the PRINT command is:

```
Print      fn ft [fm] [(options...[ ])]
           [* ]

           options: [CC] [LINECOUN {nn}]
                   [NOCC] [UPCASE] [55]
                   [MEMBER { * }
                   [membername] ] [HEX]
```

where:

fn is the filename of the file to be printed.

ft is the filetype of the file to be printed.

fm is the filemode of the file to be printed. If this field is specified as an asterisk (*), the standard order of search is followed and the first file found with the given filename and filetype is printed. If fm is not specified, the A-disk and its extensions are searched.

Options:

CC interprets the first character of each record as a carriage control character. If the filetype is LISTING, the CC option is assumed. If CC is in effect, the PRINT command does not perform page ejects or count the number of lines per page; these functions are controlled by the carriage control characters in the file. The LINECOUN option has no effect if CC is in effect.

NOCC does not interpret the first character of each record as a carriage control character. In this case, the PRINT command ejects a new page and prints a heading after the number of lines specified by LINECOUN are printed. If NOCC is specified, it is in effect even if CC was specified previously or if the filetype is LISTING.

UPCASE translates the lowercase letters in the file to uppercase for printing.

MEMBER { * }
MEM { membername }
prints the members of macro or text libraries. This option may be specified if the file is a simulated partitioned data set (filetype MACLIB or TXTLIB). If * is entered, all individual members of that library are printed. If a membername is specified, only that member is printed.

HEX prints the file in graphic hexadecimal format. If HEX is specified, the options CC and UPCASE are not in effect, even if specified, and even if the filetype is LISTING.

LINECOUN { nn }
 { 55 }

allows you to set the number of lines to be printed on each page. nn can be any decimal number from 0 through 99 and has a default value of 55. If nn is set to zero, the effect is that of an infinite line count and page ejection does not occur. This option has no effect if the CC option is also specified.

Usage Notes

1. The file may contain carriage control characters and may have either fixed- or variable-length records, but no record may exceed 132 characters for a 1403 printer or 150 characters for a 3211 printer. There are two exceptions:
 - If the CC option is in effect, the record length can be one character longer (133 or 151) to allow for the carriage control character.
 - If the HEX option is in effect, a record of any length can be printed, up to the CMS file system maximum of 65,535 bytes.
2. If you want the first character of each line to be interpreted as a carriage control character, you must use the CC option. When you use the CC option for files that do not contain carriage control characters, the first character of each line is stripped off.

Files with a filetype of UPDLOG (produced by the UPDATE command) must be printed with the CC option.

3. One spool printer file is produced for each PRINT command, for example,

```
print mylib maclib (member get
```

prints the member GET from the file MYLIB MACLIB. If you want to print a number of files as a single file (so that you do not get output separator pages, for example), use the CP command SPOOL to spool your virtual printer with the CONT option.

Responses

None. The CMS Ready message indicates the command completed without error (that is, the file is written to the spooled printer). The file is now under the control of CP spooling functions. If a CP SPOOL command option such as HOLD or COPY is in effect, you may receive a message from CP.

Other Messages and Return Codes

```
DMSVRT002E FILE 'fn ft fm' NOT FOUND RC=28
DMSVRT003E INVALID OPTION 'option' RC=24
DMSVRT008E DEVICE 'cuu' {INVALID OR NONEXISTENT|UNSUPPORTED DEVICE TYPE}
RC=36
DMSVRT013E MEMBER 'name' NOT FOUND IN LIBRARY RC=32
DMSVRT029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD
RC=24
DMSVRT033E FILE 'fn ft fm' IS NOT A LIBRARY RC=32
DMSVRT039E NO ENTRIES IN LIBRARY 'fn ft fm' RC=32
DMSVRT044E RECORD LENGTH EXCEEDS ALLOWABLE MAXIMUM RC=32
```

PRINT

DMSVRT048E INVALID MODE 'mode' RC=24
DMSVRT054E INCOMPLETE FILEID SPECIFIED RC=24
DMSVRT062E INVALID * IN FILEID RC=20
DMSVRT070E INVALID PARAMETER 'parameter' RC=24
DMSVRT104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSVRT123S ERROR PRINTING FILE 'fn ft fm' RC= 100

| PSERV

| Use the PSERV command in CMS/DOS to copy, display, print, or punch a procedure from the DOS/VS procedure library. The format of the PSERV command is:

```
|
|-----|
| PSERV  | procedure [ ft ] [ (options... [ ] ) ]
|         |         [ PROC ]
|         |         options:
|         |         [ DISK ] [ PRINT ]
|         |         [ PUNCH ] [ TERM ]
|-----|
```

| where:

| procedure specifies the name of the procedure in the DOS procedure library that you want to copy, print, punch, or display.

| ft specifies the filetype of the file to be created on your A-disk. ft defaults to PROC if a filetype is not specified; the filename is always the same as the procedure name.

| Options: You may enter as many options as you wish, depending on the functions you want to perform.

| DISK copies the procedure to a CMS file. If no options are specified, DISK is the default.

| PRINT spools a copy of the procedure to the virtual printer.

| PUNCH spool a copy of the procedure to the virtual punch.

| TERM displays the procedure on your terminal.

| Usage Notes

| 1. You cannot execute DOS/VS procedures in CMS/DOS. You can use the PSERV command to copy an existing DOS/VS procedure onto a CMS disk, use the CMS Editor to change or add DOS/VS job control statements to it, and then spool it to the reader of a DOS/VS virtual machine for execution.

| 2. The PSERV command ignores current assignments of logical units, and directs output according to the option list.

| Responses

| When you issue the TERM option, the procedure is displayed at your terminal.

PSERV

| Error Messages and Return Codes

| DMSPRV003E INVALID OPTION 'option' RC=24
| DMSPRV004E PROCEDURE 'procedure' NOT FOUND RC=28
| DMSPRV006E NO READ/WRITE 'A' DISK ACCESSED RC=36
| DMSPRV037E DISK 'A' IS READ/ONLY RC=36
| DMSPRV070E INVALID PARAMETER 'parameter' RC=24
| DMSPRV097E NO 'SYSRES' VOLUME ACTIVE RC=36
| DMSPRV098E NO PROCEDURE NAME SPECIFIED RC=24
| DMSPRV099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSPRV105S ERROR 'nn' WRITING FILE 'fn ft fm' TO DISK RC=100
| DMSPRV113S DISK (cuu) NOT ATTACHED RC=100
| DMSPRV411S INPUT ERROR CODE 'nn' ON 'SYSRES' RC=100

PUNCH

Column	Number of Characters	Contents	Meaning
1	1	:	Identifies card as a control card.
2-5	4	READ	Identifies card as a READ control card.
6-7	2	blank	
8-15	8	fname	Filename of the file punched.
16	1	blank	
17-24	8	ftype	Filetype of the file punched.
25	1	blank	
26-27	2	fmode	Filemode of the file punched.
28	1	blank	
29-34	6	volid	Label of the disk from which the file was read.
35	1	blank	
36-43	8	mm/dd/yy	The date that the file was last written.
44-45	2	blank	
46-50	5	hh:mm	The time of day that the file was written to disk.
51-80	30	blank	

Figure 16. Header Card Format

Usage Notes

1. You can punch fixed- or variable-length records with the PUNCH command, as long as no record exceeds 80 characters. Records with less than 80 characters are right-padded with blanks. Records longer than 80 characters are rejected.
2. If you punch a MACLIB or TXTLIB file specifying MEMBER *, a read control card is placed in front of each library member. If you punch a library without specifying the MEMBER option, only one read control card is placed at the front of the deck.
3. One spool punch file is produced for each PUNCH command, for example:

```
punch compute assemble (noh
```

punches the file COMPUTE ASSEMBLE, without inserting a header card. To transmit multiple CMS files as a single punch file, use the CP SPOOL command to spool the punch with the CONT option.

Responses

None. The CMS Ready message indicates if the command completed without error (the file was successfully spooled); the file is now under control

of CP spooling functions. You may receive a message from CP indicating that the file is being spooled to a particular user's virtual card reader.

Other Messages and Return Codes

DMSPUN002E FILE 'fn ft fm' NOT FOUND RC=28
DMSPUN003E INVALID OPTION 'option' RC=24
DMSPUN008E DEVICE 'cuu' {INVALID OR NONEXISTENT|UNSUPPORTED DEVICE TYPE}
RC=36
DMSPUN013E MEMBER 'name' NOT FOUND IN LIBRARY RC=32
DMSPUN033E FILE 'fn ft fm' IS NOT A LIBRARY RC=32
DMSPUN039E NO ENTRIES IN LIBRARY 'fn ft fm' RC=32
DMSPUN044E RECORD LENGTH EXCEEDS ALLOWABLE MAXIMUM RC=32
DMSPUN054E INCOMPLETE FILEID SPECIFIED RC=24
DMSPUN062E INVALID * IN FILEID RC=20
DMSPUN104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSPUN118S ERROR PUNCHING FILE 'fn ft fm' RC=100

QUERY

QUERY

Use the QUERY command to gather information about your CMS virtual machine. You can determine:

- The state of virtual machine characteristics that are controlled by the CMS SET command.
- File definitions (set with the FILEDEF and DLBL commands) that are in effect.
- The status of accessed disks.
- The status of CMS/DOS functions.

The format of the QUERY command is:

Query	{ BLIP RDYMSG LDRTBLS RELPAGE IMPCP IMPEX ABBREV REDTYPE PROTECT INPUT OUTPUT SYSNAMES SEARCH DISK { mode } * SYNONYM { SYSTEM } USER } ALL FILEDEF MACLIB TXTLIB LIBRARY <u>CMS/DOS Functions:</u> { DLBL DOS DOSLIB DOSPART OPTION UPSI }
-------	--

Operands for Functions that can be Controlled via the SET Command:

BLIP displays the BLIP character(s).

Response: BLIP = { xxxxxxxx }
 { OFF }

QUERY

where:

ON indicates that truncations are accepted for CMS commands.
OFF indicates that truncations are not accepted.

REDTYPE displays the status of the REDTYPE indicator.

Response: REDTYPE = { ON }
 { OFF }

where:

ON types CMS error messages in red, for certain terminals equipped with the appropriate terminal feature and a two-color ribbon. Supported terminals are described in the VM/370: Terminal User's Guide.

OFF does not type CMS error messages in red.

PROTECT displays the status of CMS nucleus protection.

Response: PROTECT = { ON }
 { OFF }

where:

ON means CMS nucleus protection is in effect.
OFF means CMS nucleus protection is not in effect.

INPUT displays the contents of any input translate table in effect.

Response: INPUT a1 xx1
 .
 .
 .
 .
 an xxn

If you do not have an input translate table in effect, the response is

NO USER DEFINED INPUT TRANSLATE TABLE IN USE

OUTPUT displays the contents of any output translate table in effect.

Response: OUTPUT xx1 a1
 .
 .
 .
 .
 xxn an

If you do not have an output translate table defined, the response is

NO USER DEFINED OUTPUT TRANSLATE TABLE IN USE

| SYSNAMES displays the names of the saved system currently being used by
| your virtual machine.

Response: SYSNAMES: CMSSEG CMSVSAM CMSAMS CMSDOS
 ENTRIES: entry... entry... entry... entry...

where:

SYSNAMES are the standard names associated with the
 discontinuous saved systems.
 ENTRIES are the names of the saved systems being used.

Operands for CMS Disk Status Functions:

SEARCH displays the search order of all disks currently accessed.

Response: label cuu mode { R/O } [-OS]
 { R/W } [-DOS]

where:

label is the label assigned to the disk when it was
 formatted; or, if it is an OS or DOS disk, the volume
 label.

cuu is the virtual device address.

mode is the filemode letter assigned to the disk when it was
 accessed.

{ R/O } indicates the read/write status.
 { R/W }

[OS] indicates an OS or DOS disk.
 [DOS]
 []

DISK mode displays the status of the single disk represented by 'mode'.

Response: mode (cuu): nnnn FILES, nnnnn REC IN USE, nnnnn LEFT
 (of nnnnn), nn% FULL (nnn CYL), type { R/O }
 { R/W }

If the disk is an OS or DOS disk, the response is:

mode(cuu): (nnn CYL), type, { R/O } - { OS }
 { R/W } { DOS }

where:

mode (cuu) are the access mode letter and virtual device
 address.

nnnn FILES is the number of CMS files on the disk.

nnnnn REC IN USE, nnnnn LEFT (of nnnnn)
 indicates the number of CMS 800-byte blocks in
 use.

nn% FULL (nnn CYL)
 indicates the percentage of total use and the
 number of cylinders.

QUERY

	}	R/O	indicates the read/write status.
		R/W	
		OS	
		DOS	

If the disk with the specified mode is not accessed, the response is

DISK 'mode' NOT ACCESSED

DISK * displays the status of all CMS disks.

Response: same as for QUERY DISK mode; one line is displayed for each accessed disk.

Other Functions:

SYNONYM SYSTEM

displays the CMS system synonyms in effect.

Response:

SYSTEM	SHORTEST
COMMAND	FORM
-----	-----
command	minimum truncation
.	.
:	:
.	.

If no system synonyms are in effect, the following message is displayed at the terminal:

NO SYSTEM SYNONYMS IN EFFECT

SYNONYM USER

displays user synonyms in effect.

Response:

SYSTEM	USER	SHORTEST
COMMAND	SYNONYM	FORM (IF ANY)
-----	-----	-----
command	synonym	minimum truncation
.	.	.
:	:	:
.	.	.

If no user synonyms are in effect, the following message is displayed at the terminal:

NO USER SYNONYMS IN EFFECT

SYNONYM ALL

displays all synonyms in effect.

Response: The response to the command QUERY SYNONYM SYSTEM is followed by the response to QUERY SYNONYM USER.

FILEDEF displays all file definitions in effect.

Response: ddname device [fn [ft]]

```

      :      :      :      :
      :      :      :      :
      :      :      :      :
  
```

If no file definitions are in effect, the following message is displayed at the terminal:

NO USER DEFINED FILEDEF'S IN EFFECT

MACLIB displays the names of all files, with a filetype of MACLIB, that are to be searched for macro definitions (that is, all MACLIBS specified on the last GLOBAL MACLIB command, if any).

Response: MACLIB = libname...

If no macro libraries are to be searched for macro definitions, the response is:

MACLIB = NONE

TXTLIB displays the names of all files, with a filetype of TXTLIB, that are to be searched for unresolved references (that is, all TXTLIBS specified on the last GLOBAL TXTLIB command, if any).

Response: TXTLIB = libname...

If no TXTLIBS are to be searched for unresolved references, the following message is displayed at the terminal:

TXTLIB = NONE

| LIBRARY displays the names of all library files with filetypes of
| MACLIB, TXTLIB, DOSLIB that are to be searched.

Response: MACLIB = { libname... }
 { NONE }

TXTLIB = { libname... }
 { NONE }

| DOSLIB = { libname... }
| { NONE }

| CMS/DOS Functions:

| DLBL displays all disk file definitions in effect.

Response: ddname DISK fn ft

```

      :      :      :      :
      :      :      :      :
      :      :      :      :
  
```

| If no DLBL definitions are in effect, the following message is
| displayed:

NO USER DEFINED DLBL'S IN EFFECT

QUERY

| DOS displays whether the CMS/DOS environment is active or not.
| Response: DOS = { ON }
| { OFF }

| DOSLIB displays the names of all files with a filetype of DOSLIB that
| are to be searched for executable phases (that is, all DOSLIBs
| specified on the last GLOBAL DOSLIB command, if any).
| Response: DOSLIB = { libname ... }
| { NONE }

| DOSPART displays the current setting of the virtual partition size.
| Response: { nnnnnK }
| { NONE }

| where:

| nnnnnK indicates the size of the virtual partition to be used
| at program execution time.

| NONE indicates that CMS determines the virtual partition
| size at program execution time.

| OPTION displays the compiler options that are currently in effect.
| Response: OPTION = options...

| UPSI displays the current setting of the UPSI byte. The eight
| individual bits are displayed as zeros or ones depending on
| whether the corresponding bit is on or off.
| Response: UPSI = nnnnnnnn

Usage Notes

1. You can specify only a QUERY command function at one time. If the implied CP function is in effect and you enter an invalid QUERY command operand, you may receive the message DMKCQG045E.
2. The DOSPART, OPTION, and UPSI operands are valid only if the CMS/DOS environment is active.

Error Messages and Return Codes

DMSQRY005E NO 'option' SPECIFIED RC=24
DMSQRY014E INVALID FUNCTION 'function' RC=24
DMSQRY026E INVALID PARAMETER 'parameter' FOR 'function' FUNCTION RC=24
DMSQRY047E NO FUNCTION SPECIFIED RC=24
DMSQRY070E INVALID PARAMETER 'parameter' RC=24
| DMSQRY099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40

READCARD

Use the READCARD command to read data records from your virtual card reader and to create CMS disk files containing the data records. The format of the READCARD command is:

```

READcard | ( fn ft [ fm ] )
          | ( * [ * ] [ fm ] )
          | ( [ A ] [ A ] )
  
```

where:

- fn is the filename you want to assign to the file being read.
- ft is the filetype you want to assign to the file being read.
- * [*] indicates that file identifiers are to be assigned according to READ control cards in the input deck.
- fm is the filemode of the disk onto which the file is to be read. If this field is omitted or specified as an asterisk (*), the A-disk is assumed. Whenever a mode number is specified on the command line, it is used. Otherwise, the mode number on the READ control card is used to create the disk file.

Usage Notes

1. Data records read by the READCARD command must be fixed-length, and may be a minimum of 80 and a maximum of 151 characters long.
2. CMS disk file identifiers are assigned according to READ control cards in the input deck (the PUNCH command header card is a valid READ control card). When you enter the command

```
readcard *
```

CMS reads the first spool reader file in the queue and if there are READ control cards in the input stream, it names the files as indicated on the control cards.

If the first card in the deck is not a READ control card, CMS writes a file named READCARD CMSUT1 A1 to contain the data, until a READ control card is encountered or until the end-of-file is reached.

3. If you specify a filename and filetype on the READCARD command, for example,

```
readcard junk file
```

CMS does not check the input stream for READ control cards, but reads the entire spool file onto disk and assigns it the specified filename and filetype.

If there were any READ control cards in the deck, they are not removed; you must delete them using the CMS Editor if you do not

READCARD

want them in your file. If the file is too large, you can either increase the size of your virtual storage (using the CP DEFINE command), or use the COPYFILE command to copy all records except the READ control cards (using the FROM and FOR options).

4. To read file onto a disk other than your A-disk, you can specify the filemode letter when you enter the filename and filetype, for example:

```
readcard junk file c
```

Or, if you want READ control card to determine the filenames and filetypes, you can enter

```
readcard * * c
```

5. When you read a file that has the same filename and filetype of an existing file on the same disk, the old file is replaced.
6. If you are preparing real or virtual card decks to send to your own or another user's virtual card reader, you may insert READ control cards to designate filenames and filetypes, and optionally filemode numbers, to be assigned to the disk file(s).

A READ control card must begin in column 1 and has the format:

```
:READ filename filetype filemode
```

Each field must be separated by at least one blank; the second character of the filemode field, if specified, must be a valid filemode number (0 through 5). The filemode letter is ignored when this file is read, since the mode letter is determined by specifications on the READCARD command line.

7. To send a real card deck to your own or another user's virtual card reader, you must punch a CP ID card in the front of the deck. The ID card has the keyword ID or USERID in column 1, followed by the userid you want to receive the file, and optionally spool file class and name designations, for example:

```
ID CONCARNE CLASS A NAME CHILI PEPPER
```

Each field must be separated from the others by at least one blank.

Responses

When the command READCARD * is issued, control cards encountered in the input card stream are displayed at the terminal (see message DMSRDC702I), to indicate the names assigned to each file.

DMSRDC701I NULL FILE

The spooled card reader contains no records after the control card.

DMSRDC702I :READ filename filetype fn (other information)

A READ control card has been processed; the designated file is being written on disk.

DMSRDC702I READ CONTROL CARD IS MISSING. FOLLOWING ASSUMED:
DMSRDC702I :READ READCARD CMSUT1 A1

The first card in the deck is not a READ control card. Therefore,
the file READCARD CMSUT1 A1 is created.

DMSRDC738I RECORD LENGTH IS 'nnn' BYTES

The records being read are not 80 bytes long; this message gives
the length.

Other Messages and Return Codes

DMSRDC008E DEVICE 'cuu' {INVALID OR NONEXISTENT|UNSUPPORTED DEVICE TYPE}
RC=36
DMSRDC042E NO FILEID SPECIFIED RC=24
DMSRDC054E INCOMPLETE FILEID SPECIFIED RC=24
DMSRDC062E INVALID * IN FILEID RC=20
DMSRDC105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSRDC124S ERROR READING CARD FILE RC=100
DMSRDC205W READER EMPTY OR NOT READY RC=8

RELEASE

RELEASE

Use the RELEASE command to free an accessed disk and make the files on it unavailable. The format of the RELEASE command is:

```
RELEASE | { cuu } [ (DET[ ) ] ]  
        | { mode } ^
```

where:

cuu is the virtual device address of the disk that is to be released.

Valid addresses are 001 through 5FF for a virtual machine in basic control mode and 001 through FFF for a virtual machine in extended control mode.

mode is the mode letter at which the disk is currently accessed.

Option:

DET specifies that the disk is to be detached from your virtual machine configuration, CMS calls the CP command DETACH.

Usage Notes

1. If a disk is accessed at more than one mode letter, the RELEASE cuu command releases all modes. If you access a disk specifying the mode letter of an active disk, the first disk is released.
2. You cannot release the system disk (S-disk).
3. When a disk is released, the user file directory is freed from storage and that storage becomes available for other CMS commands and programs. When you release a read/write CMS disk, either with the RELEASE command or implicitly with the FORMAT command, the user file directory is sorted and rewritten on disk; user(s) who may subsequently access the same disk may have a resultant favorable decrease in file search time.
4. When a disk is released, any read-only extensions it may have are not released. The extensions may be referred to by their own mode letters. If a disk is then accessed with the same mode as the original parent disk, the original read-only extensions remain extensions to the new disk at that mode.
5. In CMS/DOS, when you release a disk, any system or programmer logical unit assignments made for the disk are unassigned.

Responses

DASD cuu DETACHED

This is a CP message that is issued when you use the DET option. It indicates that the disk has been detached.

Error Messages and Return Codes

DMSARE017E INVALID DEVICE ADDRESS 'cuu' RC=24
DMSARE028E NO DEVICE SPECIFIED RC=24
DMSARE048E INVALID MODE 'mode' RC=24
DMSARE069E DISK {'mode'|'cuu'} NOT ACCESSED RC=36
DMSARE070E INVALID PARAMETER 'parameter' RC=24

RENAME

RENAME

Use the RENAME command to change the fileid of one or more CMS files on a read/write CMS disk. The format of the RENAME command is:

Rename	fileid1 fileid2 [(options...[])]
	<u>options:</u>
	[TYPE] [UPDIRT]
	[NOTYPE] [NOUPDIRT]

where:

fileid1 is the file identifier of the original file whose name is to be changed. All components of the fileid (filename, filetype, and filemode) must be coded, with either a name or an asterisk. If an asterisk is coded in any field, any file that satisfies the other qualifications is renamed.

fileid2 is the new file identifier of the file. All components of the file (filename, filetype, and filemode) must be coded, with either a name or an equal sign; if an equal sign (=) is coded, the corresponding file identifier is unchanged. The output filemode can also be specified as an asterisk (*), indicating that the filemode is not changed.

Options:

TYPE displays, at the terminal, the new identifiers of all the files that are renamed. The file identifiers are displayed only when an * is specified for one or more of the file identifiers (fn, ft or fm) in fileid1.

NOTYPE suppresses displaying, at the terminal, of the new file identifiers of all files renamed.

UPDIRT updates the master file directory upon completion of this command.

NOUPDIRT suppresses the updating of the master file directory upon completion of this command. (See Usage Note 3.)

Usage Notes

1. When you code an asterisk in any portion of the input fileid, any or all of the files that satisfy the other qualifiers may be renamed, depending on how you specify the output fileid. For example,

```
rename * assemble a test file a
```

results in the first ASSEMBLE file found on the A-disk being renamed to TEST FILE. If more than one ASSEMBLE file exists, error messages are issued to indicate that they cannot be renamed.

If you code an equal sign in an output fileid in a position corresponding to an asterisk in an input fileid, all files that satisfy the condition are renamed. For example,

```
rename * assemble a = oldasm =
```

renames all files with a filetype of ASSEMBLE to files with a filetype of OLDASM. Current filenames are retained.

2. You cannot use the RENAME command to move a file from one disk to another. You must use the COPYFILE command if you want to change filemode letters.

You can use the RENAME command to modify filemode numbers, for example,

```
rename * module a1 = = a2
```

changes the filemode number on all MODULE files that have a mode number of 1 to a mode number of 2.

3. Normally, the master file directory for a CMS disk is updated whenever you issue a command that affects files on the disk. When you use the NOUPDIRT option of the RENAME command, the master file directory is not updated until you issue a command that writes, updates, or deletes any file on the disk, or until you explicitly release the disk (with the RELEASE command).

Responses

```
newfn newft newfm
```

The new filename, filetype, and filemode of each file altered is displayed when the TYPE option is specified and an asterisk was specified for at least one of the file identifiers (fn, ft or fm) of the input fileid.

Error Messages and Return Codes

```
DMSRNM002E FILE 'fn ft fm' NOT FOUND RC=28
DMSRNM003E INVALID OPTION 'option' RC=24
DMSRNM019E IDENTICAL FILEIDS RC=24
DMSRNM024E FILE 'fn ft fm' ALREADY EXISTS RC=28
DMSRNM030E FILE 'fn ft fm' ALREADY ACTIVE RC=28
DMSRNM037E DISK 'mode(cuu)' IS READ/ONLY RC=36
DMSRNM051E INVALID MODE CHANGE RC=24
DMSRNM054E INCOMPLETE FILEID SPECIFIED RC=24
DMSRNM062E INVALID * IN OUTPUT FILEID RC=20
```

Note: You can invoke the RENAME command from the terminal, from an EXEC file, or as a function from a program. If RENAME is invoked as a function or from an EXEC file that has the &CONTROL NOMSG option in effect, the message DMSRNM002E FILE fn ft fm NOT FOUND is not issued.

RSERV

| RSERV

| Use the RSERV command in CMS/DOS to copy, display, print, or punch a
| DOS/VS relocatable module from a private or system library. The format
| of the RSERV command is:

```
|-----|
| RSERV | modname [ ft ] [ (options...[]) ]
|       |          |TEXT|
|       |          |-----|
|                   options:
|                   [DISK] [PRINT]
|                   [PUNCH [TERM]
```

| where:

| modname specifies the name of the module on the DOS/VS private or
| system relocatable library.

| ft specifies the filetype of the file to be created on your
| A-disk. ft defaults to TEXT if a filetype is not specified.
| The filename is always the same as the module name.

| Options: You may specify as many options as you wish on the RSERV
| command, depending on which functions you want to perform.

| DISK copies the relocatable module onto your A-disk. If no other
| options are specified, DISK is the default.

| PUNCH punches the relocatable module on the virtual punch.

| PRINT prints the relocatable module on the virtual printer.

| TERM displays the relocatable module at your terminal.

| Usage Notes

| 1. If you want to copy modules from a private relocatable library, you
| must issue an ASSGN command for the logical unit SYSRLB and
| identify the library on a DLBL command line using the ddname
| IJSYSRL.

| To copy modules from the system relocatable library, you must have
| entered the CMS/DOS environment specifying a mode letter on the SET
| DOS ON command line.

| 2. The RSERV command ignores the assignment of logical units, and
| directs output to the devices specified on the option list.

| Responses

| If you use the TERM option, the relocatable module is displayed at the
| terminal.

| Messages and Return Codes

```
| DMSRRV003E INVALID OPTION 'option' RC=24
| DMSRRV004E MODULE 'module' NOT FOUND RC=28
| DMSRRV006E NO READ/WRITE 'A' DISK ACCESSED RC=36
| DMSRRV070E INVALID PARAMETER 'parameter' RC=24
| DMSRRV097E NO 'SYSRES' VOLUME ACTIVE RC=36
| DMSRRV098E NO MODULE NAME SPECIFIED RC=24
| DMSRRV099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSRRV105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
| DMSRRV113S DISK (cuu) NOT ATTACHED RC=100
| DMSRRV411S INPUT ERROR CODE 'nn' ON '{SYSRES|SYSRLB}' RC=100
```

RUN

RUN

Use the RUN EXEC procedure to initiate a series of functions on a file. The RUN command can compile, load, and start execution of the specified file, depending upon the filetype. The format of the RUN command is:

```
| | RUN | fn [ft [fm]] [(args...)] |
```

where:

fn is the filename of the file to be manipulated.

ft is the filetype of the file to be manipulated. If filetype is not specified, a search is made for a file with the specified filename and the filetype of EXEC, MODULE, or TEXT (the search is performed in that order). If the filetype of an input file for a language processor is specified, the language processor is invoked to compile the source statements and produce a TEXT file. Then, LOAD and START are called to initiate program execution. The valid filetypes and resulting action for this command are:

<u>Filetype</u>	<u>Action</u>
EXEC	The EXEC processor is called to process the file.
MODULE	The LOADMOD command is issued to load the program into storage and the START command begins execution of the program at the entry point equal to fn.
TEXT	The LOAD command brings the file into storage in an executable format and the START command executes the program beginning at the entry point named by fn.
FORTRAN	The FORTRAN processor module that is called is FORTRAN, FORTGI, GOFORT, TESTFORT, or FORTHX, whichever is found first.
FREEFORT	The GOFORT module is called to process the file.
COBOL	The COBOL processor module that is called is COBOL or TESTCOB, whichever is found first.
PLI PLIOPT	The PLIOPT processor module is called to process the file.

fm is the filemode of the file to be manipulated. If this field is specified, a filetype must be specified. If fm is not specified, the default search order is used to search your disks for the file.

args are arguments you want to pass to your program. You can specify up to 13 arguments in the RUN command, provided they fit on a single input line. Each argument is left-justified, and any argument more than 8 characters long is truncated on the right.

Usage Notes

1. The RUN command is an EXEC procedure; if you want to execute it from within an EXEC, you must use the EXEC command.
2. If you are executing an EXEC file, the arguments you enter on the RUN command line are assigned to the variable symbols &1, &2, and so on.

If you are executing a TEXT or MODULE file, or compiling and executing a program, the arguments are placed in a parameter list and passed to your program when it executes. The arguments are placed in a series of doublewords in storage, terminated by X'FF'. If you enter

```
run myprog (charlie dog
```

the arguments CHARLIE and DOG are placed in a parameter list, and the address of the list is in Register 1 when your program receives control.

Note: You cannot use the argument list to override default options for the compilers or for the LOAD or START commands.

3. The RUN command is not designed for use with CMS/DOS.

Responses

Any responses are from the programs or procedures that executed within the RUN EXEC.

Error Messages and Return Codes

```
DMSRUN001E NO FILENAME SPECIFIED RC=24
| DMSRUN002E FILE['fn [ft [fm]]'] NOT FOUND RC=28
DMSRUN048E INVALID MODE 'fm' RC=24
DMSRUN070E INVALID PARAMETER 'parameter' RC=24
| DMSRUN999E NO [ft] PROCESSOR FOUND RC=28
```

SET

SET

Use the SET command to establish, turn off, or reset a particular function in your CMS virtual machine. Only one function may be specified per SET command. The format of the SET command is:

SET	function									
	<table border="0"> <tr> <td><u>functions:</u></td> <td>[BLIP string[(count)]]</td> <td>[RDYMSG LMSG]</td> </tr> <tr> <td></td> <td>[BLIP ON</td> <td>[RDYMSG SMSG]</td> </tr> <tr> <td></td> <td>[BLIP OFF</td> <td>]</td> </tr> </table>	<u>functions:</u>	[BLIP string[(count)]]	[RDYMSG LMSG]		[BLIP ON	[RDYMSG SMSG]		[BLIP OFF]
<u>functions:</u>	[BLIP string[(count)]]	[RDYMSG LMSG]								
	[BLIP ON	[RDYMSG SMSG]								
	[BLIP OFF]								
	<table border="0"> <tr> <td>[LDRTBLS nn]</td> <td>[RELPAGE ON]</td> <td>[INPUT [a xx]]</td> </tr> <tr> <td></td> <td>[RELPAGE OFF]</td> <td>[xx yy]]</td> </tr> <tr> <td></td> <td></td> <td>[OUTPUT [xx a]]</td> </tr> </table>	[LDRTBLS nn]	[RELPAGE ON]	[INPUT [a xx]]		[RELPAGE OFF]	[xx yy]]			[OUTPUT [xx a]]
[LDRTBLS nn]	[RELPAGE ON]	[INPUT [a xx]]								
	[RELPAGE OFF]	[xx yy]]								
		[OUTPUT [xx a]]								
	<table border="0"> <tr> <td>[ABBREV ON]</td> <td>[REDTYPE ON]</td> <td>[IMPEX ON]</td> </tr> <tr> <td>[ABBREV OFF]</td> <td>[REDTYPE OFF]</td> <td>[IMPEX OFF]</td> </tr> </table>	[ABBREV ON]	[REDTYPE ON]	[IMPEX ON]	[ABBREV OFF]	[REDTYPE OFF]	[IMPEX OFF]			
[ABBREV ON]	[REDTYPE ON]	[IMPEX ON]								
[ABBREV OFF]	[REDTYPE OFF]	[IMPEX OFF]								
	<table border="0"> <tr> <td>[IMPCP ON]</td> <td>[PROTECT ON]</td> <td>[AUTOREAD ON]</td> </tr> <tr> <td>[IMPCP OFF]</td> <td>[PROTECT OFF]</td> <td>[AUTOREAD OFF]</td> </tr> </table>	[IMPCP ON]	[PROTECT ON]	[AUTOREAD ON]	[IMPCP OFF]	[PROTECT OFF]	[AUTOREAD OFF]			
[IMPCP ON]	[PROTECT ON]	[AUTOREAD ON]								
[IMPCP OFF]	[PROTECT OFF]	[AUTOREAD OFF]								
	<table border="0"> <tr> <td>[SYSNAME {CMSDOS CMSVSAM CMSAMS CMSSEG} entryname]</td> <td>[NONSHARE {CMSDOS CMSVSAM CMSAMS CMSSEG}]</td> </tr> </table>	[SYSNAME {CMSDOS CMSVSAM CMSAMS CMSSEG} entryname]	[NONSHARE {CMSDOS CMSVSAM CMSAMS CMSSEG}]							
[SYSNAME {CMSDOS CMSVSAM CMSAMS CMSSEG} entryname]	[NONSHARE {CMSDOS CMSVSAM CMSAMS CMSSEG}]									
	<p><u>CMS/DOS functions:</u></p> <table border="0"> <tr> <td>[DOS ON [mode [(VSAM[])]]]</td> <td>[UPSI nnnnnnnn]</td> <td>[DOSPART nnnnnK]</td> </tr> <tr> <td>[DOS OFF]</td> <td>[UPSI OFF]</td> <td>[DOSPART OFF]</td> </tr> </table>	[DOS ON [mode [(VSAM[])]]]	[UPSI nnnnnnnn]	[DOSPART nnnnnK]	[DOS OFF]	[UPSI OFF]	[DOSPART OFF]			
[DOS ON [mode [(VSAM[])]]]	[UPSI nnnnnnnn]	[DOSPART nnnnnK]								
[DOS OFF]	[UPSI OFF]	[DOSPART OFF]								

where:

Functions:

BLIP string[(count)]

defines the characters which are displayed at the terminal to indicate every two seconds of virtual interval timer time. This time is made up of virtual CPU time plus, if the REALTIMER option on, self-imposed wait time.

You can define up to 8 characters as a blip string; if you want trailing blanks, you must specify count. ON and OFF must not be used as BLIP characters.

BLIP ON

sets the BLIP character string to its default, which is a string of nonprintable characters. ON is the default for typewriter devices. The default BLIP character provides no visual or audio-visual signal on a 3767 terminal. You must define a BLIP character for a 3767 if you want the BLIP function.

BLIP OFF

turns off BLIP. OFF is the default for graphics devices.

<u>RDYMSG LMSG</u>	indicates that the standard CMS Ready message, including current and elapsed time, is used. The format of the standard Ready message is: R; T=s.mm/s.mm hh:mm:ss where the virtual CPU time, real CPU time, and clock time are listed.
RDYMSG SMSG	indicates that a shortened form of the CMS Ready message (R;) which does not include the time, is used.
LDRTBLS nn	defines the number (nn) of pages of storage to be used for loader tables. By default, a virtual machine having up to 384K of addressable real storage has two pages of loader tables; a larger virtual machine has three pages. Each loader table page has a capacity of 204 external names. During LOAD and INCLUDE command processing, each unique external name encountered in a TEXT deck is entered in the loader table. The LOAD command clears the table before reading TEXT files; INCLUDE does not. This number can be changed with the SET LDRTBLS nn command provided that: (1) nn is a decimal number less than 128, (2) the virtual machine has enough storage available to allow nn pages to be used for loader tables, and (3) the system has not started using storage located below the LDRTBLS. If these three conditions are met, nn pages are set aside for loader tables. If you plan to change the number of pages allocated for loader tables, you should do so as soon after IPL as possible.
<u>RELPAGE ON</u>	releases page frames of storage and sets them to binary zeros after the following commands complete execution: ASSEMBLE, COPYFILE, COMPARE, EDIT, MACLIB, SORT, TXTLIB, UPDATE, and the program product language processors supported by VM/370. These processors are listed in the <u>VM/370: Introduction</u> .
RELPAGE OFF	does not release pages of storage after the commands listed in the RELPAGE ON description complete execution. Use the SET RELPAGE OFF function when debugging or analyzing a problem so that the storage used is not released and can be examined.
INPUT a xx	translates the specified character 'a' to the specified hexadecimal code xx for characters entered from the terminal.
INPUT xx yy	allows you to reset the hexadecimal code xx to the specified hexadecimal code yy in your translate table. <u>Note:</u> If you issue SET INPUT and SET OUTPUT commands for the same characters, issue the SET OUTPUT command first.
INPUT	returns all characters to their default translation.
OUTPUT xx a	translates the specified hexadecimal representation xx to the specified character 'a' for all xx characters displayed at the terminal. (X'00' is not translated.)
OUTPUT	returns all characters to their default translation.

SET

| Note: Output translation does not occur for SCRIPT files
| when the SCRIPT command output is directed to the
| terminal, nor when you use the CMS Editor on a display
| terminal in display mode.

ABBREV ON accepts system and user abbreviations for system commands. The SYNONYM command makes the system and user abbreviations available.

ABBREV OFF accepts only the full system command name or the full user synonym (if one is available) for system commands.

For a discussion of the relationship of the SET ABBREV and SYNONYM commands, refer to the SYNONYM command description.

RETYPE ON types CMS error messages in red for certain terminals equipped with the appropriate terminal feature and a two-color ribbon. Supported terminals are described in the VM/370: Terminal User's Guide.

RETYPE OFF suppresses red typing of error messages.

IMPEX ON treats EXEC files as commands; an EXEC file is invoked when the filename of the EXEC file is entered.

IMPEX OFF does not consider EXEC files as commands. You must issue the EXEC command to execute an EXEC file.

IMPCP ON passes command names that CMS does not recognize to CP; that is, unknown commands are considered to be CP commands.

IMPCP OFF generates an error message at the terminal if a command is not recognized by CMS.

PROTECT ON protects the CMS nucleus against writing in its storage area.

PROTECT OFF does not protect the storage area containing the CMS nucleus.

AUTOREAD ON specifies that a console read is to be issued immediately after command execution. ON is the default for non-display, non-buffered terminals.

AUTOREAD OFF specifies that you do not want a console read to be issued until you press the Enter key or its equivalent. OFF is the default for display terminals because the display terminal does not lock, even when there is no READ active for it.

Note: If you disconnect from one type of terminal and reconnect on another type, the AUTOREAD status remains unchanged.

| SYSNAME { CMSDOS
| { CMSVSAM } entryname
| { CMSAMS
| { CMSSEG

allows you to replace a saved system name entry in the SYSNAMES table with the name of an alternative, or backup system. A separate SET SYSNAME command must be issued for each name entry to be changed. CMSDOS, CMSVSAM, CMSAMS, and CMSSEG are the default names

| assigned to the systems when the CMS system is
| generated.

| NONSHARE { CMSDOS
| { CMSVSAM
| { CMSAMS
| { CMSSEG }

| specifies that you want your own nonshared copy of a
| normally shared named system.

| CMS/DOS Functions:

| The following functions describe the SET operands that apply to the
| CMS/DOS environment.

| DOS ON places your CMS virtual machine in the CMS/DOS
| environment. The logical unit SYSLOG is assigned to your
| terminal.

| mode specifies the mode letter at which the DOS/VS system
| residence is accessed; the logical assignment of SYSRES
| is made for the indicated mode letter.

| VSAM specifies that you are going to use the AMSERV command
| or you are going to execute programs to access VSAM data
| sets.

| DOS OFF returns your virtual machine to the normal CMS
| environment. All previously assigned system and
| programmer logical units are unassigned.

| UPSI nnnnnnn sets the UPSI (User Program Switch Indicator) byte to
| the specified bit string of 0's and 1's. If you enter
| fewer than 8 digits, the UPSI byte is filled in from the
| left and zero-padded to the right.

| UPSI OFF resets the UPSI byte to binary zeros.

| DOSPART nnnnnK specifies the size of the virtual partition you want to
| a program to execute in. The value, nnnnnK, may not
| exceed the amount of user free storage available in your
| virtual machine. You should use this function only when
| you can control the performance of a particular program
| by reducing the amount of available virtual storage.

| Note: In rare circumstances, it may happen that when a
| program is executed, the amount of storage available is
| less than the current DOSPART. Then, only the amount of
| storage available is obtained; no message is issued.

| DOSPART OFF specifies that you no longer want to control your
| virtual machine partition size. When the DOSPART
| setting is OFF, CMS computes the partition size whenever
| a program is executed.

Responses

None. To determine or verify the setting of a function, use the QUERY
command.

SET

Messages and Return Codes

```
| DMSLIO002I FILE 'fn' TXTLIB NOT FOUND RC=0
| DMSSET014E INVALID FUNCTION 'function' RC=24
| DMSSET026E INVALID PARAMETER 'parameter' FOR 'function' FUNCTION RC=24
| DMSSET031E LOADER TABLES CANNOT BE MODIFIED RC=40
| DMSSET047E NO FUNCTION SPECIFIED RC=24
| DMSSET048E INVALID MODE 'mode' RC=24
| DMSSET050E PARAMETER MISSING AFTER (NONSHARE|SYSNAME|label) RC=24
| DMSSET061E NO TRANSLATION CHARACTER SPECIFIED RC=24
| DMSSET070E INVALID PARAMETER 'parameter' RC=24
| DMSSET098W CMS OS SIMULATION NOT AVAILABLE RC=4
| DMSSET099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSSET100W SYSTEM NAME 'name' NOT AVAILABLE RC=4
| DMSSET142S SAVED SYSTEM NAME 'name' INVALID RC=24
| DMSSET333E nnnnnK PARTITION TOO LARGE FOR THIS VIRTUAL MACHINE RC=24
| DMSSET400S SYSTEM 'sysname' DOES NOT EXIST RC=44
| DMSSET401S V.M. SIZE (size) CANNOT EXCEED 'DMSDOS' START ADDRESS
| (address) RC=104
| DMSSET410S CONTROL PROGRAM ERROR INDICATION 'retcode' RC=nnn
| where nnn is the actual error code from CP
```

SORT

Use the SORT command to read fixed-length records from a CMS input file, arrange them in ascending EBCDIC order according to specified sort fields, and create a new file containing the sorted records. The format of the SORT command is:

```
SORT | fileid1 fileid2
```

where:

fileid1 is the file identifier (filename, filetype, filemode) of the file containing the records to be sorted.

fileid2 is the file identifier (filename, filetype, filemode) of the new output file to contain the sorted records.

Usage Notes

1. The input and output files must not have the same file identifiers, since SORT cannot write the sorted output back into the space occupied by the input file. If a file with the same name as the output file already exists, the old file is erased.

Entering Sort Control Fields: After the SORT command is entered, CMS responds with the following message on the terminal:

```
DMSRT604R ENTER SORT FIELDS:
```

You should respond by entering one or more pairs of numbers of the form "xx yy" separated by one or more blanks. Each xx is the starting character position of a sort field within each input record and yy is the ending character position. The leftmost pair of numbers denotes the major sort field. The number of sort fields is limited to the number of fields you can enter on one line. The records can be sorted on up to a total of 253 positions.

Virtual Storage Requirements for Sorting: The sorting operation takes place with two passes of the input file. The first pass creates an ordered pointer table in virtual storage. The second pass uses the pointer table to read the input file in a random manner and write the output file. Therefore, the size of storage and the size and number of sort fields are the limiting factors in determining the number of records that can be sorted at any one time. An estimate of the maximum number of records that can be sorted is:

$$NR = \frac{VMSIZE - 132K}{14 + NC}$$

where: NR is the estimated maximum number of input records; NC is the total number of characters in the defined sort fields; VMSIZE is the storage size of the virtual machine; and 132K is the size of the resident CMS nucleus. For example, enter the command and respond to the prompting message:

SORT

sort name address a1 sortedna address b1

DMSRT604R ENTER SORT FIELDS:

1 10 25 28

The records in the NAME ADDRESS file are sorted on positions 1-10 and 25-28. The sorted output is written into the newly created file SORTEDNA ADDRESS. If you have a 320K virtual machine, you can sort a maximum of 6875 records.

$$\text{NR} = \frac{\text{VMSIZE}-132\text{K}}{14 + \text{NC}} = \frac{320\text{K}-132\text{K}}{14 + 14} = \frac{188\text{K}}{28} = \frac{192,512}{28} = 6875$$

Responses

DMSRT604R ENTER SORT FIELDS:

You are requested to enter SORT control fields. You should enter them in the form described in "Entering Sort Control Fields."

Other Messages and Return Codes

DMSRT002E FILE 'fn ft fm' NOT FOUND RC=28
DMSRT009E COLUMN 'col' EXCEEDS RECORD LENGTH RC=24
DMSRT019E IDENTICAL FILEIDS RC=24
DMSRT034E FILE 'fn ft fm' IS NOT FIXED LENGTH RC=32
DMSRT037E DISK 'mode' IS READ/ONLY RC=36
DMSRT053E INVALID SORT FIELD PAIR DEFINED RC=24
DMSRT054E INCOMPLETE FILEID SPECIFIED RC=24
DMSRT062E INVALID * IN FILEID RC=20
DMSRT063E NO LIST ENTERED RC=40
DMSRT070E INVALID PARAMETER 'parameter' RC=24
DMSRT104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSRT105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSRT212E MAXIMUM NUMBER OF RECORDS EXCEEDED RC=40

| **SSERV**

| Use the SSERV command in CMS/DOS to copy, display, print, or punch a
| book from a DOS/VS source statement library. The format of the SSERV
| command is:

```

|-----|
| SSERV | sublib bookname [ ft ] [ (options... [ ] ) ]
|       |                [ COPY ]
|       |                options:
|       |                [ DISK ] [ PRINT ]
|       |                [ PUNCH ] [ TERM ]
|-----|

```

| where:

| sublib specifies the source statement sublibrary in which the book is
| cataloged.

| bookname specifies the name of the book in the DOS private or system
| source statement sublibrary.

| ft specifies the filetype of the file to be created on your
| A-disk. ft defaults to COPY if a filetype is not specified.
| The filename is always the same as the bookname.

| Options: You may enter as many options as you wish, depending on the
| functions you want to perform.

| DISK copies the book to a CMS file.

| PUNCH punches the book on the virtual punch.

| PRINT spools a copy of the book to your virtual printer.

| TERM displays the book on your terminal.

| Usage Notes

- | 1. If you want to copy books from private libraries, you must issue an
| ASSGN command for the logical unit SYSSLB and identify the library
| on a DLBL command line using a ddname of IJSYSSL.
- | If you want to copy books from the system library, you must have
| entered the CMS/DOS environment specifying the mode letter of the
| system residence volume.
- | 2. You should not use the SSERV command to copy books from E
| sublibraries, since they are in "edited" (that is, compressed)
| form. Use the ESERV command to copy and de-edit macros from an E
| sublibrary.

| Responses

| When you use the TERM option, the specified book is displayed at the
| terminal.

SSERV

| Messages and Return Codes

| DMSSRV003E INVALID OPTION 'option' RC=24
| DMSSRV004E BOOK 'subl.book' NOT FOUND RC=28
| DMSSRV006E NO READ/WRITE 'A' DISK ACCESSED RC=36
| DMSSRV070E INVALID PARAMETER 'parameter' RC=24
| DMSSRV097E NO 'SYSRES' VOLUME ACTIVE RC=36
| DMSSRV098E NO BOOK NAME SPECIFIED RC=24
| DMSSRV099E CMS/DOS ENVIRONMENT NOT ACTIVE RC=40
| DMSSRV105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
| DMSSRV113S DISK (cuu) NOT ATTACHED RC=100
| DMSSRV411S INPUT ERROR CODE 'nn' ON '{SYSRES|SYSSLB}' RC=100
| DMSSRV194S BOOK 'subl.book' CONTAINS BAD RECORDS RC=100

START

| Use the START command to begin execution of CMS, OS or DOS programs that
| were previously loaded or fetched. The format of the START command is:

```

START | [ entry [args...] ]
      | [ * ]

```

where:

entry passes control to the control section name or entry point name at execution time. The operand, entry, may be a filename only if the filename is identical to a control section name or an entry point name.

* passes control to the default entry point. See the discussion of the LOAD command for a discussion of the default entry point selection.

args... are arguments to be passed to the started program. If user arguments are specified, entry or * must be specified; otherwise, the first argument is taken as the entry point. Arguments are passed to the program via general register 1. The entry operand and any arguments become a string of doublewords, one argument per doubleword, and the address of the list is placed in general register 1.

Usage Notes:

1. Any undefined names or references specified in the files loaded into storage are defined as zero. Thus, if there is a call or branch to a subroutine from a main program, and if the subroutine has never been loaded, the call or branch transfers control to location zero of the virtual machine at execution time.
2. Do not use the START command for programs that are generated via the GENMOD command with the NOMAP option. The START command does not execute properly for such programs.

Responses

DMSLI0740I EXECUTION BEGINS...

is displayed when the designated entry point is validated.

| This message is suppressed if CMS/DOS is active and the COMP option
| is specified in the FETCH command.

Error Messages and Return Codes

DMSLI0021E ENTRY POINT 'name' NOT FOUND RC=40
DMSLI0055E NO ENTRY POINT DEFINED RC=40

| STATE/STATEW

| Use the STATE command to verify the existence of a CMS, OS, or DOS file
 | on any accessed disk; use the STATEW command to verify the existence of
 | a CMS, OS, or DOS file on any accessed read/write disk. The formats of
 | the STATE and STATEW commands are:

```
| { STATE } | fn ft [fm]
| { STATEW } | * * *
```

where:

fn is the filename of the file whose existence is to be verified. If fn is specified as *, the first file found satisfying the rest of the fileid is used.

ft is the filetype of the file whose existence is to be verified. If ft is specified as *, the first file found satisfying the rest of the fileid is used.

fm is the filemode of the file whose existence is to be verified. If fm is omitted, or specified as *, all your disks are searched.

Usage Notes:

1. If you issue the STATEW command specifying a file that exists on a read-only disk, you receive error message DMSST002E.
2. When you code an asterisk in the fn or ft fields, the search for the file is ended as soon as any file satisfies any of the other conditions. For example, the command

```
state * file
```

executes successfully if any file on any accessed disk (including the system disk) has a filetype of FILE.

3. To verify the existence of an OS or DOS file, when DOS is set OFF, you must issue the FILEDEF command to establish a CMS file identifier for the file. For example, to verify the existence of the OS file TEST.DATA on an OS C-disk you could enter

```
filedef check disk check list c dsn test data
state check file
```

where CHECK LIST is the default filename and filetype (FILE ddname) associated with the OS data set name.

4. To verify the existence of an OS or DOS file when the CMS/DOS environment is active, you must issue the DLBL command to establish a CMS file identifier for the file. For example, to verify the existence of the DOS file TEST.DATA on a DOS C-disk, you could enter

```
dlbl check c dsn test data
state file check
```

where FILE CHECK is the default CMS filename and filetype (FILE ddname) associated with the DOS file-id.

Responses

| The CMS Ready message indicates that the specified file exists.

DMSSTT227I PROCESSING VOLUME 'no' IN DATA SET 'data set name'

The specified data set has multiple volumes; the volume being processed is shown in the message. The STATE command treats end-of-volume as end-of-file and there is no end-of-volume switching.

DMSSTT228I USER LABELS BYPASSED ON DATA SET 'data set name'

The specified data set has disk user labels; these labels are skipped.

Error Messages and Return Codes

DMSSTT002E FILE 'fn ft fm' NOT FOUND RC=28
 DMSSTT048E INVALID MODE 'mode' RC=24
 DMSSTT054E INCOMPLETE FILEID SPECIFIED RC=24
 DMSSTT062E INVALID 'char' IN FILEID 'fn ft' RC=20
 DMSSTT069E DISK 'mode' NOT ACCESSED RC=36
 DMSSTT070E INVALID PARAMETER 'parameter' RC=24
 DMSSTT229E UNSUPPORTED OS DATA SET, ERROR 'code' RC=code

Note: You can invoke the STATE command from the terminal, from an EXEC file, or as a function from a program. If STATE is invoked as a function or from an EXEC file that has the &CONTROL NOMSG option in effect, the message DMSSTT002E FILE fn ft fm NOT FOUND is not issued.

SVCTRACE

SVCTRACE

Use the SVCTRACE command to trace and record information about supervisor calls occurring in your virtual machine. The format of the SVCTRACE command is:

```
SVCTrace | {ON }  
          | {OFF }
```

where:

ON starts tracing all SVC instructions issued within CMS.

OFF stops SVC tracing.

Usage Notes

1. The trace information recorded on the printer includes:
 - The virtual storage location of the calling SVC instruction and the name of the called program or routine.
 - The normal and error return addresses.
 - The contents of the general registers both before the SVC-called program is given control and after a return from that program.
 - The contents of the general registers when the SVC handling routine is finished processing.
 - The contents of the floating-point registers before the SVC-called program is given control and after a return from that program.
 - The contents of the floating-point registers when the SVC handling routine is finished processing.
 - The parameter list passed to the SVC.
2. To terminate tracing previously established by the SVCTRACE command, issue the H0 or SVCTRACE OFF commands. SVCTRACE OFF and H0 cause all trace information recorded, up to the point they are issued, to be printed on the virtual spooled printer. On typewriter terminals SVCTRACE OFF can be issued only when the keyboard is unlocked to accept input to the CMS command environment. To terminate tracing at any other point in system processing, H0 must be issued. To suspend tracing temporarily during a session, interrupt processing and enter the Immediate command S0 (Suspend Tracing). To resume tracing that was suspended with the S0 command, enter the Immediate command R0 (Resume Tracing).

If you issue the CMS Immediate command HX or you log off the VM/370 system before termination of tracing previously set by the SVCTRACE command, the switches are cleared automatically and all recorded trace information is printed on the virtual spooled printer.

Responses

A variety of information is printed whenever the

SVCTRACE ON

command is issued.

The first line of trace output starts with a -, or +, or *. The format of the first line of trace output is:

$$\left\{ \begin{array}{l} + \\ - \\ * \end{array} \right\} \text{ N/D = xxx/dd name FROM loc OLDPSW = psw1 GOPSW = psw2 [RC=rc]}$$
where:

- indicates information recorded before processing the SVC.
- + indicates information recorded after processing the SVC, unless * applies.
- * indicates information recorded after processing a CMS SVC which had an error return.

N/D is an abbreviation for SVC number and depth (or level).

xxx is the number of the SVC call (they are numbered sequentially).

dd is the nesting level of the SVC call.

name is the macro or routine being called.

loc is the program location from which the SVC was issued.

psw1 is the PSW at the time the SVC was called.

psw2 is the PSW with which the routine being called is invoked, if the first character of this line is a minus sign (-). If the first character of this line is a plus sign or asterisk (+ or *), PSW2 represents the PSW which returns control to the user.

rc is the return code from the SVC handling routine in general register 15. This field is omitted if the first character of this line is a minus sign (-), or if this is an OS SVC call. For a CMS SVC, this field is 0 if the line begins with a plus sign (+), and nonzero for an asterisk (*). Also, this field equals the contents of register 15 in the "GPRS AFTER" line.

The next two lines of output are the contents of the general registers when control is passed to the SVC handling routine. This output is identified at the left by ".GPRSB". The format of the output is:

```
.GPRSB = h h h h h h h h *dddddddd*
        = h h h h h h h h *dddddddd*
```

where h represents the contents of a general register in hexadecimal format and d represents the EBCDIC translation of the contents of a general register. The contents of general registers 0 through 7 are printed on the first line, with the contents of registers 8 through F on the second line. The hexadecimal contents of the registers are printed first, followed by the EBCDIC translation. The EBCDIC translation is preceded and followed by an asterisk(*) .

SVCTRACE

The next line of output is the contents of general registers 0, 1, and 15 when control is returned to your program. The output is identified at the left by ".GPRS AFTER :". The format of the output is:

```
.GPRS AFTER : R0-R1 = h h *dd* R15 = h *d*
```

where h represents the hexadecimal contents of a general register and d is the EBCDIC translation of the contents of a general register. The only general registers that CMS routines alter are registers 0, 1, and 15 so only those registers are printed when control returns to your program. The EBCDIC translation is preceded and followed by an asterisk (*).

The next two lines of output are the contents of the general registers when the SVC handling routine is finished processing. This output is identified at the left by ".GPRSS." The format of the output is:

```
.GPRSS = h h h h h h h h *dddddddd*  
       = h h h h h h h h *dddddddd*
```

where h represents the hexadecimal contents of a general register and d represents the EBCDIC translation of the contents of a general register. General registers 0 through 7 are printed on the first line with registers 8 through F on the second line. The EBCDIC translation is preceded and followed by an asterisk (*).

The next line of output is the contents of the calling routine's floating-point registers. The output is identified at the left by ".FPRS". The format of the output is:

```
.FPRS = f f f f *gggg*
```

where f represents the hexadecimal contents of a floating-point register and g is the EBCDIC translation of a floating-point register. Each floating point register is a doubleword; each f and g represents a doubleword of data. The EBCDIC translation is preceded and followed by an asterisk (*).

The next line of output is the contents of floating-point registers when the SVC handling routine is finished processing. The output is identified by ".FPRSS" at the left. The format of the output is:

```
.FPRSS = f f f f *gggg*
```

where f represents the hexadecimal contents of a floating-point register and g is the EBCDIC translation. Each floating-point register is a doubleword and each f and g represents a doubleword of data. The EBCDIC translation is preceded and followed by an asterisk (*).

The last two lines of output are only printed if the address in register 1 is a valid address for the virtual machine. If printed, the output is the parameter list passed to the SVC. The output is identified by ".PARM" at the left. The output format is:

```
.PARM = h h h h h h h h *dddddddd*  
       = h h h h h h h h *dddddddd*
```

where h represents a word of hexadecimal data and d is the EBCDIC translation. The parameter list is found at the address contained in register 1 before control is passed to the SVC handling program. The EBCDIC translation is preceded and followed by an asterisk (*).

Figure 17 summarizes the types of SVC trace output.

Identification	Comments
{ + } { - } N/D { * }	The SVC and the routine which issued the SVC.
.GPRSB	Contents of general registers when control is passed to the SVC handling routine.
.GPRS AFTER	Contents of general registers 0, 1, and 15 when control is returned to your program.
.GPRSS	Contents of the general registers when the SVC handling routine is finished processing.
.FPRS	Contents of floating-point registers before the SVC-called program is given control and after returning from that program.
.FPRSS	Contents of the floating-point registers when the SVC handling routine is finished processing.
.PARM	The parameter list, when one is passed to the SVC.

Figure 17. Summary of SVC Trace Output Lines

Messages and Return Codes

```
DMSOVR014E INVALID FUNCTION 'function' RC=24
DMSOVR047E NO FUNCTION SPECIFIED RC=24
DMSOVR104S ERROR 'nn' READING FILE 'DMSOVR MODULE' ON DISK RC=100
DMSOVR109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
```

SYNONYM

SYNONYM

Use the SYNONYM command to invoke a table of synonyms to be used with, or in place of, CMS and user-written command names. You create the table yourself using the CMS Editor. The form for specifying the entries for the table is described under "The User Synonym Table."

The names you define can be used either instead of or in conjunction with the standard CMS command truncations. However, no matter what truncations, synonyms, or truncations of the synonyms are in effect, the full real name of the command is always accepted. The format of the SYNONYM command is:

```
SYNONYM | [fn [SYNONYM [fm]]] [(options...)]
         | [ [ [A] ] ]
         | [ * ] ]
         |
         |
         | options: [STD] [CLEAR]
         | [NOSTD]
         | ]
```

where:

fn is the filename of the file containing your synonyms table.

fm is the filemode of the file containing your synonyms; if omitted, your A-disk and its extensions are searched. If you specify fm, you must enter the keyword, SYNONYM. If you specify fm as an asterisk (*), all disks are searched for the specified SYNONYM file.

Options:

STD specifies that standard CMS abbreviations are accepted.

NOSTD standard CMS abbreviations are not to be accepted. (The full CMS command and the synonyms you defined can still be used.)

CLEAR removes any synonym table set by a previously entered SYNONYM command.

Usage Notes

1. If you enter the SYNONYM command with no operands, the system synonym table and the user synonym table (if one exists) are listed.
2. The SET ABBREV ON or OFF command, in conjunction with the SYNONYM command, determines which standard and user-defined forms of a particular CMS command are acceptable.

THE USER SYNONYM TABLE

You create the synonym table using the CMS Editor. The table must be a file with the filetype SYNONYM. The file consists of 80-byte fixed-length records in free form format with columns 73-80 ignored. The format for each record is:

```
systemcommand usersynonym count
```

where:

systemcommand is the name of the CMS command, or MODULE or EXEC file for which you are creating a synonym.

usersynonym is the synonym you are assigning to the command name. When you create the synonym, you must follow the same syntax rules as for commands, that is, you must use the character set used to create commands, the synonym may be no longer than 8 characters, and so on.

count is the minimum number of characters that must be entered for the synonym to be accepted by CMS. If omitted, the entire synonym must be entered (see the following example).

A table of command synonyms is built from the contents of this file. You may have several synonym files but only one may be active at a time. For example, if the synonym file named MYSYN contains:

```
MOVEFILE MVIT
```

then, after you have issued the command

```
synonym mysyn
```

the synonym MVIT can be entered as a command name to execute the MOVEFILE command. It cannot be truncated since no count is specified. If MYSYN SYNONYM contains

```
ACCESS GETDISK 3
```

then, the synonyms GET, GETD, GETDI, GETDIS, or GETDISK can be entered as the command name instead of ACCESS.

If you have an EXEC file named TDISK, you might have a synonym entry

```
TDISK TDISK 2
```

so that you can invoke the EXEC procedure by specifying the truncation TD.

The Relationship Between the SET ABBREV and SYNONYM Commands

The default values of the SET and SYNONYM commands are such that the system synonym abbreviation table is available unless otherwise specified.

The system synonym abbreviation table for the FILEDEF command states that FI is the minimum truncation. Therefore, the acceptable abbreviations for FILEDEF are: FI, FIL, FILE, FILED, FILEDE, and FILEDEF. The system synonym abbreviation table is available whenever both SET ABBREV ON and SYNONYM (STD) are in effect.

SYNONYM

If you have a synonym table with the file identification USERTAB SYNONYM A, that has the entry

```
FILEDEF USERNAME 3
```

then, USERNAME is a synonym for FILEDEF, and acceptable truncations of USERNAME are: USE, USEN, USENA, USENAM, and USERNAME. The user synonym abbreviation table is available whenever both SET ABBREV ON and SYNONYM USERTAB are specified.

No matter what synonyms and truncations are defined, the full real name of the command is always in effect.

Figure 18 lists the forms of the system command and user synonyms available for the various combinations of the SET ABBREV and SYNONYM commands.

Responses

| When you enter the SYNONYM command with no operands, the synonym table
| or tables currently in effect are displayed.

SYSTEM COMMAND	USER SYNONYM	SHORTEST FORM (IF ANY)
.	.	.
:	:	:
.	.	.

| This response is the same as the response to the command QUERY
| SYNONYM ALL.

| DMSSYN711I NO SYSTEM SYNONYMS IN EFFECT

| This response is displayed when you issue the SYNONYM command with
| no operands after the command SYNONYM (NOSTD) has been issued.

DMSSYN712I NO SYNONYMS (DMSINA NOT IN NUCLEUS)

The system routine which handles SYNONYM command processing is not in the system.

Other Messages and Return Codes

DMSSYN002E FILE 'fn ft fm' NOT FOUND RC=28
DMSSYN003E INVALID OPTION 'option' RC=24
DMSSYN007E FILE 'fn ft fm' NOT FIXED, 80 CHAR RECORDS RC=32
DMSSYN032E INVALID FILETYPE 'ft' RC=24
DMSSYN056E FILE 'fn ft fm' CONTAINS INVALID RECORD FORMATS RC=32
| DMSSYN066E 'option AND 'option' ARE CONFLICTING OPTIONS RC=24
DMSSYN104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100

Options	Acceptable Command Forms	Comments
SET ABBREV ON SYN USERTAB (STD)	FI FIL . . FILEDEF USE USEN . . USENAME	The ABBREV ON option of the SET command and the STD option of the SYNONYM command make the system table available. The user synonym, USERNAME is available because the synonym table (USERTAB) is specified on the SYNONYM command. The truncations for USERNAME are available because SET ABBREV ON was specified with the USERTAB also available.
SET ABBREV OFF SYN USERTAB (STD)	FILEDEF USENAME	The user-defined synonym, USERNAME, is permitted because the user synonym table (USERTAB) is specified on the SYNONYM command. No system or user truncations are permitted.
SET ABBREV ON SYN USERTAB (NOSTD)	FILEDEF USE USEN . . USENAME	The system synonym table is unavailable because the NOSTD option is specified on the SYNONYM command. The user synonym, USERNAME, is available because the user synonym table (USERTAB) is specified on the SYNONYM command and the truncations of USERNAME are permitted because SET ABBREV ON is specified with USERTAB also available.
SET ABBREV OFF SYN USERTAB (NOSTD)	FILEDEF USENAME	The system synonym table is made unavailable either by the SET ABBREV OFF command or by the SYN (NOSTD) command. The synonym, USERNAME, is permitted because the user-defined synonym table (USERTAB) is specified on the SYNONYM command. The truncations for USERNAME are not permitted because the SET ABBREV OFF option is in effect.
SET ABBREV ON SYN (CLEAR STD)	FI FIL . . FILEDEF	The user-defined table is now unavailable. The system synonym table is available because both the ABBREV ON option of the SET command and the STD option of the SYNONYM command are specified.
SET ABBREV OFF SYN (CLEAR STD)	FILEDEF	Because CLEAR is specified on the SYNONYM command, the synonym and its truncations are no longer available. Either the SET ABBREV OFF command or the SYNONYM (NOSTD) command make the system synonym table unavailable.
SET ABBREV ON SYN (CLEAR NOSTD)		
SET ABBREV OFF SYN (CLEAR NOSTD)		

Figure 18. System and User-Defined Truncations

TAPE

TAPE

Use the TAPE command to dump CMS-formatted files from disk to tape, load previously dumped files from tape to disk, and perform various control operations on a specified tape drive. TAPE is used solely for CMS files; therefore, the files on tape are in a unique CMS format. The TAPE command does not process multivolume files. Disk files to be dumped can contain either fixed- or variable-length records. The format of the TAPE command is:

TAPE	DUMP	{fn}	{ft}	{fm}					
		{*}	{*}	{*}					[(optionA optionB optionD)]
	LOAD	{fn}	{ft}	{fm}					[(optionB optionC optionD)]
		{*}	{*}	{A}					
	SCAN	{fn}	{ft}						[(optionB optionC optionD)]
		{*}	{*}						
	SKIP	{fn}	{ft}						[(optionB optionC optionD)]
		{*}	{*}						
	MODESET								[(optionD)]
	tapcmd	{n}							[(optionD)]
		{1}							
	<u>optionA:</u>	{WTM}							
		{NOWTM}							
	<u>optionB:</u>	{NOPrint}							
		{Print}							
		{Term}							
		{DISK}							
	<u>optionC:</u>	{EOT}							
		{EOF n}							
		{EOF 1}							
	<u>optionD:</u>	{TAPi}			{7TRACK}		{DEN den}		{TRTCH a}
		{TAP1}			{9TRACK}				
		{cuu}							
		{181}							

where:

DUMP {fn}{ft}{fm}
 {*}{*}{* }

umps one or more disk files to tape. If fn and/or ft is specified as an asterisk (*) all files that satisfy the other file identifier are dumped.

If fm is coded as a letter, that disk and its extensions are searched for the specified file(s). If fm is coded as a letter and number, only files with that mode number and letter are dumped. If fm is coded as *, all accessed disks are searched for the specified file(s). If fm is not specified, only the A-disk and its extensions are searched.

LOAD [{fn}{ft}{fm}]
 [{*}{*}{A}]

reads tape files onto disk. If a file identifier is specified, only that one file is loaded. If the option EOF n is specified and no file identifier is entered, n tape files are written to disk. If an asterisk (*) is specified for fn or ft, all files within EOF n that satisfy the other file identifier are loaded.

The files are written to the disk indicated by the filemode letter. The filemode number, if entered, indicates that only files with that filemode number are to be loaded.

SCAN [{fn}{ft}]
 [{*}{*}]

positions the tape at a specified point, and lists the identifiers of the files it scans. Scanning occurs over n tape marks, as specified by the option EOF n (the default is 1 tape file). However, if a file identifier (fn and ft) is specified, scanning stops upon encountering that file; the tape remains positioned in front of the file.

SKIP [{fn}{ft}]
 [{*}{*}]

positions the tape at a specified point and lists the identifiers of the files it skips. Skipping occurs over n tape marks, as specified by the option EOF n (the default is 1 tape mark). However, if a file identifier (fn and ft) is specified, skipping stops after encountering that file; the tape remains positioned after the file.

MODESET sets the values specified by the DEN, TRACK, and TRTCH options. These values remain in effect for the specified tape until they are changed in a subsequent TAPE command.

tapcmd [n]
 [1] specifies a tape control function (tapcmd) to be executed n times (default is 1 if n is not specified):
 []

<u>Tapcmd</u>	<u>Action</u>
BSF	Backspace <u>n</u> tape marks
BSR	Backspace <u>n</u> tape records
ERG	Erase gap
FSF	Forward space <u>n</u> tape marks
FSR	Forward space <u>n</u> tape records
REW	Rewind tape to load point
RUN	Rewind tape and unload
WTM	Write <u>n</u> tape marks

TAPE

Options: If conflicting options are specified, the last one entered is in effect.

WTM writes a tape mark on the tape after each file is dumped.

NOWTM writes a tape mark after each file is dumped, then backspaces over the tape mark so that subsequent files written on the tape are not separated by tape marks.

NOPRINT does not spool the list of files dumped, loaded, scanned, or skipped to the printer.

PRINT spools the list of files dumped, loaded, scanned, or skipped to the printer.

TERM displays a list of files dumped, loaded, scanned, or skipped at the terminal.

DISK creates a disk file containing the list of files dumped, loaded, scanned, or skipped. The disk file has the file identification of TAPE MAP A5.

EOT reads the tape until an end-of-tape indication is received.

EOF n reads the tape through a maximum of n tape marks. The
EOF 1 default is EOF 1.

TAPn specifies the symbolic tape identification (TAPn) or the
18n actual device address of the tape to be read from or written to where n is 1, 2, 3, or 4. The default is TAP1 or 181. The unit specified by cuu must previously have been attached to your CMS virtual machine before any tape I/O operation can be attempted. Only symbol names TAP1 through TAP4 and virtual device addresses 181 through 184 are supported.

7TRACK specifies a 7-track tape. Odd parity, data convert on, and translate off are assumed unless TRTCH is specified.

9TRACK specifies a 9-track tape.

DEN den is the tape density where den is 200, 556, 800, 1600, or 6250. If 200 or 556 is specified, 7TRACK is assumed. If 1600 or 6250 is specified, 9TRACK is assumed; if 800 is specified, 9TRACK is assumed unless 7TRACK is specified. In the case of either 800/1600 or 1600/6250 dual-density drives, 1600 is the default.

TRTCH a is the tape recording technique for 7-track tape. If TRTCH is specified, 7TRACK is assumed. One of the following must be specified as a:

<u>a</u>	<u>Meaning</u>
O	odd parity, data convert off, translate off
OC	odd parity, data convert on, translate off
OT	odd parity, data convert off, translate on
E	even parity, data convert off, translate off
ET	even parity, data convert off, translate on

Usage Notes

1. Tape records written by the CMS TAPE DUMP command are 805 bytes long. The first character is a binary 2 (X'02'), followed by the characters CMS and an EBCDIC blank (X'40'), followed by 800 bytes of file data packed without regard for logical record length. In the final record, the character N replaces the blank after CMS, and the data area contains CMS file directory information.
2. If a tape file contains a large number of CMS files, that would not fit on disk, the tape load operation may terminate if there is not enough disk space to hold the files. To prevent this, when you dump the files, separate logical files by tape marks, then forward space to the appropriate file.
3. Because the CMS file directory is the last record of the file, the TAPE command creates a separate workfile so that backspacing and rereading can be avoided when the disk file is built. If the load criteria is not satisfied the workfile is erased; if it is satisfied the workfile is renamed. This workfile is named TAPE CMSUT1, which may exist if a previous TAPE command has abnormally terminated. If the work file is accidentally dumped to tape and subsequently loaded, it appears on your disk as TAPE CMSUT2.
4. The RUN option (rewind and unload) indicates completion before the physical operation is completed. Thus, a subsequent operation to the same physical device may encounter a device busy situation.
5. For more information on tape file handling, see the CMS User's Guide.

Responses

DMSTPE701I NULL FILE

A final record was encountered and no prior records were read in a TAPE LOAD operation. No file is created on disk.

If the TERM option is in effect, the following is displayed at the terminal depending on the operation specified:

LOADING.....

```
fn ft fm
. . .
. . .
. . .
```

SKIPPING.....

```
fn ft fm
. . .
. . .
. . .
```

DUMPING.....

```
fn ft fm
. . .
. . .
. . .
```

SCANNING.....

```
fn ft fm
. . .
. . .
. . .
```

TAPE

When a tape mark is encountered the following is displayed at the terminal if the TERM option is specified:

END-OF-FILE OR END-OF-TAPE

Other Messages and Return Codes

```
DMSTPE002E FILE 'fn ft fm' NOT FOUND RC=28
DMSTPE003E INVALID OPTION 'option' RC=24
DMSTPE010E PREMATURE EOF ON FILE 'fn ft fm' RC=40
DMSTPE014E INVALID FUNCTION 'function' RC=24
DMSTPE017E INVALID DEVICE ADDRESS 'cuu' RC=24
DMSTPE023E NO FILETYPE SPECIFIED RC=24
DMSTPE027E INVALID DEVICE 'device name' RC=24
DMSTPE029E INVALID PARAMETER 'parameter' IN THE OPTION 'option' FIELD
RC=24
DMSTPE037E DISK 'mode' IS READ/ONLY RC=36
DMSTPE042E NO FILEID SPECIFIED RC=24
DMSTPE043E 'TAPn(cuu)' IS FILE PROTECTED RC=36
DMSTPE047E NO FUNCTION SPECIFIED RC=24
DMSTPE048E INVALID MODE 'mode' RC=24
DMSTPE057E INVALID RECORD FORMAT RC=32
DMSTPE058E END-OF-FILE OR END-OF-TAPE RC=40
DMSTPE070E INVALID PARAMETER 'parameter' RC=24
DMSTPE104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSTPE105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSTPE110S ERROR READING 'TAPn(cuu)' RC=100
DMSTPE111S ERROR WRITING 'TAPn(cuu)' RC=100
DMSTPE113S TAPn(cuu) NOT ATTACHED RC=100
| DMSTPE115S {CONVERSION|{7|9}-TRACK|{800|6250} BPI|TRANSLATION|DUAL
| DENSITY} FEATURE NOT SUPPORTED ON DEVICE 'cuu' RC=88
```


| TAPEMAC

| Use the TAPEMAC command to create a CMS MACLIB from an unloaded
 | partitioned data set (PDS) from a tape created by the IEHMOVE utility
 | program under OS. The PDS from which the tape was created can be
 | blocked, but the logical record length must be 80. The format of the
 | TAPEMAC command is:

```
|-----|
| TAPEMAC | fn [ (options...[ ] ) ]      options:
|         |                               [ TAPn ] [ ITEMCT yyyyy ]
|         |                               [ TAP1 ] [ ITEMCT 50000 ]
|         |                               [ ]     [ ]
|-----|
```

| where:

| fn specifies the filename of the first, or only, CMS MACLIB to be
 | created on the A-disk. If fn MACLIB already exists on the A-disk,
 | the old one is erased; no warning message is issued.

| Options:

| TAPn specifies the symbolic address of the tape, where n is a number
 | between 1 and 4 corresponding to virtual device addresses 181
 | through 184, respectively. The default is TAP1.

| ITEMCT yyyyy
 | specifies the item count threshold of each MACLIB to be
 | created, which is the maximum number of records to be written
 | into each file. yyyyy is a number between 0 and 62500 (commas
 | are not allowed). If ITEMCT is not specified, the default is
 | 50000.

| Usage Notes

| 1. Tape records are read and placed into fn MACLIB until the file size
 | exceeds the ITEMCT (item count); loading then continues until the
 | end of the current member is reached. Then another CMS file is
 | created; its filename consists of the number 2 appended to the end
 | of the filename specified (fn) if the filename is 7 characters or
 | less. The appended number overlays the last character of the
 | filename if the name is 8 characters long. Loading then continues
 | with this new name. For example, if you enter the command

```
|         tapemac mylib
```

| you may create files named MYLIB MACLIB, MYLIB2 MACLIB, MYLIB3
 | MACLIB...

| This process continues until up to nine CMS files have been
 | created. If more data exists on the tape than can fit in 9 CMS
 | files, processing is terminated with the error message DMSTMA139S.
 | The maximum size of the unloaded PDS which can be loaded into CMS
 | MACLIBs would be approximately 9 times 62500 or 584,500 records.

TAPEMAC

| Responses

| The TAPEMAC command displays the message:

| LOADING fn MACLIB

| for each macro library created.

| Other Messages and Return Codes

| DMSTMA001E NO FILENAME SPECIFIED RC=24
| DMSTMA003E INVALID OPTION 'option' RC=24
| DMSTMA057E INVALID RECORD FORMAT RC=32
| DMSTMA070E INVALID PARAMETER 'parameter' RC=24
| DMSTMA105S ERROR nn WRITING FILE fn ft ON DISK RC=100
| DMSTMA109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
| DMSTMA110S ERROR READING TAPn RC=100
| DMSTMA137S ERROR nn ON STATE FOR fn ft RC=100
| DMSTMA138S ERROR nn ERASING 'fn ft' BEFORE LOADING TAPE RC=100
| DMSTMA139S TAPE FILE EXCEEDS 9 CMS MACLIBS RC=104

TAPPDS

Use the TAPPDS command to create CMS disk files from tapes created by the following OS utility programs:

- IEBTPCH (files may be sequential or partitioned, but must be in unblocked card-image format).
- IEBUPDTE (files may be blocked or unblocked).
- IEHMOVE (unloaded partitioned data sets are read).

The tape can be unlabeled or it can contain OS standard labels. The format of the TAPPDS command is:

```

TAPPDS  [fn [ft [fm]]] [(options...[ ])]
        [ * | * | A1 ]
        [   |   | * ]
        [   |   |   ]

options: [ PDS ] [ COL1 ] [ TAPn ]
         [ NOPDS ] [ NOCOL1 ] [ TAP1 ]
         [ UPDATE ]

         [ END ] [ MAXTEN ]
         [ NOEND ] [ NOMAXTEN ]

```

where:

fn is the filename of the disk file to be created from the sequential tape file. If the tape contains members of a partitioned data set (PDS), **fn** must be specified as an asterisk; one file is created for each member with a filename the same as the member name. If NOPDS or UPDATE is specified, and you do not specify **fn**, or specify it as *, the default filename is TAPPDS.

ft is the filetype of the newly created files. The default filetypes are CMSUT1 (for PDS or NOPDS) and ASSEMBLE (for UPDATE). The defaults are used if **ft** is omitted or specified as *.

fm is the mode of the disk to contain the new files. If this field is omitted or specified as an asterisk (*), A1 is assumed.

Options: If conflicting options are specified, the last one entered is used. All options, except TAPn, are ignored when unloaded PDS tapes are read.

PDS indicates that the tape contains members of an OS partitioned data set, each preceded by a MEMBER NAME=name statement. The tape must have been created by the OS IEBTPCH service program if this option is specified.

NOPDS indicates that the tape contains one file.

TAPPDS

UPDATE	indicates that the tape file is in IEBUPDTE control file format. The filename of each file is taken from the NAME= parameter in the "./ ADD" record that precedes each member. (See Usage Note 2.)
COL1	reads data from columns 1-80. You should specify this option when you use the UPDATE option.
<u>NOCOL1</u>	reads data from columns 2-81; column 1 contains control character information. This is the format produced by the OS IEBTPCH service program.
TAPn	is the tape unit number. n can be 1, 2, 3, or 4, representing virtual units 181, 182, 183, and 184, respectively. If not specified, TAP1 is assumed.
END	considers an END statement a delimiter for the current member.
<u>NOEND</u>	specifies that END statements are not to be treated as member delimiters, but are to be processed as text.
MAXTEN	reads up to ten members. This is valid only if the PDS option is selected.
<u>NOMAXTEN</u>	reads any number of members.

Usage Notes

1. You can use the TAPE command to position a tape at a particular tape file before reading it with the TAPPDS command.
2. If you use the UPDATE option, you must also specify the COL1 option. Each tape record is scanned for a "./ ADD" record beginning in column 1. When a "./ ADD" record is found, subsequent records are read onto disk until the next "./ ADD" record is encountered or until a "./ ENDUP" record is encountered.

A "./ ENDUP" record or a tape mark ends the TAPPDS command execution; the tape is not repositioned.

"./ label" records are not recognized by CMS and are included in the file as data records.

If the NAME= parameter is missing on the "./ ADD" record or if it is followed by a blank, TAPPDS uses the default filename, TAPPDS, for the CMS disk file. If this happens more than once during the execution of the command, only the last unnamed member is contained in the TAPPDS file.

3. If you are reading a macro library from a tape created the IEHMOVE utility, you can create a CMS MACLIB file directly by using the TAPEMAC command.

Responses

```
DMSTPD703I FILE 'fn ft [fm]' COPIED
```

The named file is copied to disk.

DMSTPD707I TEN FILES COPIED

The MAXTEN option was specified and ten members have been copied.

If the tape being read contains standard OS labels, the labels are displayed at the terminal.

Other Messages and Return Codes

DMSTPD003E INVALID OPTION 'option' RC=24
DMSTPD058E END-OF-FILE OR END-OF-TAPE RC=40
DMSTPD105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
| DMSTPD109S VIRTUAL STORAGE CAPACITY EXCEEDED RC=104
DMSTPD110S ERROR 'nn' READING 'TAPn(cuu)' RC=100

TXTLIB

TXTLIB

Use the TXTLIB command to update CMS text libraries. The format of the TXTLIB command is:

TXTLib	{	GEN libname fn1 [fn2 ...]	}	
	{	ADD libname fn1 [fn2 ...]	}	<u>options:</u>
	{	DEL libname membername1 [membername2...]	}	[TERM]
	{	MAP libname [(options...)]	}	[DISK]
				[PRINT]

where:

GEN creates a TXTLIB on your A-disk. If a TXTLIB with the same name already exists, it is replaced.

ADD adds TEXT files to the end of an existing TXTLIB on your A-disk. No checking is done for duplicate names, entry points or CSECTs.

DEL deletes members from a TXTLIB on your A-disk, and compresses the TXTLIB to remove unused space. If more than one member exists with the same name, only the first entry is deleted.

MAP lists information about TXTLIB members, including their names (entry points), locations in the library, and size.

libname specifies the filename of a file with a filetype of TXTLIB, which is to be created or listed, or from which members are to be deleted or added.

fn1 [fn..] specifies the names of files with a filetype of TEXT, that you want to add to a TXTLIB.

membername1 [membername2] specifies the names of TXTLIB members that you want to delete.

Options:

TERM displays information about the TXTLIB on your terminal.

DISK writes a CMS file, named libname MAP A5, that contains a list of TXTLIB members.

PRINT spools a copy of the TXTLIB map to the virtual printer.

Usage Notes

1. When a TEXT file is added to a library, its membername(s) are taken from the CSECT names or NAME statements in the TEXT file. Deletions and LOAD or INCLUDE command references must be made on these names. For example, a TEXT file with a filename of TESTPROG that contains CSECTs named CHECK and RECHECK, when added to a TXTLIB, creates members named CHECK and RECHECK.

2. If you want your TXTLIBs to be searched for missing subroutines during CMS loader processing, you must identify the TXTLIB on a GLOBAL command, for example

```
global txtlib newlib
```

3. You may add OS linkage editor control statements NAME, ALIAS, ENTRY, and SETSSI to a TEXT file before adding it to a TXTLIB. You must follow OS linkage editor conventions concerning format (column 1 must be blank) and placement within the TEXT file.
4. TXTLIB members are not fully link-edited, and may return erroneous entry points during dynamic loading.
5. The total number of members in the TXTLIB file cannot exceed 1000. When this number is reached, an error message is displayed. The text library created includes all the text files entered up to (but not including) the one that caused the overflow.

Responses

When the TXTLIB MAP command is issued with the TERM option, the contents of the directory of the specified text library are displayed at the terminal. The number of entries in the text library (xxx) is also displayed.

```
ENTRY INDEX
name location
.
.
.
xxx ENTRIES IN LIBRARY
```

Other Messages and Return Codes

```
DMSLBT001E NO FILENAME SPECIFIED RC=24
DMSLBT002E FILE 'fn ft' NOT FOUND RC=28
DMSLBT002W FILE 'fn ft' NOT FOUND RC=4
DMSLBT003E INVALID OPTION 'option' RC=24
DMSLBT013E MEMBER 'name' NOT FOUND IN LIBRARY 'fn ft fm' RC=32
DMSLBT014E INVALID FUNCTION 'function' RC=24
DMSLBT046E NO LIBRARY NAME SPECIFIED RC=24
DMSLBT047E NO FUNCTION SPECIFIED RC=24
DMSLBT056E FILE 'fn ft fm' CONTAINS [NAME|ALIAS|ENTRY|ESD] INVALID
RECORD FORMATS RC=32
DMSLBT056W FILE 'fn ft fm' CONTAINS [{NAME|ALIAS|ENTRY|ESD}] INVALID
RECORD FORMATS RC=4
DMSLBT104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
DMSLBT105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
DMSLBT106S NUMBER OF MEMBER NAMES EXCEEDS MAX 'nnnn'. FILE 'fn ft' NOT
ADDED RC=88
DMSLBT213W LIBRARY 'fn ft fm' NOT CREATED RC=4
```



```
MEMBER { * }
MEM     { name }
```

displays member(s) of a library. If ft is MACLIB or TXTLIB, a MEMBER entry can be specified. If an asterisk (*) is specified, all members of the library are displayed. If a name is specified, only that particular member is displayed.

Responses

The file is displayed at the terminal according to the given specifications. When you use the HEX option, each record is preceded by a header record:

```
RECORD nnnnn LENGTH=nnnnn
```

Other Messages and Return Codes

```
DMSTYP002E FILE 'fn ft fm' NOT FOUND RC=28
DMSTYP003E INVALID OPTION 'option' RC=24
DMSTYP005E NO 'option' SPECIFIED RC=24
DMSTYP009E COLUMN 'col' EXCEEDS RECORD LENGTH RC=24
DMSTYP013E MEMBER 'name' NOT FOUND IN LIBRARY RC=32
DMSTYP029E INVALID PARAMETER 'parameter' [IN THE OPTION 'option' FIELD]
RC=24
DMSTYP033E FILE 'fn ft fm' IS NOT A LIBRARY RC=32
DMSTYP039E NO ENTRIES IN LIBRARY 'fn ft fm' RC=32
DMSTYP049E INVALID LINE NUMBER 'line number' RC=24
DMSTYP054E INCOMPLETE FILEID SPECIFIED RC=24
DMSTYP062E INVALID * IN FILEID RC=20
DMSTYP104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
```


NOSEQ8 specifies that columns 73-75 contain a 3-character label field, and that the sequence number is a 5-digit value in columns 76-80.

INC puts sequence numbers in columns 73 through 80 of each updated record inserted from the update file.

NOINC puts asterisks (*****) in the sequence number field of each updated record inserted from the update file.

CTL specifies that fn2, ft2, and fm2 describe an update control file for applying multiple update files to the source input file (see "The CTL Option").

Note: The CTL option implies the INC option.

NOCTL specifies that a single update file is to be applied to the source input file.

STK stacks information resulting from a multiple update at your CMS console. This information can then be read by a CMS EXEC procedure. STK is used only with the CTL option.

NOSTK specifies that no external communication of the multiple update results is desired.

TERM displays warning messages at the terminal whenever a sequence or update control card error is discovered. (Such warning messages appear in the update log, whether they are displayed at the terminal or not.)

NOTERM suppresses the display of warning messages at the terminal. However, error messages which terminate the entire update procedure are displayed at the terminal.

DISK places the update log file on disk. This file has a file identifier "fn UPDLOG", where "fn" is the filename of the file being updated.

PRINT prints the update log file directly on the virtual printer.

STOR specifies that the source input file is to be read into storage and the updates performed in storage prior to placing the updated source file on disk. This option is meaningful only when used in conjunction with CTL option since the benefit of increased processing speed is realized when processing multiple updates. STOR is the default when CTL is specified.

NOSTOR specifies that no updating is to take place in storage. NOSTOR is the default when performing single updates or when CTL is omitted from the command line.

UPDATE

Control Statements

The UPDATE control statements let you insert, delete and replace source records, as well as resequence the output file. All UPDATE control statements are identified by the characters './' in columns 1 and 2 of the 80-byte record, followed by one or more blanks and a maximum of six additional, blank-delimited fields. Control statement data must not extend beyond column 50. All references to the sequence field of an input record refer to the numeric data in columns 73-80 of the source record, or columns 76-80 if NOSEQ8 is specified. Leading zeros in sequence fields are not required. If no sequence numbers exist in an input file, a preliminary UPDATE with only the './ S' control statement can be used to establish file sequencing.

Any sequence fields in the update control statements are ignored; if the NOINC option is specified, all sequence fields in the update file are ignored, including those on inserted records. If the INC option is specified, sequence fields for the inserted records are either generated by UPDATE, if the dollar-sign (\$) delimiter is used, or are included intact from the update file if the dollar sign (\$) is not used.

Changes are made sequentially in a single pass through the input and update files; an error condition results if any sequence errors occur in the update control statements, and warnings are issued if an error is detected in the sequencing of the input file. Any source input records with a sequence field of eight blanks are skipped, without any indication of a sequence error. Such records may be replaced or deleted only if they occur within a range of records that are being replaced or deleted entirely and if that range has limits with valid sequence numbers. There is no means provided for specifying a sequence field of blanks on an update control statement.

Control Statement Formats

SEQUENCE Control Statement -- resequences the updated source output file in columns 73-80 (if SEQ8 is specified), or in columns 76-80 with the label placed in columns 73-75 (if NOSEQ8 is specified). If this statement is included in the update file, it must be the first control statement. The format of the SEQUENCE control statement is:

```
./ S [seqstrt [seqincr [label]]]
```

where:

seqstrt is a 1- to 8-digit numeric field specifying the first decimal sequence number to be used. The default value is 1000 if SEQ8 is specified and 10 if NOSEQ8 is specified.

seqincr is a 1- to 8-digit numeric field specifying the decimal increment for resequencing the output file. The default is the 'seqstrt' value.

label is a 3-character field to be duplicated in columns 73-75 of each source record if NOSEQ8 is specified. The default value is the first three characters of the input filename (fn1).

An error is indicated if any valid control statement precedes the ./ S statement in the update file, and the resequence operation is suppressed.

Each source record is resequenced in columns 73-80 as it is written onto the output file. Unchanged records from the input file and records inserted from the update file are resequenced.

INSERT Control Statement -- inserts all records following it, up to the next control statement, into the output file. The format of the INSERT control statement is:

```
./ I seqno [$ [seqstrt [seqincr]]]
```

where:

seqno is the sequence number of the source input record following which the insertion is to be made.

\$ is an optional delimiter indicating that the inserted records are to be sequenced by increments.

seqstrt is a 1- to 8-digit numeric field specifying the first decimal number to be used for sequencing the inserted records.

seqincr is a 1- to 8-digit numeric field specifying the decimal increment for sequencing the inserted records.

All records following the "./ I" statement, up to the next control statement, are inserted in the output file following the record identified by the "seqno" field. If the NOINC option is specified, each inserted record is identified with asterisks (*****) in columns 73-80. If either the INC or CTL option is specified, the records are inserted unchanged in the output file, or they are sequenced according to the "seqstrt" and "seqincr" fields, if the dollar sign (\$) key is specified.

The default sequence increment, if the dollar sign is included, is determined by using one tenth of the least significant, nonzero digit in the seqno field, with a maximum of 100. The default seqstrt is computed as seqno plus the default seqincr. For example, the control statement:

```
./ I 2600 $ 2610
```

causes the inserted records to be sequenced XXX02610, XXX02620, and so forth (NOSEQ8 assumed here). For the control statement:

```
./ I 240000 $
```

the defaulted seqincr is the maximum, 100, and the starting sequence number is 240100. SEQ8 is assumed, so the inserted records are sequenced 00240100, 00240200, and so forth.

If either INC or CTL is specified but the dollar sign is not included, whatever sequence number appears on the inserted records in the update file is included in the output file.

UPDATE

DELETE Control Statement -- deletes one or more records from the source file. The format of the DELETE control statement is:

```
./ D seqno1 [seqno2] [$]
```

where:

seqno1 is the sequence number identifying the first or only record to be deleted.

seqno2 is the sequence number of the last record to be deleted.

\$ is an optional delimiter indicating the end of the control fields.

All records of the input file, beginning at seqno1, are deleted from the output file, up to and including the seqno2 record. If the seqno2 field is omitted, only a single record is deleted.

REPLACE Control Statement -- replaces one or more input records with updated records from the update file. The format of the REPLACE control statement is:

```
./ R seqno1 [seqno2] [$ [seqstrt [seqincr]]]
```

where:

seqno1 is the sequence number of the first input record to be replaced.

seqno2 is the sequence number of the last record to be replaced.

\$ is an optional delimiter key indicating that the substituted records are to be sequenced incrementally.

seqstrt is a 1- to 8-digit numeric field specifying the first decimal number to be used for sequencing the substituted records.

seqincr is a 1- to 8-digit numeric field specifying the decimal increment for sequencing the substituted records.

All records of the input file, beginning with the seqno1 record, up to and including the seqno2 record, are replaced in the output file by the records following the "./ R" statement in the update file, up to the next control statement. As with the "./ D" (delete) function, if the seqno2 field is omitted, only a single record is replaced, but it may be replaced by more than a single inserted record. The "./ R" (replace) function is performed as a delete followed by an insert, such that the number of statements inserted need not match the number deleted. The dollar sign (\$), seqstrt, and seqincr processing is identical to that for the insert function.

COMMENT Statements --The format of the COMMENT statement is:

```

./ * [comment]

```

where:

- * indicates that this is a comment statement, and is to be ignored, except that it is copied into the log file.

Summary of Input and Output Files for the UPDATE Command

The following discussions describe the files used and created by the UPDATE command, and the placement of the files created.

Input Files When a Single Update Is to Be Applied: When the CTL option is not specified in the UPDATE command line, only one update is applied to the source file. The input files are:

- The source file, which is to be updated. The filename of this file must be specified in the command line. The filetype and filemode default to ASSEMBLE and A1, respectively, unless overridden by the command line.
- The update file, whose control statements have been described under "Control Statement Formats." The filename of this file defaults to the filename of the source file, and the filetype and filemode default to UPDATE and A1, respectively. All three may be overridden by the command line.

Output Files When a Single Update Is Applied: When a single update is applied to the source file, the following output files are created:

- An updated source file is created. "\$fn" becomes the name of this file, where "fn" is the filename of the original source file, unless the REP option is specified. When the REP option is specified, the filename of this file becomes "fn". (For exceptions, see "Warning and Error Handling").
- An update log, showing all transactions and errors, is created. The filename of the file is the filename of the original source file, and the filetype of this file is UPDLOG. Note, however, that if the PRINT option is specified with the command line, then the update log is printed directly on the virtual spooled printer, and no disk file is created.

Input Files When Multilevel Updates Are Applied: When the CTL option is specified on the command line, multilevel updates are applied to the source file. In this case, the following files are input to the UPDATE command:

- A source file, specified in exactly the same way as the source file for a single update.
- A control file that controls what updates are applied, and the order in which they are to be applied. The filename of this file defaults to the filename of the source file, and the filetype and filemode default to CNTRL and A1, respectively. All three may be overridden by the command line. This file contains, in its control statements,

UPDATE

pointers to update files, PTF files, and auxiliary files (these are described under "The CTL Option").

- One or more update files, as specified by the control file. The filename of these files is the same as the filename of the source file. The filetype of these files is "UPDTxxxx".
- Auxiliary files, as specified by the control file. The filename of these files is the same as the filename of the source file. The filetype of these files is "AUXxxxx". The filetype can be specified as either 'AUXnnnn' or 'nnnn AUX'. If you use the second form, the first three characters may not be 'AUX'. The auxiliary files contain additional control statements pointing to PTF files. The format of the auxiliary files is described under, "The CTL Option."
- PTF files, as specified by either the control file or the auxiliary files. The filename of these files is the same as the filename of the source file. The filetype is specified in full by the control file or the auxiliary file. In format, these files are identical to ordinary update files.

Output Files When Multilevel Updates Are Applied: When the CTL option is specified, the following output files are created by the UPDATE command:

- An updated source file, as in the case of a single update.
- An update log, as in the case of a single update.
- An UPDATES file. This file has the filename of the original source file, and a filetype of UPDATES. It contains information summarizing the updates that were applied to the file, and that are to be concatenated onto the assembly text deck for documentation and information.
- Although not a disk file, additional output is produced in the form of lines placed in the terminal read stack, for interrogation by an EXEC file which may have invoked the UPDATE command. These lines are placed there only if the STK option is specified.

Disk Mode of Output Files: If several read/write disks are accessed when the UPDATE command is invoked, the following steps are taken to determine the disk upon which the output files are to be placed (the search stops as soon as one of the following steps is successful):

1. If the disk on which the original source file resides is read/write, then the output files are placed on that disk.
2. If that disk is a read-only extension of a read/write disk, then the output files are placed on that particular read/write disk.
3. Otherwise, the output files are placed on the primary read/write disk (the A-disk).

The CTL Option

If the NOCTL option is specified or defaulted, UPDATE processes one input file and one update file to produce an updated source output file and an update log file containing a record of what changes were made. This mode of operation is suitable for testing modifications prior to incorporating them in the base source code, providing that only one set of changes has to be tested at a time. If, for any reason, more than one set of changes is outstanding against a single source input file, the difficulties in managing that base code can multiply very rapidly.

For this reason, UPDATE provides the CTL option, which has a multilevel update control and management scheme developed for updating VM/370 distributed source code, and may be used wherever its advantages are felt.

The major components of the multilevel update scheme are:

- A set of base source code which is not permanently changed.
- A set of update files for each source file that must be applied in a specific order.
- One or more CNTRL files that describe the order or priority of updates to be applied to each source file.
- Optionally, one or more auxiliary control files, each pertaining to a specific source file.

An integral part of the multilevel update scheme is a naming convention for the update files themselves, and for any TEXT files produced by assembling or compiling the updated output files. In normal usage, any update file has the filename of the source file to which it applies and the filetype of UPDATE. When the CTL option is used to invoke the multilevel update controls, the filename usage becomes a requirement, such that the update files must have the filename of the source file to which they apply, but the filetypes are modified to distinguish between separate update levels. The filetype for an update file is constructed from UPDT plus a 1- to 4-character update identifier. For example, if the command

```
UPDATE DMSUPD ASSEMBLE A1 X4 CNTRL A1 (CTL
```

is issued, the source file is DMSUPD ASSEMBLE A1 and the control file is X4 CNTRL A1. Assume that the control file contains three update files, named "DMSUPD UPDT750", "DMSUPD UPDTX4", and "DMSUPD UPDT009." The CNTRL file specifies which update files are to be applied to the source file and in what order they are to be applied, on the basis of the update identifier. Another identification parameter, the update level identifier, is used when naming a TEXT file produced from the updated source file. The update level identifier is specified by the CNTRL file and is associated with a specific update identifier, also in the CNTRL file. For example, in applying the preceding update to DMSUPD ASSEMBLE, a file named X4 CNTRL might appear as follows:

```
00D MACS DMSLIB SYSLIB
X4D UPDTX4
75X UPDT750
009X UPDT009
```

This control file applies the updates DMSUPD UPDT009, DMSUPD UPDT750, and DMSUPD UPDTX4, in that order, to the file DMSUPD ASSEMBLE. The updates are applied in reverse order as they appear in the CNTRL file, that is, the lowest level of update is at the bottom of the file, and the highest level update is at the top. As the CNTRL file and update files are processed, the UPDATE command displays the following message at the terminal:

```
DMSUPD178I UPDATING ['fn ft fm'] WITH 'fn ft fm'
```

for each update file which is applied to the source input during the multilevel update; the bracketed expression is displayed only for the first update.

In the preceding example, the fields X4D, 75X, and 009X are the update level identifiers, associated with the UPDTX4, UPDT750, and

UPDATE

UPDT009 update identifiers, respectively. According to the naming convention for VM/370 TEXT files, the result of assembling the updated \$DMSUPD ASSEMBLE file would be named DMSUPD TTX4D, where the X4D is the update level identifier of the highest-level update applied. The TXT portion of the filetype indicates that this is a TEXT file, but allows up to a 5-character update level identifier.

For more information on using update control files, see the VM/370: Planning and System Generation Guide.

The STK/NOSTK Options

The STK option is provided for use with the multilevel update invoked via the CTL option, primarily for communication with CMS EXEC procedures which invoke UPDATE. If the CTL and STK options are specified, UPDATE places two lines of data in the CMS terminal read stack, as follows:

first line = * update level identifier

second line = * library list from 'MACS' record

These lines are placed in the terminal read stack via the CMS ATTN function, and are available to an invoking EXEC procedure via the EXEC control words &READ ARGS or &READ VARS. The first line, the update level identifier, is the level identifier of the highest level update applied; this is the TEXT file filetype-modifier used by the VM/370 update procedures. The second line consists of the list of libraries specified on the MACS record in the CNTRL file. The library search order for an assembly or compilation can be established by issuing the GLOBAL command using the library list returned.

If the NOSTK option is used with the multilevel update, no data is made available to external procedures and the update level identifier has no meaning.

Example of Multilevel Update

If the command

```
update proga assemble * proga cntrl * (ctl stk)
```

is issued and the contents of the PROGA CNTRL file are :

```
-----  
| * THIS IS AN EXAMPLE OF A CONTROL FILE  
| 00D MACS MYLIB SYSLIB  
| * FIX FOR SAVING ALL REGISTERS  
| 00A UPDTLVL4  
| PTF A7300DMS  
| * AUX FILE CONTAINING UPDATES FOR B1 FEATURE  
| 00B AUXLVL3  
|-----
```

and the contents of the PROGA AUXLVL3 file are :

```
-----  
| * PTF A2330DMS CONTAINS FUNCTIONAL CODE FOR B1  
| PTF A2330DMS  
| * PTF A0915DMS CONTAINS ERROR MESSAGES FOR B1  
| PTF A0915DMS  
|-----
```

The following files are used to update PROGA ASSEMBLE in the order indicated.

<u>Filename</u>	<u>Filetype</u>
PROGA	A0915DMS
PROGA	A2330DMS
PROGA	A7300DMS
PROGA	UPDTLVL4

The resultant output file \$PROGA ASSEMBLE contains the updates from the four files listed. In addition, two lines are placed in front of the CMS terminal read stack:

```
* 00A
* MYLIB SYSLIB
```

If the UPDATE command shown was issued from an EXEC procedure and followed by the EXEC commands:

```
&READ VARS &I1 &I2
&READ VARS &I3 &I4 &I5
```

then

```
&I1 = *
&I2 = 00A
&I3 = *
&I4 = MYLIB
&I5 = SYSLIB
```

In this example, the UPDATE command was entered from the terminal and the stacked lines are ignored by CMS.

Warning and Error Handling

The UPDATE command detects a number of invalid requests, and decides whether they should be treated as warning situations or as errors. The following general description shows the handling of these situations, and the return codes associated with each situation.

Sequencing and Update Control Card Errors: These errors are treated as "warning situations." That is, a warning message is generated, and processing continues. The warning messages are printed in the update log, and are displayed on the terminal unless the NOTERM option is specified in the command line. The errors are:

- Input sequencing errors (return code = 4). The input source file contains sequence errors (that is, one or more control cards are not in ascending order).
- Output sequencing errors (return code = 8). The updating procedure introduces new sequencing errors into the output source file.
- Invalid update control statements (return code = 12). The update file contains invalid control statements. Erroneous statements in control files cause the update procedure to terminate.

If more than one such error is detected, the UPDATE command returns the highest return code (4, 8, or 12) encountered.

UPDATE

If any such error is detected, the REP option, if specified, is ignored, and the update source file retains the filename "\$fn", as if NOREP was in effect.

Other Errors: Other errors are invalid control file statements, invalid file formats, and disk input/output errors. The UPDATE command processing is terminated as soon as the error is detected. The return code is always 20 or greater.

If any such error is detected, the update file is left with the filename UPDATE and the filetype CMSUT1, so that you may examine or otherwise make use of it. This file must be erased before the UPDATE command can be invoked again.

Responses

FILE 'fn ft fm,' REC #n = update control statement

This message is displayed when the TERM option is specified and an error is detected in an update file. It identifies the file and record number where the error is found.

DMSUPD177I WARNING MESSAGES ISSUED (SEVERITY=nn). ['REP' OPTION IGNORED.]

Warning messages were issued during the updating process. The severity shown in the error message in the 'nn' field is the highest of the return codes associated with the warning messages which were generated during the updating process.

The warning return codes have the following meanings:

RC = 4; Sequence errors were detected in the original source file being updated.

RC = 8; Sequence errors which did not previously exist in the source file being updated were introduced in the output file during the updating process.

RC = 12; Any other nonfatal error detected during the updating process. Such errors include invalid update file control statements, and missing PTF files.

The severity value is passed back as the return code from the UPDATE command. In addition, if the REP option is specified in the command line, then it is ignored, and the updated source file has the fileid "\$fn1 ft1", as if the REP option was not specified.

DMSUPD178I UPDATING ['fn ft fm'] WITH 'fn ft fm'

The specified update file is being applied to the source file. This message appears only if the CTL option is specified in the command line. The updating process continues.

| DMSUPD304I UPDATE PROCESSING WILL BE DONE USING DISK

| An insufficient amount of virtual storage was available to perform
 | the updating in virtual storage, so a CMS disk must be used. This
 | message is displayed only if NOSTOR was specified in the UPDATE
 | command line.

Other Messages and Return Codes

DMSUPD001E NO FILENAME SPECIFIED RC=4
 DMSUPD002E FILE 'fn ft fm' NOT FOUND RC=28
 DMSUPD003E INVALID OPTION 'option' RC=24
 DMSUPD007E FILE 'fn ft fm' IS NOT FIXED, 80 CHAR. RECORDS RC=32
 DMSUPD010W PREMATURE EOF OF FILE 'fn ft fm' --SEQ NUMBER '.....' NOT
 FOUND RC=12
 | DMSUPD024E FILE 'UPDATE CMSUT1 fm' ALREADY EXISTS RC=28
 DMSUPD037E DISK 'mode' IS READ/ONLY RC=36
 DMSUPD048E INVALID MODE 'mode' RC=24
 DMSUPD065E 'option' OPTION SPECIFIED TWICE RC=24
 DMSUPD066E 'option' AND 'option' ARE CONFLICTING OPTIONS RC=24
 DMSUPD069E DISK 'mode' NOT ACCESSED RC=36
 DMSUPD070E INVALID PARAMETER 'parameter' RC=24
 DMSUPD104S ERROR 'nn' READING FILE 'fn ft fm' FROM DISK RC=100
 DMSUPD105S ERROR 'nn' WRITING FILE 'fn ft fm' ON DISK RC=100
 DMSUPD174W SEQUENCE ERROR INTRODUCED IN OUTPUT FILE: '.....' TO
 '.....' RC=8
 DMSUPD176W SEQUENCING OVERFLOW FOLLOWING SEQ NUMBER'.....' RC=8
 DMSUPD179E MISSING OR DUPLICATE 'MACS' CARD IN CONTROL FILE 'fn ft fm'
 RC=32
 DMSUPD180W MISSING PTF FILE 'fn ft fm' RC=12
 DMSUPD181E NO UPDATE FILES WERE FOUND RC=40
 DMSUPD182W SEQUENCE INCREMENT IS ZERO RC=8
 DMSUPD183E INVALID {CONTROL|AUX} FILE CONTROL CARD RC=32
 DMSUPD184W './S ' NOT FIRST CARD IN INPUT FILE --IGNORED RC=12
 DMSUPD185W INVALID CHAR IN SEQUENCE FIELD '.....' RC=12
 DMSUPD186W SEQUENCE NUMBER '.....' NOT FOUND RC=12
 DMSUPD187E OPTION 'STK' INVALID WITHOUT 'CTL' RC=24
 DMSUPD207W INVALID UPDATE FILE CONTROL CARD RC=12
 DMSUPD210W INPUT FILE SEQUENCE ERROR: '.....' TO '.....' RC=4
 | DMSUPD299E INSUFFICIENT STORAGE TO COMPLETE UPDATE RC=40
 | DMSUPD300E INSUFFICIENT STORAGE TO BEGIN UPDATE RC=40

Immediate Commands

1 Immediate Commands

You can issue an Immediate command only after causing an attention interrupt by pressing the Attention key (or its equivalent). These commands are processed as soon as they are entered. They are also executed immediately when they are stacked in an EXEC procedure. Any program execution in progress is suspended until the Immediate command is processed.

None of the Immediate commands issue responses.

HB

Use the HB command to stop the execution of a CMS batch virtual machine at the end of the current job. The format of the HB Immediate command is:

```
| HB |
```

Usage Notes

1. If the batch virtual machine is running disconnected, it must be reconnected.
2. When the HB command is executed, CMS sets a flag such that at the end of the current job, the batch processor generates accounting information for the current job and then logs out the CMS batch virtual machine.

HO

Use the HO command during the execution of a command or one of your programs to stop the recording of trace information. Program execution continues to its normal completion, and all recorded trace information is spooled to the printer. The format of the HO command is:

```
| HO |
```

HT

Use the HT command to suppress all terminal output generated by any CMS command or your program that is currently executing. The format of the HT command is:

```
HT |
```

Usage Notes

1. Program execution continues. When the Ready message is displayed, normal terminal output resumes. Use the RT command to restore typing or displaying.
2. CMS error messages having a suffix letter of W, E, S, or T cannot be suppressed.

HX

Use the HX command to stop the execution of any CMS or CMS/DOS command or program, close any open files or I/O devices, and return to the CMS command environment. The format of the HX command is:

```
HX |
```

Usage Notes

1. HX clears all file definitions made via the FILEDEF or DLBL commands, including those entered with the PERM option.
2. The HX command is executed when the next SVC or I/O interrupt occurs, therefore a delay may occur between keying HX and the return to CMS. All terminal output generated before HX is processed is displayed before the command is executed.

RO

Use the RO command, during the execution of a command or one of your programs, to resume the recording of trace information that was temporarily suspended by the SO command. Program execution continues to its normal completion, and all recorded trace information is spooled to the printer. The format of the RO command is:

```
RO |
```

Immediate Commands

RT

Use the RT command to restore terminal output from an executing CMS command or one of your programs that was previously suppressed by the HT command. The format of the RT command is:

```
| RT |
```

Usage Notes

1. Program execution continues, and displaying continues from the current point of execution in the program. Any terminal output that is generated after the HT command is issued and up to the time the RT command is issued is lost. Execution continues to normal program completion.

SO

Use the SO command during the execution of a command or one of your programs to temporarily suspend the recording of trace information. Program execution continues to its normal completion and all recorded trace information is spooled to the printer. The format of the SO command is:

```
| SO |
```

Usage Notes

1. To resume tracing, issue the RO command.

Section 3: EDIT Subcommands and Macros

This section describes the formats and operands of the EDIT subcommands and macros. EDIT subcommands are valid only in the environment of the CMS Editor, which is invoked with the EDIT command. The EDIT command format is described in "Section 2. CMS Commands."

The editor has two modes of operation: edit mode and input mode. Whenever the EDIT command is issued, edit mode is entered; when the INPUT or REPLACE subcommands are issued with no operands, input mode is entered. In input mode, all lines you enter are written into the file you are editing. To return to edit mode from input mode, you must enter a null line (one that has no data on it).

For a functional description of the CMS Editor, and tutorial information on using it, consult the VM/370: CMS User's Guide.

For a summary of the default settings assumed by the editor for CMS reserved filetypes, see "Appendix A: Reserved Filetype Defaults."

EDIT Subcommands

The EDIT subcommands are listed in alphabetical order for easy reference. Each subcommand description includes the format, a list of operands (if any), usage notes, and responses. For those subcommands that operate somewhat differently on a 3270 terminal than on a typewriter terminal, an additional discussion, "Display Mode Considerations," is added.

Subcommands that are valid only with 3270 terminals, namely SCROLL, SCROLLUP and FORMAT have the notation "(3270 only)" next to the subcommand names. The FORWARD and BACKWARD subcommands, which were designed for use with 3270 terminals but can be issued at any terminal, have the notation "(primarily 3270)" next to the subcommand names.

ALTER

Use the ALTER subcommand to change a specific character to another character, one that may not be available on your terminal keyboard. The ALTER subcommand allows you to reference characters by their hexadecimal values. The format of the ALTER subcommand is:

Alter	char1 char2	[n	[G]]
		[*	[*]]
		[1	[]]
		[[]]

where:

- char1 specifies the character to be altered. It may be specified either as a single character or as a pair of hexadecimal digits (00 through FF).
- char2 specifies the character to which char1 is to be altered. It may be specified either as a single character or as a pair of hexadecimal digits.
- n indicates the number of lines to be searched for the specified character. If you specify an asterisk (*), all lines in the file, beginning with the current line, are searched. If this option is omitted, then only the current line is searched.
- G requests the editor to alter every occurrence of char1 in the lines specified. If G or * is not specified, only the first occurrence of char1 in each line specified is altered.

Usage Notes

1. If char2 is a hexadecimal value that cannot be represented on your terminal, the character space it occupies appears blank. For example,

```
input XSLC
alter X 02
SLC
```

Column 1 contains a X'02', which cannot be displayed.

2. Use the ZONE subcommand if you want only particular columns searched for a specific character.

Responses

When verification is on, each line that is altered is displayed at your terminal.

AUTOSAVE

Use the AUTOSAVE subcommand to set, reset, or display the automatic save function of the editor. When the automatic save function is in effect, the editor automatically issues the SAVE subcommand each time the specified number of changes or insertions are made. The format of the AUTOSAVE subcommand is:

```

| AUTOSave | [ n ]
|           | [ OFF ]
|           | [ ]

```

where:

n is a decimal number between 1 and 32767, indicating the frequency of the automatic save function. One SAVE subcommand is issued for every **n** lines that are changed, deleted, or added to the file.

OFF turns off the automatic save function.

Usage Notes

1. Each line affected by the \$MOVE macro is treated as one update. However, all changes caused by a single CHANGE, DELETE, DSTRING, GETFILE, or OVERLAY subcommand are treated as a single update, no matter how many lines are affected.
2. If you do not issue the AUTOSAVE subcommand, the default setting is OFF.
3. If you are editing a file on a read-only disk, and an automatic save request occurs, the message


```

| SET NEW FILEMODE AND RETRY
|
| is issued. You can enter CMS subset and access the disk in
| read/write mode, or use the FMODE subcommand to change the filemode
| to the mode of a read/write disk. If you were in input mode, you
| are placed in edit mode.

```

 is issued. You can enter CMS subset and access the disk in read/write mode, or use the FMODE subcommand to change the filemode to the mode of a read/write disk. If you were in input mode, you are placed in edit mode.
4. The message "_SAVED" is displayed at the terminal each time the save operation occurs.

Responses

If you issue the AUTOSAVE subcommand with no operands, the editor displays the current setting of the automatic save function.

BACKWARD (Primarily 3270)

Use the BACKWARD subcommand to move the current line pointer towards the beginning of the file you are editing. The format of the BACKWARD subcommand is:

```
Backward | [r ]  
         | |n|  
         | |1|  
         | [ ]
```

where:

n is the number of records backward you wish to move the current line pointer. If n is not specified, the current line pointer is moved up one line, toward the top of the file.

Usage Notes

1. The BACKWARD subcommand is equivalent to the UP subcommand; it is provided for the convenience of 3270 users.

Responses

When verification is on, the new current line is displayed on line 9 of the display screen. If n exceeds the number of records in the file above the current line, TOP is displayed on line 9.

On a typewriter terminal the new current line is typed if verification is on.

BOTTOM

Use the BOTTOM subcommand to make the last line of the file the new current line. The format of the BOTTOM subcommand is:

```
Bottom |
```

Usage Notes

1. Use the BOTTOM subcommand followed by the INPUT subcommand to begin entering new lines at the end of a file.

Responses

When verification is on, the last line in the file is displayed.

Display Mode Considerations

If the BOTTOM subcommand is issued at a 3270 display terminal in display mode, EOF: is displayed on line 10, lines 2 through 9 contain the last eight records of the file, and lines 11 through 23 are blank.

CASE

Use the CASE subcommand to indicate how the editor is to process uppercase and lowercase letters. The format of the CASE subcommand is:

```

CASE      | [ ]
           | [M]
           | [U]
           | [ ]

```

where:

M indicates that the editor is to accept any mixture of uppercase and lowercase letters for the file as they are entered at the terminal.

U indicates that the editor is to translate all lowercase letters to uppercase letters before the letters are entered into the file. U is the default value for all filetypes except MEMO and SCRIPT.

Responses

If you enter the CASE subcommand with no operand, the current setting is displayed at the terminal.

Display Mode Considerations

If you specify CASE M when using a 3270 that does not have the lowercase feature (RPQ), you can key in lowercase characters, but they appear on the screen as uppercase characters.

CHANGE

Use the CHANGE subcommand to change a specified group of characters to another group of characters of the same or a different length. You may use the CHANGE subcommand to change more than one line at a time. The format of the CHANGE subcommand is:

```

Change    | [ /string1 [ /string2 [ [ [ ] ] ] ] ]
           | [ * * ]
           | [ 1 ]
           | [ [ ] ]

```

where:

/ (diagonal) signifies any unique delimiting character that does not appear in the character strings involved in the change.

string1 specifies a group of characters to be changed (old data). string1 may be a null string.

string2 specifies the group of characters that are to replace string1 (new data). string2 may be a null string; if omitted, it is assumed null.

EDIT Subcommands—CHANGE

- n or *** indicates the number of lines to be searched, starting at the current line. If * is entered, the search is performed until the end of the file is reached. If this option is omitted, then only one line is searched.
- G or *** requests the editor to change every occurrence of string1 in the lines specified. If G or * is not specified, only the first occurrence of string1 in each line specified is changed. If string1 is null, G or * may not be specified.

Usage Notes

1. The first nonblank character following the CHANGE subcommand (or any of its truncation) is considered the delimiter. For example:

```
c.VM/370.CMS.*
```

changes the first occurrence of VM/370 to CMS on every line from the current line to the end of the file.

2. If string2 is omitted, it is assumed to be a null string. For example,

```
THIS ISN THE LINE.  
change /n  
THIS IS THE LINE.
```

A null string causes a character deletions. If string1 is null, characters are inserted at the beginning of the line, for example,

```
THIS IS THE LINE.  
change //SO /  
SO THIS IS THE LINE.
```

3. To change multiple occurrences of the same string on one line, enter

```
change/string1/string2/ 1 *
```

4. The CHANGE subcommand can be used on typewriter terminals to display, without changing, any lines that contain the information specified in string1. Enter:

```
change /string1/string1/ * *
```

5. Use the ZONE subcommand to indicate which columns are to be searched for string1. If string1 is wider than the current zone, you receive the message

```
ZONE ERROR
```

and you should either re-enter the CHANGE subcommand or change the zone setting.

6. If the character string inserted causes the data line to extend beyond the truncation column or the zone column, any excess characters are truncated. (See the description of the TRUNC subcommand for additional information on truncation.)
7. You should use the ALTER subcommand when you want to change a single character to some special character (one that is not available on your keyboard).

Responses

When verification is on, every line that is changed is displayed.

Display Mode Considerations

If you issue the CHANGE subcommand without operands at a 3270 display terminal in display mode, the following occurs:

1. The record pointed to by the current line pointer appears in the user input area of the display.
2. You can then alter the record in the user input area by retyping part or all of the line, or by using the Insert, Delete, or Erase EOF keys to insert or delete characters.
3. When the line is modified, press the Enter key, which causes the record in the user input area to replace the old record at the current line in the output display area.

If you bring a line down to the user input area and decide not to change it, press the Erase Input key and then the Enter key, and the line is not changed.

When a line is moved to the user input area, all nonprintable characters (including tabs, backspaces, control characters, and so on) are stripped from the line. Also, any characters currently assigned to VM/370 logical line editing symbols (#, @, \$, ") are reinterpreted when the line is reentered. You should issue an explicit CHANGE subcommand to change to lines containing special characters.

The CHANGE subcommand is treated as an invalid subcommand if it is issued without operands at a typewriter terminal or at a 3270 display terminal that is not in display mode.

| When you request a global change on a 3270 terminal, the display is
| changed only once, to reflect the final position of the current line
| pointer. The editor displays, in the message area of the display
| screen:

```
|      {nnnn} LINE(S) CHANGED
|      {NO  }
```

| to indicate the number of lines that were updated. If the change
| request resulted in the truncation of any lines, the message is
| displayed as:

```
|      nnnn LINE(S) CHANGED nnnn LINE(S) TRUNCATED
```

| If the change request moves the current line pointer beyond the end
| of the file, the word EOF: is displayed on line 9, preceded by the last
| seven records of the file. Lines 10 through 23 are blank.

CMS

Use the CMS subcommand to cause the editor to enter the CMS subset mode, where you may execute those CMS commands that do not need to use the main storage being used by the editor. The format of the CMS subcommand is:

```

|-----|
| CMS   |
|-----|
    
```

Usage Notes

1. You can execute any CMS command that is nucleus resident or that executes in the transient area in CMS subset. The nucleus-resident CMS commands are:

CP	GENMOD	START
DEBUG	INCLUDE	STATE
ERASE	LOAD	STATEW
FETCH	LOADMOD	

The commands that execute in the transient are:

ACCESS	LISTFILE	RELEASE
ASSGN	MODMAP	RENAME
COMPARE	OPTION	SET
DISK	PRINT	SVCTRACE
DLBL	PUNCH	SYNONYM
FILEDEF	QUERY	TAPE
GENDIRT	READCARD	TYPE
GLOBAL		

- To return to edit mode, use the CMS subset command RETURN.
2. If you attempt to execute a CMS command that requires main storage, you receive the message:
- ```

| INVALID SUBSET COMMAND
|
| You should not attempt to execute any program that executes in the
| user program area. Using the LOAD, INCLUDE (RESET), FETCH, START,
| and RUN commands could load programs that would overlay the
| editor's storage area and its contents. Use these commands only
| for programs that execute in the transient area.
|
| 3. In an edit macro, if you attempt to use a command that is invalid
| in CMS subset, you receive a return code of -2.

```

### Responses

After you issue the CMS subcommand, you receive the message

```
CMS SUBSET
```

to indicate that you are in CMS subset mode. On a display terminal, the screen is cleared before the editor issues this message; the display of the file is restored when you enter the RETURN command.



## DELETE

Use the DELETE subcommand to delete one or more lines from a file, beginning with the current line. The line immediately following the last line deleted becomes the new current line. The format of the DELETE subcommand is:

```

Delete | []
 | [n]
 | [*]
 | [1]
 | []

```

### where:

n indicates the number of lines to be deleted, starting at the current line. If \* is entered, the remainder of the file is deleted. If n is omitted, only one line is deleted.

### Responses

None. If you delete the last line in the file, or if you issue the DELETE subcommand when the current line pointer is already at the end of the file, the editor displays the message

EOP:

### Display Mode Considerations

If you delete a record when using a display terminal in display mode, the editor rewrites the output display area with the top seven records unchanged. The bottom 12 records move up by one, and a new record (if one exists) moves into the bottom of the output display area (line 23).

## DOWN

Use the DOWN subcommand to advance the line pointer forward in the file. The line pointed to becomes the new current line. The format of the DOWN subcommand is:

```

Down | []
 | [n]
 | [1]
 | []

```

### where:

n indicates the number of lines to advance the pointer, starting at the current line. If it is not specified, the line pointer is advanced one line.

## EDIT Subcommands—DOWN, DSTRING

### Usage Notes

1. DOWN is equivalent to the NEXT and FORWARD subcommands.

### Responses

When verification is on, the new current line is displayed at the terminal; if the end of the file is reached, the message

EOF:

is displayed.

## DSTRING

Use the DSTRING subcommand to delete one or more lines beginning with the current line, down to, but not including, the first line containing a specified character string. The current line is not checked for the character string. The format of the DSTRING subcommand is:

```
| DString | /[string[/]] |
```

### where:

/ (diagonal) signifies any unique delimiting character that does not appear in the string.

string specifies the group of characters to be checked for. If string is not specified, only the current line is deleted.

### Usage Notes

1. The zone set by the ZONE subcommand or the default zone setting is checked for the presence of the character string. A character string with a length greater than the current zone setting causes the error message ZONE ERROR.

### Responses

If the character string is not found by the end of the file, no deletions occur, the current line pointer is unchanged, and the message

STRING NOT FOUND, NO DELETIONS MADE

is displayed.

### Display Mode Considerations

When the DSTRING subcommand is issued at a display terminal in display mode, if verification is on, the screen is changed to reflect the deletions from the file.

**FILE**

Use the FILE subcommand to write the edited file on disk and, optionally, override the file identifier originally supplied in the EDIT command. The format of the FILE subcommand is:

```
FILE | [fn [ft [fm]]]
```

where:

- fn indicates the filename for the file. If filename is omitted, filetype and filemode cannot be specified, and the existing filename, filetype, and filemode are used.
- ft indicates the filetype for the file.
- fm indicates the filemode for the file.

Usage Notes

1. When you specify a file identifier, any existing file that has an identical fileid is replaced. If the file being edited had been previously written to disk, that copy of the file is not altered.
2. You can change the filename and filemode during the editing session using the FNAME and FMODE subcommands.

Responses

The CMS Ready message indicates that the file has been written to disk and control is returned to the CMS environment.

**FIND**

Use the FIND subcommand to locate a line based on its initial character string. The format of the FIND subcommand is:

```
Find | [line]
```

where:

- line is any character string, including blanks and tabs, that you expect to find beginning in column 1 of an input record. If line is not specified, the current line pointer is moved down one line.

Usage Notes

1. Only one blank can be used as a delimiter following the FIND subcommand; additional blanks are considered part of the character string.
2. If the image setting is ON, the editor expands tab characters to the appropriate number of blanks before searching for the line.

## EDIT Subcommands-FIND, FMODE

3. If the current line pointer is at the bottom of the file when the FIND subcommand is issued the search begins at the top of the file.

### Responses

When verification is on, the line is displayed at the terminal. If the line is not found, the message

EOF:

is displayed and you may use the REUSE (=) subcommand to search again, beginning at the top of the file.

## FMODE

Use the FMODE subcommand to display or change the filemode of a file. The format of the FMODE subcommand is:

```
| FMode | [fm]
```

### where:

fm indicates the filemode that is to replace the current filemode setting. You can specify only a filemode letter (A-G, S, Y, or Z), or a filemode letter and number (0-5). If you specify a filemode letter, the existing filemode number is retained.

### Usage Notes

1. The specified filemode is used the next time a FILE, SAVE, or automatic save request is issued. If the file being edited had been previously filed or saved, that copy of the file remains unchanged.
2. If the disk specified by filemode already contains a file with the same filename and filetype, that file is replaced when a FILE, SAVE, or automatic save request is issued; no warning message is issued.
3. If the filemode specified is that of a read-only disk, then when an attempt is made to file or save the file, the editor displays an error message.

### Responses

If you enter the FMODE subcommand without specifying fm, the editor displays the current filemode.

### Display Mode Considerations

When you specify a new filemode with the FMODE subcommand, the editor writes the new filemode in the filemode field at the top of the screen.

**FNAME**

Use the FNAME subcommand to display or change the filename of a file. The format of the FNAME subcommand is:

```
| FName | [fn]
```

where:

fn indicates the filename that is to replace the current filename.

Usage Notes

1. The specified filename is used the next time a FILE, SAVE, or automatic save request is issued. If the file being edited had been previously filed or saved, that copy of the file remains unchanged.
2. If a file already exists with the specified filename and the same filetype and filemode, that file is replaced; no warning message is issued.
3. You can use the FNAME subcommand when you want to make multiple copies of a file, with different filenames, without terminating your edit session.

Responses

If you enter the FNAME subcommand without specifying fn, the editor displays the current filename.

Display Mode Considerations

When you issue the FNAME subcommand specifying a new filename, the editor writes the new name in the filename field at the top of the screen.

**FORMAT (3270 only)**

Use the FORMAT subcommand to change the mode of a local or remote 3270 terminal from display to line (or line to display) mode. The format of the FORMAT subcommand is:

```
| FORMat | { DISPLAY }
| | { LINE }
```

where:

DISPLAY specifies that a full screen display of data is to occur. Subcommands do not appear as part of the data displayed.

## EDIT Subcommands--FORMAT, FORWARD

LINE specifies that the display station is to operate as a typewriter terminal. Every line you enter is displayed on the screen; the screen looks like a typewriter terminal's console sheet.

### Usage Notes

1. Line mode is the default for remote 3270s. If you are using a remote 3270 in display mode, and you enter the INPUT subcommand, you are placed in line mode while you enter input. When you return to edit mode, the full screen display is restored.
2. If you used the NODISP option of the EDIT command to invoke the editor, the FORMAT subcommand is treated as an invalid subcommand, as it is on typewriter terminals.
3. The column settings for the VERIFY, TRUNC, and ZONE subcommands remain unchanged when you issue the FORMAT subcommand.

### Responses

None.

## FORWARD (Primarily 3270)

Use the FORWARD subcommand to move the current line pointer towards the end of the file you are editing. The format of the FORWARD subcommand is:

```
Forward | []
 | [n]
 | [1]
 | []
```

### where:

n is the number of records you wish to move forward in the file being edited. If n is not specified, 1 is assumed.

### Usage Notes

1. The FORWARD subcommand is equivalent to the DOWN and NEXT subcommands; it is provided for the convenience of 3270 users.

### Responses

When verification is on, the new current line is displayed. If the number specified exceeds the number of lines remaining in the file, the current line pointer is positioned at EOF:.

## GETFILE

Use the GETFILE subcommand to insert all or part of a specific CMS file into a file that you are editing. The format of the GETFILE subcommand is:

```

|-----|
| Getfile | fn [ft [fm [firstrec [numrec]]]] |
| | | | | | | | | | |
| | | | | | | | | | |
| | | | | | | | | | |
| | | | | | | | | | |
|-----|

```

### where:

fn is the filename of the file that contains the data to be inserted into the file you are editing.

ft is the filetype of the file that contains the data to be inserted. If ft is not specified, the filetype of the file you are editing is assumed.

fm is the filemode of the file that contains the data to be inserted. If fm is not specified, all of your accessed disks are searched for the file.

firstrec indicates the record number of the first record you want to copy.

numrec indicates the number of lines to be inserted, starting with the line specified by firstrec. If numrec is not specified, or specified as \*, then the remainder of the file between firstrec and the end of the file is inserted.

### Usage Notes

1. The GETFILE operand list is positional; if you omit one operand, you cannot specify any operands that follow. Thus, if you want to specify firstrec and lastrec, you must specify the filetype and filemode of the file.
2. The last line inserted becomes the new current line.
3. If the record length of the records in the file containing the data to be inserted exceeds that of the file being edited, an error message is displayed, and the GETFILE is not executed; if shorter, the records are padded to the record length of the file being edited and inserted in the file.
4. If you use the GETFILE subcommand to insert lines into a VSBASIC file, you must also use the RENUM subcommand to resequence the file.
5. If the editor fills up available storage while executing a GETFILE request, it may not be able to copy all of the file. You should determine how many records were actually copied, and then write the current file on disk.

## EDIT Subcommands—GETFILE, IMAGE

### Responses

When verification is on, the last line inserted into the file is displayed. If the end of the file has been reached the message

```
EOF REACHED
```

is displayed, followed by the display of the last line inserted.

### IMAGE

Use the IMAGE subcommand to control how the editor should handle backspaces and tab characters or to display the current image setting. The format of the IMAGE subcommand is:

```
IMAGE | [ON] |
 | [OFF] |
 | [CANON] |
 | [] |
```

### where:

**ON** specifies that any text entered while in input mode or as a line of data following a FIND, INPUT, OVERLAY, or REPLACE subcommand, is expanded into a line image; backspaces are removed and tabs are replaced by blanks.

Text entered in the form of delimited strings, as in CHANGE, LOCATE, and ALTER, is not expanded; tabs and backspaces are treated in the same way as other characters.

IMAGE ON is the default for all filetypes except SCRIPT.

**OFF** specifies that tabs and backspaces are treated as data characters in the same way as other characters. They are not deleted, translated, expanded, or reordered.

**CANON** specifies that backspaces may be used to produce compound characters such as underscored words, headings, or phrases. Before they are inserted in the file, compound characters are ordered, with backspaces arranged singly between the characters that overlay each other; the overlaying characters are arranged according to their EBCDIC values. Tab characters are handled as for IMAGE OFF.

CANON is the default for SCRIPT files.

### Usage Notes

1. When the image setting is ON, tab characters are expanded to an appropriate number of blanks, according to the current settings of the TABSET subcommand. The TABSET command has no effect if the image setting is either off or canon.



2. When the image setting is on, backspaces are handled as follows:
  - Backspace characters act in a similar manner to the logical character delete symbol, in deleting the previous characters if a sufficient number of other characters or blanks follow the backspace characters. However, backspace characters that immediately follow a command name are interpreted as separator characters and do not delete any part of the command name.
  - If a backspace character is the last character in the input line, it is ignored.

### Responses

When you issue the IMAGE subcommand with no operand, the current IMAGE setting is displayed.

## INPUT

Use the INPUT subcommand to insert a single line into a file, or, if no data line is specified, to leave edit mode and enter input mode. The format of the INPUT subcommand is:

```
[Input | [line]]
```

### where:

line specifies the input line to be entered into the file. It can contain blanks and tabs; if you enter at least two blanks following the INPUT subcommand and no additional text, a blank line is inserted into the file.

### Usage Notes

1. Each line that is inserted into the file becomes the new current line.
2. When you are using line-number editing (LINEMODE LEFT or LINEMODE RIGHT) you cannot use the INPUT subcommand to insert a single line of data; use the nnnnn subcommand.

### Responses

When you issue the INPUT subcommand with two operands, and verification is on, the editor displays:

INPUT:

All subsequent lines you entered are written into the file, until you enter a null line to return to edit mode.

Display Mode Considerations

1. When you insert lines when using a local display terminal in display mode, the editor writes each record on line 9. The old current line and all records above it move up one line, except for the topmost record formerly on line 2, which is deleted from the screen.
2. If you are using a remote display terminal in display mode and you issue the INPUT subcommand with no text, the terminal is forced into line mode. The display of the file on the screen disappears and the word INPUT: appears. As you enter input lines, they appear in the output display area. When you leave input mode by entering a null line, the remote terminal returns to display mode. The display of the file reappears on the screen, with the lines you have just entered in their proper place in the file.
3. When you are entering data in input mode at a display terminal that is in line mode, a tab character generated by a program function (PF) key only generates one character, and appears as one character on the screen. That is, the line does not appear spaced according to the tab settings.

**LINEMODE**

Use the LINEMODE subcommand to set, cancel, or display the status of line-number editing. When you use line-number editing, you can input, locate, and replace lines by referencing their record numbers. Line-number editing is the default for VSBASIC and FREEFORT files. The format of the LINEMODE subcommand is:

```

|-----|
| LINEmode | [LEFT] |
| | [RIGHT] |
| | [OFF] |
| | [] |
|-----|

```

where:

**LEFT** initializes line-number editing and places sequence numbers on the left, in columns 1 through 5, right justified and blank padded; the near zone is set to 7. If the filetype is FREEFORT, columns 1 through 8 are used for serial numbers; the near zone is set to 9.

You should never use left-handed line-number editing for files in which data must occupy columns 1 through 6, for example ASSEMBLE files.

**RIGHT** initializes line-number editing and places sequence numbers on the right, in columns 76 to 80, right justified and zero padded. The end zone and truncation columns are set to 72.

This operand is valid only for files with fixed-length 80-character records.

OFF cancels line-number editing and (if you were using left-handed line-number editing) resets the first logical tab setting to column 1. The VERIFY, TRUNC, and ZONE subcommand settings remain unchanged. Serialization may still be in effect. OFF is the default for all filetypes except VSBASIC and FREEFOT.

#### Usage Notes

1. When you enter input mode while you are using line-number editing, you are prompted with a line number to enter each line. The default prompting increment is 10; you may change it using the PROMPT subcommand.
2. When you are prompted on a typewriter terminal, enter your input line on the same line as the prompted line number. If you are using right-handed line-number editing, on a typewriter terminal or on a display terminal in line mode, the serial numbers are not redisplayed in columns 76 to 80 (unless you use the VERIFY subcommand to increase the verification setting). When a line is displayed in edit mode, the line numbers always appear on the left, even though they are on the right in the disk copy of the file. Whether or not the line numbers are displayed on the right depends on the current verification setting.
3. You cannot use the INPUT or REPLACE subcommands to input a single data line when you are using line-number editing; use the nnnnn subcommand instead.
4. When you initialize line-number editing for files that already exist, the editor assumes that the records are in the proper format and numbered in ascending order.
5. If you want to place serial numbers in columns 76 through 80, but you do not wish to use line-number editing, use the SERIAL subcommand.

#### Responses

When you issue the LINEMODE subcommand with no operands, the current setting is displayed.

#### Display Mode Considerations

When you use line-number editing on a display terminal in display mode, the prompting numbers in input mode appear on line 2 of the display screen, in the editor message area. Enter your input lines in the user input area. Regardless of whether you are using right- or left-handed line-number editing, the line numbers always appear in their true position in the file.

## LOCATE

Use the LOCATE subcommand to scan the file beginning with the next line for the first occurrence of a specified character string. The format of the LOCATE subcommand is:

```
[[Locate] | /[string[/]]]
```

### where:

/ (diagonal) signifies any unique delimiting character that does not appear in the string. The delimiter may be any nonblank character. The closing delimiter is optional.

string specifies any group of characters to be searched for in the file.

### Usage Notes

1. If the beginning delimiter is /, you can omit the subcommand name LOCATE. If you enter only

/

on a line, the current line pointer is moved down one line.

2. If string is null or blank, the search is successful on the first line encountered. If the line pointer is at the end of the file when the LOCATE subcommand is issued, scanning starts from the top of the file.
3. Use the ZONE subcommand when you want the Editor to search only a specific column. If you specify a character string longer than the current zone width, the Editor issues the message ZONE ERROR.

### Responses

When verification is on, the line containing the specified string is displayed. If the string is not found, the messages

```
NOT FOUND
EOF:
```

are displayed, and you may use the REUSE (=) subcommand to request that command be repeated, beginning at the top of the file.

## LONG

Use the LONG subcommand to cancel a previous SHORT subcommand request. The format of the LONG subcommand is:

```
[LONG |]
```

Usage Notes

1. When the LONG subcommand is in effect (it is the default), the Editor responds to invalid subcommands with the message

?EDIT: line ...

Responses

None.

**NEXT**

Use the NEXT subcommand to advance the line pointer a specified number of lines towards the end of the file. The line pointed to becomes the new current line. The format of the NEXT subcommand is:

```

Next | []
 | [n]
 | [1]
 | []

```

where:

n indicates the number of lines to move the line pointer. If n is omitted, then the pointer is moved down only one line.

Usage Notes

1. NEXT is equivalent to DOWN and FORWARD.

Responses

When verification is on, the new current line is displayed. If the end of the file is reached, the message

EOF:

is displayed.

## OVERLAY

Use the OVERLAY subcommand to selectively replace one or more character strings in the current line with the corresponding nonblank characters in the line being keyed in. The format of the OVERLAY subcommand is:

```
| Overlay | [line]
```

### where:

line specifies an input line that replaces corresponding character positions in the current line. On a typewriter terminal, if you enter the OVERLAY subcommand with no data line, the input record remains unchanged.

### Usage Notes

1. Blank characters in the input line indicate that the corresponding characters in the current line are not to be overlaid. For example

```
CHARMIE
 o L
CHARLIE
```

Blanks in columns 3, 4, 5, and 6 of the OVERLAY line indicate that columns 1, 2, 3 and 4 of the current line are not to be changed. (At least one blank must follow the OVERLAY subcommand, which can be truncated as 0).

2. This subcommand may be entered at a typewriter terminal by typing the letter "o", followed by a backspace, followed by the overlaying characters. This sets up the correct alignment on the terminal.
3. An underscore in the overlaying line must be used to place a blank into the corresponding position of the current line. Thus, an underscore cannot be placed (or replaced) in a line

OVERLAY should be used with care on lines containing underscored words or other compound characters.

4. To perform a global overlay operation, issue the REPEAT subcommand just prior to issuing the OVERLAY subcommand. For example, when you enter

```
repeat *
overlay *
```

an asterisk is placed in the left-most column of each record in the file, beginning with the current line. The left-most column, for files with the IMAGE setting ON, is determined by the first logical tab setting.

### Responses

When verification is on, the line is displayed at the terminal after it has been overlaid.

Display Mode Considerations

In addition to using the OVERLAY subcommand in the normal way, you may also issue the OVERLAY subcommand with no operands. The next line you enter is treated as overlay data. To cancel the overlay request, press the Erase Input key and then the Enter key.

**PRESERVE**

Use the PRESERVE subcommand to save the settings of various EDIT subcommands until a subsequent RESTORE subcommand is issued. The format of the PRESERVE subcommand is:

```

PREserve

```

Usage Notes

1. Settings are saved for the following subcommands:

|          |        |        |
|----------|--------|--------|
| CASE     | LONG   | TABSET |
| FMODE    | RECFM  | TRUNC  |
| FNAME    | SERIAL | VERIFY |
| IMAGE    | SHORT  | ZONE   |
| LINEMODE |        |        |

Responses

None.

**PROMPT**

Use the PROMPT subcommand to change the prompting increment for input line numbers when you are using line-number editing. The format of the PROMPT subcommand is:

```

| PROMPT | [n] |
|-----| [10] |
|-----|

```

where:

n specifies the prompting increment; the default value is 10. The value of n should not exceed 32,767.

Responses

When you issue the PROMPT subcommand with no operands, the current setting is displayed.

## QUIT

Use the QUIT subcommand to terminate the current editing session and leave the previous copy of the file, if any, intact on the disk. The format of the QUIT subcommand is:

```
QUIT
```

### Usage Notes

1. You can use the QUIT subcommand when you have made a global change that introduced errors into your file; or whenever you discover that you have made errors in editing a file and want to cancel your editing session.

If a SAVE subcommand or automatic save request has been issued, the file remains as it was when last written.

2. The QUIT subcommand is a convenient way to terminate an edit session when you enter an incorrect filename on the EDIT command line, or when you edit a file merely to examine, but not to change, its contents.

### Responses

The CMS Ready message indicates that control has been returned to CMS.

## RECFM

Use the RECFM subcommand to indicate to the editor whether the record format of the file is fixed-length or variable-length, or to display the current RECFM setting. The format of the RECFM subcommand is:

```
RECFM [F|V]
```

### where:

- F indicates fixed-length records.
- V indicates variable-length records.

### Usage Notes

1. V is assumed by default for all new LISTING, FREEFOT, VSBDATA, and SCRIPT files. V is also recommended for EXEC files. Usually, a variable-format file occupies a smaller amount of disk space because trailing blanks are deleted from each line before it is written onto disk.
2. When you use the RECFM subcommand to change the format of a file from fixed-length to variable-length records, trailing blanks are



removed when the file is written to disk; when you are changing variable-length records to fixed-length, all records are padded to the record length.

Responses

When you use the RECFM subcommand without specifying F or V, the current setting is displayed.

Display Mode Considerations

When you specify a new record format with the RECFM subcommand, the editor writes the new record format in the format field at the top of the screen.

**RENUM**

Use the RENUM subcommand to recompute the line numbers for VSBASIC and FREEFOT source files. The format of the RENUM subcommand is:

```

RENUM | [strtno [incrn]]
 | [10 [strtn]]
 | []

```

where:

strtno indicates the number from which you wish to start renumbering your file. Because RENUM renumbers the whole file from beginning to end, the number you specify as strtno becomes the statement number of the first statement in the newly renumbered file. This number may not exceed 99999 for VSBASIC files or 99999999 for FREEFOT files. The default start number value is 10 and the specified start number must not be zero.

incrn indicates the increment number value by which you wish to renumber your file. This value may not exceed 99999 for VSBASIC files or 99999999 for FREEFOT files. The default for incrn is strtno, the first sequence number in the renumbered file, and the specified incrn must not be zero.

Usage Notes

1. If you do not specify strtno and incrn, the default value for both is 10. If you specify only strtno, incrn defaults to the same value as strtno.
2. All VSBASIC statements that use statement numbers for operands are updated to reflect the new line numbers. The VSBASIC statements with line number operands are:

|        |             |             |
|--------|-------------|-------------|
| DELETE | IF          | READFILE    |
| EXIT   | INPUT       | REREADFILE  |
| GET    | PRINT USING | REWRITEFILE |
| GOSUB  | PUT         | WRITEFILE   |
| GOTO   |             |             |

## EDIT Subcommands-RENUM, REPEAT

3. The current line pointer remains as it was before you entered the RENUM subcommand regardless of whether or not RENUM completes successfully. If you are editing a VSBASIC file, the file to be renumbered must either originate from a read/write disk or you must issue an FMODE subcommand to change the file destination to a read/write disk.
4. If any error occurs during the RENUM operation, the editor terminates the RENUM operation and the file being edited remains unchanged.

### Responses

When verification is on, the message EDIT: indicates that the RENUM subcommand completed processing.

## REPEAT

Use the REPEAT subcommand to execute the immediately following OVERLAY subcommand (or an X or Y subcommand assigned to invoke OVERLAY) for the specified number of lines, or to the end of the file. The format of the REPEAT subcommand is:

```
REPEAT | [n]
 | [*]
 | [1]
 | []
```

### where:

n indicates the number of times to repeat the OVERLAY request that immediately follows, beginning with the current line. An asterisk (\*) indicates that the request is to be repeated until the end of the file is reached. If neither n nor \* is specified, then only one line is handled. The last line processed becomes the new current line.

### Usage Notes

1. If the next subcommand issued after the REPEAT subcommand is not an OVERLAY subcommand, the REPEAT subcommand is ignored.
2. For an example of a REPEAT subcommand followed by an OVERLAY subcommand, see the discussion of the OVERLAY subcommand.

### Responses

None.

## REPLACE

Use the REPLACE subcommand to replace the current line with a specified line or to delete the current line and enter input mode. The format of the REPLACE subcommand is:

```
[Replace | [line]
```

### where:

line specifies an input line that is to replace the current line. If a line is specified, then the editor puts it into the file in place of the current line. If no line is specified, the editor deletes the current line and enters input mode.

### Usage Notes

1. If the LINEMODE option is set to LEFT or RIGHT, then issuing the REPLACE subcommand specifying a line is not valid. If the REPLACE subcommand is used without any operands when LINEMODE is set to LEFT or RIGHT, you are prompted for the next available line number; the first data line you enter replaces the current line number.
2. If you use the REPLACE subcommand with no operands to enter input mode, and the next line you enter is a null line, then the current line is not deleted, and you are returned to edit mode.

### Responses

When verification is on, and you issue the REPLACE subcommand with no data line, the message

INPUT:

indicates that your virtual machine is in input mode.

## RESTORE

Use the RESTORE subcommand to restore the settings of EDIT subcommands to their values when the PRESERVE subcommand was last issued, or to their default values if a PRESERVE subcommand has not been issued. The format of the RESTORE subcommand is:

```
[REStore |
```

### Usage Notes

1. The settings are restored for the following subcommands:

|          |        |        |
|----------|--------|--------|
| CASE     | LONG   | TABSET |
| FMODE    | RECFM  | TRUNC  |
| FNAME    | SERIAL | VERIFY |
| IMAGE    | SHORT  | ZONE   |
| LINEMODE |        |        |

EDIT Subcommands—RESTORE, RETURN, REUSE (=)

### Responses

None.

## RETURN

Use the RETURN command to return to edit mode from the CMS subset environment. RETURN is not an EDIT subcommand, but is listed here as a companion to the CMS subcommand. The format of the RETURN command is:

```
| RETURN |
```

### Responses

When verification is on, the editor responds

EDIT:

to indicate that your virtual machine is in edit mode.

## REUSE (-)

Use the REUSE subcommand (which can also be specified as =) to stack last in, first out (LIFO) the last EDIT request, except for REUSE or a question mark, and then execute the stacked subcommands. The format of the REUSE (or =) subcommand is:

```
| { REUSE } | [subcommand]
| { = } |
```

### where:

subcommand specifies any valid EDIT subcommand.

### Usage Notes

1. If the subcommand you enter on the REUSE subcommand line is an invalid subcommand, the editor clears the stack.
2. You can use the REUSE subcommand to repeat a subcommand request that was not satisfied the first time, for example, a LOCATE subcommand that resulted in an end-of-file condition. If you enter

=

the LOCATE subcommand is stacked, then read by the editor and executed again. This time the search begins from the top of the file.

3. You can also enter more than one = on a single line, to stack the last issued subcommand more than once. For example:

```

locate /xyz/
XYZ IS MY FAVORITE
= = = =
I FIRST MET XYZ
XYZ'S NAME IS DERIVED
LAST SAW XYZ
EOF:

```

the LOCATE subcommand is stacked four times, and then the editor, reading from the stack, executes the four stacked subcommands.

4. You can do the following, if you issue a CHANGE subcommand before positioning your current line pointer:

```

c/xx/yy
NOT FOUND
= l/x/
LINE XXXX
LINE YYYY

```

in this example, the CHANGE request was issued and string1 was not found. The REUSE subcommand stacks the CHANGE subcommand and stacks a LOCATE subcommand in front of it then, the LOCATE subcommand is read and executed, followed by the CHANGE subcommand.

5. You can stack an INPUT or REPLACE subcommand in front of a data line you mistakenly entered in edit mode, for example:

```

roses are red, violets are blue
?EDIT: ROSES ARE RED, VIOLETS ARE BLUE
= input
INPUT:
without cms
i would be, too.

```

the = subcommands stacks the INPUT subcommand in front of the data line. Reading from the stack, the editor executes the INPUT subcommand, then reads in, as the first line of data, the line beginning with ROSES. The file contains

```

ROSES ARE RED, VIOLETS ARE BLUE
WITHOUT CMS
I WOULD BE, TOO.

```

### Responses

Responses are those that are issued to the stacked subcommands.

## SAVE

Use the SAVE subcommand to write on disk the file that is currently being edited, without returning control to CMS, and optionally to change the file identifier. The format of the SAVE subcommand is:

```
SAVE | [fn [ft [fm]]]
```

### where:

fn indicates the filename of the file to be saved. If you specify only fn, then the filetype and filemode are the same.

ft indicates the filetype of the file to be saved.

fm indicates the filemode of the file to be saved.

### Usage Notes

1. If you specify a new file identifier, any existing file with same file identifier is replaced; no warning message is issued. The file being edited, if previously written to disk, is not altered.
2. To write a file on disk and terminate the editing session, use the FILE subcommand.
3. If you want to save the contents of a file at regular intervals, use the AUTOSAVE subcommand.

### Responses

When verification is on, the editor displays

```
EDIT:
```

to indicate the SAVE request completed successfully and you may continue to enter EDIT subcommands.

## SCROLL/SCROLLUP (3270 only)

Use the SCROLL and SCROLLUP subcommands to scan the contents of a file on a display screen.

SCROLL causes the editor to scan forward through the file; SCROLLUP causes the editor to scan backward through the file. The format of the SCROLL and SCROLLUP subcommands is:

```
{ Scroll } | [n]
{ S[croll]U[p] } | [*]
 | []]
```

where:

n is a number from 1 to 255 that specifies the number of successive screens of data to be displayed. If an asterisk (\*) is specified, the entire file, from the current line to the end or beginning of the file, is displayed. If n is not specified, 1 is the default.

Usage Notes

1. The SCROLLUP subcommand can be specified by any combination of the truncation of SCROLL and UP; the minimum truncation is SU.
2. The number of lines shifted forward or backward depends on the current verification setting. If the verification setting is 80 characters or less, then a scroll request displays a file in increments of 20 lines. If the verification setting is more than 80 characters, then a scroll request displays a file in increments of 10 lines.

A single SCROLL subcommand, therefore, is the equivalent of DOWN 20 or DOWN 10, depending on the record length, and SCROLLUP is the equivalent of UP 20 or UP 10.

3. When you use the SCROLL or SCROLLUP subcommands to display more than one screenful, each display is held for one minute, and the screen status area indicates MORE... . To hold the screen display longer, press the Enter key.

To halt scrolling before all the requested screenfuls are displayed, enter the HT immediate command and press the Cancel key twice.

4. When you begin scrolling from the top of the file, the first screenful contains only the first seven lines. When you scroll to the end of the file, the last screen may duplicate lines displayed in the previous screen.

Responses

The screen display is shifted forward or backward.

**SERIAL**

Use the SERIAL subcommand to control the serialization of records in columns 73 through 80. The format of the SERIAL subcommand is:

```

SERIAL | (OFF
 | { ON [incr]
 | { ALL [10]
 | { seq []

```

where:

OFF indicates that neither serialization numbers nor identifiers are to be placed in columns 73-80.

## EDIT Subcommands--SERIAL

- ON** indicates that the first 3 characters of the filename are to be used in columns 73-75 as an identifier.
- ALL** indicates that columns 73-80 are to be used for serialization numbers.
- seq** specifies a 3-character identification to be used in columns 73-75.
- incr** specifies the increment for the line number in columns 76-80 (or 73-80). This number also becomes the first line number. If **incr** is not specified, then 10 is assumed.

### Usage Notes

1. The SERIAL subcommand is valid only for files with fixed-length, 80 character records. To renumber VSBASIC or FREEFORTH files, use the RENUM subcommand.
2. The serialization setting is ON, by default, for the following filetypes:

|          |          |
|----------|----------|
| ASSEMBLE | PLI      |
| COBOL    | PLIOPT   |
| DIRECT   | UPDATE   |
| FORTRAN  | UPDTxxxx |
| MACRO    |          |

3. When serialization is in effect, records in a file are resequenced each time a FILE, SAVE, or automatic save request is issued. If you are using line-number editing, you must issue the subcommand

linemode off

before issuing a FILE or SAVE subcommand if you wish the records to be resequenced.

### Responses

If you issue the SERIAL subcommand in a file with a zone column greater than 72, the message

END ZONE SET TO 72

is displayed, to indicate that the zone has been changed. If the zone column is 72 or less, but the truncation column is greater than 72, the message

TRUNC SET TO 72

is displayed.



## SHORT

Use the SHORT subcommand to request the editor to respond to invalid subcommand lines with the short form of the ?EDIT message. The format of the SHORT subcommand is:

```

SHORT

```

### Usage Notes

1. When the SHORT subcommand is in effect, the editor responds
  - 
  - to an invalid subcommand line, and
  - \$
  - to an invalid macro request.
2. To resume displaying the long form of the ?EDIT message, use the LONG subcommand.

### Responses

None.

## STACK

Use the STACK subcommand to stack data lines or EDIT subcommands in the console stack for subsequent reading. The format of the STACK subcommand is:

```

	r	
		n
STACK		subcommand
		0
		1

```

### where:

- n indicates the number of lines to be stacked beginning with the current line. If a number or a subcommand is not specified, then one line is assumed by default. A maximum of 25 lines can be stacked.
- subcommand specifies an EDIT subcommand to be stacked.
- 0 stacks a null line.

## EDIT Subcommands-STACK, TABSET

### Usage Notes

1. STACK subcommands are used in writing edit macros, to stack lines from a file so that they can be moved around, or to stack additional subcommands.
2. All lines stacked with the STACK subcommand are stacked FIFO (first in, first out).
3. The length of stacked lines is determined by the current TRUNC setting.

### Responses

None. If you issue the STACK subcommand to stack an EDIT subcommand line, the stacked subcommand is executed immediately; responses are those to the stacked subcommands, if any.

## TABSET

Use the TABSET subcommand to set logical tab stops for a file. The format of the TABSET subcommand is:

```
| | TABSet | n1 [n2 ... nn] |
```

### where:

- | n1 [n2... nn] indicates column positions for logical tab settings. You may specify up to 25 numbers, separated from each other by at least one blank. n1 indicates the first column in the file that may contain data.

### Usage Notes

1. The editor assigns the following tab settings by default:

| <u>Filetypes</u>                                 | <u>Default Tab Settings</u>                                                     |
|--------------------------------------------------|---------------------------------------------------------------------------------|
| ASM3705, ASSEMBLE,<br>MACRO, UPDATE,<br>UPDTxxxx | 1, 10, 16, 31, 36, 41, 46, 69, 72, 80                                           |
| AMSERV                                           | 2, 6, 11, 16, 21, 26, 31, 36, 41, 46, 51,<br>61, 71, 80                         |
| FORTRAN                                          | 1, 7, 10, 15, 20, 25, 30, 80                                                    |
| FREEFORT                                         | 9, 15, 18, 23, 28, 33, 38, 81                                                   |
| BASIC, VSBASIC                                   | 7, 10, 15, 20, 25, 30, 80                                                       |
| PLIOPT, PLI                                      | 2, 4, 7, 10, 13, 16, 19, 22, 25, 31, 37,<br>43, 49, 55, 79, 80                  |
| COBOL                                            | 1, 8, 12, 20, 28, 36, 44, 68, 72, 80                                            |
| Others                                           | 1, 6, 11, 16, 21, 26, 31, 36, 41, 46, 51,<br>61, 71, 81, 91, 101, 111, 121, 131 |

2. Tab settings have no effect if the IMAGE setting is either OFF or CANON. (CANON is the default for SCRIPT filetypes). A tab entered into a file under these conditions appears as X'05'.
3. The margins set by the TABSET subcommand are used by the INPUT, REPLACE, OVERLAY, and FIND subcommands.

Responses

None.

**TOP**

Use the TOP subcommand to move the line pointer to the top of the file. The null top line becomes the current line. The format of the TOP subcommand is:

```
TOP
```

Responses

When verification is on, the message

TOP:

is displayed.

Display Mode Considerations

When you are using a display terminal, if you specify TOP and verification is on, line 9 contains the characters TOP (indicating the top of the file), lines 2 through 8 are blank, and lines 10 through 21 contain the first 12 lines of the file.

**TRUNC**

Use the TRUNC subcommand to change the truncation column of records or to display the current truncation column setting. The format of the TRUNC subcommand is:

```
TRUNC [n]
 [*]
```

where:

n indicates the column at which truncation is to occur. If n is specified as an asterisk (\*), the truncation column is set to the record length for the filetype.

## EDIT Subcommands—TRUNC, TYPE

### Usage Notes

1. The editor assigns the following truncation setting by default:

| <u>Filetypes</u>                               | <u>Truncation Column</u> |
|------------------------------------------------|--------------------------|
| ASSEMBLE, MACRO, UPDATE, UPDTxxxx              | 71                       |
| AMSERV, COBOL, DIRECT, FORTRAN,<br>PLI, PLIOPT | 72                       |
| All Others                                     | Record Length            |

2. The truncation value is used by the INPUT, REPLACE, STACK, and OVERLAY subcommands, and also, for display terminals in display mode, the CHANGE subcommand when it is used with no operands.
3. If your virtual machine is in input mode and you enter a line that is longer than the current truncation setting, the message

TRUNCATED

is displayed along with a display of the truncated line. Your virtual machine is still in input mode.

### Responses

When you enter the TRUNC subcommand with no operands, the editor displays the current setting.

## TYPE

Use the TYPE subcommand to display all or any part of a file at the terminal. The format of the TYPE subcommand is:

```

Type		r	r	r
		m	n	
		*	*	
		1		
		L	L	J

```

where:

- m indicates the number of lines to be displayed, beginning with the current line. An asterisk (\*) indicates all lines between the current line and the end of the file. If m is omitted, only one line is displayed. If the number of lines specified exceeds the number remaining in the file, displaying stops at the end of the file.
- n indicates the column at which displaying is to stop, overriding the current end column for verification. If n is specified as \*, it indicates that displaying is to take place for the full record length.

### Usage Notes

1. Use the TYPE subcommand to display lines when you are editing a file with verification off.

2. If you display one line, the current line pointer does not move; if you display more than one line, the current line is positioned at the last line displayed, or at the end of the file if you specified \*.
3. If you have set an end verification column to a value less than the record length, and you want to display an entire record, enter  

```
type 1 *
```
4. If you do not specify an end column, the length of the line(s) displayed is determined by the current end verification setting. If you are using right-handed line-number editing, on a typewriter terminal or a display terminal in line mode, the line numbers are displayed on the left.

Responses

The requested lines are displayed.

Display Mode Considerations

Since the TYPE subcommand was designed for printing terminals, it is of marginal value on a display terminal, except when you use line mode. However, if the display screen is interrupted by communication from the control program (CP), you should use the TYPE subcommand to restore the full screen display.

**UP**

Use the UP subcommand to reposition the line pointer towards the beginning of the file. The format of the UP subcommand is:

```
Up | r |
 | |n |
 | |1 |
 | | |
```

where:

n indicates the number of lines the pointer is to be moved towards the beginning of the file. If a number is not specified, then the pointer is moved up only one line. The line pointed to becomes the new current line.

Usage Notes

1. UP is equivalent to BACKWARD.

Responses

When verification is on, the line pointed to is displayed at your terminal. If the UP subcommand causes the current line pointer to move beyond the beginning of the file, the following message is displayed:

TOF:



**X or Y**

Use the X or Y subcommands to assign a given EDIT subcommand to be executed whenever X or Y is entered, or to execute the previously assigned subcommand a specified number of times. The format of the X and Y subcommands are:

```

{ X } | [subcommand]
{ Y } | |n
 | |1

```

where:

subcommand indicates any EDIT subcommand line. The editor assumes that you have specified a valid EDIT subcommand, and no error checking is done.

n indicates the number of times the previously assigned subcommand is to be executed. If X or Y is entered with no operands, 1 is assumed.

Usage Notes

1. Advancement of the current line pointer depends upon the EDIT subcommand that has been assigned to X or Y. If a number or a subcommand is not specified, the previously assigned subcommand is executed once.
2. X and Y are initially set to null strings. If you enter X or Y without having previously assigned a subcommand to it, the editor issues the ?EDIT error message.
3. You can use the X and Y subcommands in many instances where you must repeat a subcommand line many times while editing a file, but the situation does not lend itself to a global request. For example, if you assign X to a LOCATE and Y to a CHANGE subcommand, issue

x

to execute the LOCATE request, and after examining the line, you can change it and continue searching, by entering the Y subcommand followed by the X subcommand,

y#x

or just continue searching:

x

Responses

Responses are issued for the EDIT subcommands that are assigned to X and Y, in accordance with the current verification setting.

## ZONE

Use the ZONE subcommand to specify the columns of each record (starting position and ending position) to be scanned when the editor searches for a character string or to display the current ZONE settings. The format of the ZONE subcommand is:

```

Zone | [firstcol [lastcol]]
 | [* [*
 | 1 |
 | []

```

where:

firstcol indicates the near zone column of each record to be scanned. If firstcol is specified as \*, column 1 is assumed by default.

lastcol indicates the end zone column of each record to be scanned. If lastcol is specified as \*, the length of the record is assumed by default.

Usage Notes

1. The editor assigns the following settings by default:

| <u>Filetypes</u>                     | <u>Near_Zone</u> | <u>End_Zone</u> |
|--------------------------------------|------------------|-----------------|
| ASSEMBLE, MACRO, UPDATE,<br>UPDTxxxx | Column 1         | Column 71       |
| AMSERV, PLI, PLIOPT                  | Column 2         | Column 72       |
| COBOL, DIRECT, FORTRAN               | Column 1         | Column 72       |
| BASIC, VSBASIC                       | Column 7         | Record Length   |
| FREEFORT                             | Column 9         | Record Length   |
| Others                               | Column 1         | Record Length   |

2. The ZONE settings are used by the ALTER, CHANGE, and LOCATE subcommands to define the columns that will be scanned. If you specify a character string longer than the zone, you receive the message.

ZONE ERROR

and the subcommand is not executed.

3. If you issue a CHANGE subcommand that increases the length of a line beyond the end zone setting, the line is truncated.
4. You can use the ZONE subcommand to protect data in particular columns, for example,



```
edit newfile memo
NEW FILE:
EDIT:
zone
 1 80
zone 10 20
input the zone is now set for columns 10-20

EDIT:
change /o/*/
the zone is n*w set for columns 10-20
```

Note that the LOCATE and CHANGE subcommands operated on the word now, not the word zone, because scanning started in position 10, not in position 1.

Responses

When you enter the ZONE subcommand without specifying zone settings, the editor displays the current setting.

?

Use the ? subcommand to display the last EDIT subcommand executed except for a REUSE or ? (question mark) subcommand. The format of the ? subcommand is:

```
| ? |
```

Usage Notes

1. After an X, Y, or = subcommand, the last EDIT subcommand is the subcommand that was executed as a result of issuing the X or Y subcommand.

Display Mode Considerations

When you issue the ? subcommand using a 3270 in display mode, the last EDIT subcommand that was executed is redisplayed in the user input area. Press the Enter key to execute it again; you may modify the line before reentering it.

## EDIT Subcommands-nnnnn

### nnnnn

Use the nnnnn subcommand to enter and locate lines when you are using line-number editing. The format of the nnnnn subcommand is:

```
| {nnnnn } | [text] |
| {nnnnnnnn } | |
```

#### where:

nnnnn indicates a line number between 0 and 99999 if the filetype is BASIC or VSBASIC, or 0 and 99999999 if the filetype is FREEFORT.

text specifies a line of text to be inserted into the file at the specified line number. If a line with that number already exists, it is replaced. If no text line is specified, the current line pointer is positioned at the line number specified.

#### Usage Notes

1. The nnnnn subcommand is valid only when you are using line-number editing, that is, you have issued the LINEMODE subcommand using the RIGHT or LEFT operand. Line-number editing is the default for VSBASIC and FREEFORT files.

#### Responses

When you issue the nnnnn subcommand with no operands, the line with the specified line number is displayed. If the line is not found, the editor displays the message

LINE NOT FOUND

and the current line pointer remains where it was when the nnnnn subcommand was issued.

## EDIT Macros

Edit macros are CMS EXEC files that execute sequences of EDIT subcommands. The following edit macros are supplied with VM/370 for your convenience. For additional information on creating and invoking your own edit macros and EXEC files, VM/370: CMS User's Guide.

### ***\$DUP***

Use the \$DUP to duplicate the current line. The format of the \$DUP macro is:

```

|-----|
| $DUP | | [n] |
| | | [1] |
| | | [] |
|-----|

```

### where:

n indicates the number of times you want to duplicate the line; the maximum value you can specify is 25. If n is omitted, the current line is duplicated once.

### Usage Notes

1. The last copy of the line duplicated becomes the new current line.
2. If you use the logical line end symbol (#) to stack additional subcommands on the same line with the \$DUP edit macro those subcommands are cleared from the console stack and the message

STACKED LINES CLEARED BY \$DUP

is issued. The stacked subcommand(s) are not executed.

### Responses

The last line duplicated (the new current line) is displayed.

## Edit Macros-\$MOVE

### **\$MOVE**

Use the \$MOVE edit macro to move one or more lines from one place in a file to another place. The format of the \$MOVE macro is:

```
$MOVE | n { UP m
 | { DOWN m
 | { TO label }
```

#### where:

- n indicates the number of records you want to move, beginning with the current line. The maximum number of lines you can move is 25.
- UP m indicates that you want to move the lines toward the top of the file, m lines above the current line.
- DOWN m indicates that you want to move the lines toward the end of the file, m lines below the last line you are going to move.
- TO label indicates that you want the lines inserted following the specified label. The label must be all uppercase characters, and must start in column 1.

#### Usage Notes

1. The last line moved becomes the new current line.
2. If the label is not found or if the DOWN value exceeds the number of lines remaining before end-of-file, the lines are inserted at the end of the file. If the UP value exceeds the number of lines remaining before the top-of-file, the lines are inserted at the top of the file.
3. If you use the logical line end symbol (#) to stack additional subcommands on the same line with the \$MOVE request, those subcommands are cleared from the console stack and the message

STACKED LINES CLEARED BY \$MOVE

is displayed. The stacked subcommands are not executed.

#### Responses

When verification is on, the last line moved is displayed.

## Section 4. DEBUG Subcommands

This section describes the subcommands that are available to you when you use the debug environment to test and debug your programs. The debug environment is entered when:

- The DEBUG command is issued from the CMS environment. (The DEBUG command is described in "Section 2. CMS Commands.")
- An external interrupt occurs. (An external interrupt is caused by the CP EXTERNAL command.)
- A breakpoint (instruction address stop) is encountered during program execution. (Breakpoints are set with the DEBUG subcommand BREAK.)

When the debug environment is entered, the contents of all general registers, the channel status word (CSW), and the channel address word (CAW) are saved so they may be examined and changed before being restored when leaving the debug environment. If debug is entered via an interrupt, the old program status word (PSW) for that interrupt is also saved. If DEBUG is the first command entered after an abnormal terminal (abend) occurs, the contents of all general registers, the CSW, the CAW, and the old PSW are available from the time of the abend.

For hints on debugging your programs using the CMS debug environment, consult the VM/370: CMS User's Guide.

**BREAK**

Use the **BREAK** subcommand to stop execution of a program or module at a specific instruction location, called a breakpoint. The format of the **BREAK** subcommand is:

```

 BReak | id {symbol}
 | {hexloc}

```

where:

- id** is a decimal number, from 0 to 15, which identifies the breakpoint. A maximum of 16 breakpoints may be in effect at one time; if you specify an id number that is already set for a breakpoint, the previous breakpoint is cleared and the new one is set.
- symbol** is a name assigned to the storage location where the breakpoint is set. **symbol**, if used, must have been previously set using the **DEFINE** subcommand.
- hexloc** is the hexadecimal storage location (relative to the current origin) where the breakpoint is to occur. **hexloc** must be on a halfword boundary and its value added to the current origin must not exceed your virtual machine size.

Usage Notes

1. To set breakpoints before beginning program execution, enter the debug environment with the **DEBUG** command after you load the program into storage. After setting the breakpoints use the **RETURN** subcommand to leave the debug environment and issue the **START** command to begin program execution.

```

load myprog
debug
break 1 20016
break 2 20032
return
start

```

2. When you assign **hexloc** to a breakpoint, you must know the current origin (set with the **ORIGIN** subcommand). The **hexloc** you specify is added to the current origin to determine the breakpoint address.
3. When a breakpoint is found during program execution, the message

```
DMSDBG728I DEBUG ENTERED BREAKPOINT yy AT xxxxxx
```

is displayed at the terminal. To resume program execution, use the **GO** subcommand.

4. Breakpoints are cleared after they are encountered; thus if a breakpoint is encountered during a program loop you must reset the breakpoint if you want to interrupt execution the next time that address is encountered.
5. When you set a breakpoint, the halfword at the address specified is replaced with **B2Ex**, where **x** represents the id number you assigned. After the breakpoint is encountered during execution, **B2Ex** is replaced with the original operation code.



## CSW

Use the CSW subcommand to display at the terminal the contents of the CSW (Channel Status Word), as it existed at the time the debug environment was entered. The format of the CSW subcommand is:

```

|-----|
CSW

```

### Usage Notes

1. The CSW indicates the status of the channel or an input/output device, or the conditions under which an I/O operation terminated. The CSW is formed in the channel and stored in storage location X'40' when an I/O interrupt occurs. If I/O interrupts are suppressed, the CSW is stored when the next Start I/O, Test I/O, or Halt I/O instruction is executed.
2. Whenever an I/O operation abnormally terminates, issue the CSW subcommand. The status and residual count information in the CSW is very useful in debugging. Also, use the CSW to calculate the address of the last executed CCW (subtract 8 bytes from the command address to find the address of the last CCW executed).

### Responses

The contents of the CSW are displayed at the terminal in hexadecimal representation. Its format is:

```

|-----|
|KEY|0000| Command Address | Status | Byte Count
|-----|
0 3 4 7 8 31 32 47 48 63

```

#### Bits

#### Contents

- 0-3 The protection key is moved to the CSW from the CAW. It indicates the protection key at the time the I/O operation started. The contents of this field are not affected by programming errors detected by the channel or by the condition causing termination of the operation.
- 4-7 This field is not used and must contain binary zeros.
- 8-31 The command address contains a storage address (in hexadecimal representation) that is 8 bytes greater than the address of the last CCW executed.
- 32-47 The status bits indicate the conditions in the device or channel that caused the CSW to be stored.
- 48-63 The residual count is the difference between the number of bytes specified in the last executed CCW and the number of bytes that were actually transferred. When an input operation is terminated, the difference between the original count in the CCW and the residual count in the CSW is equal to the number of bytes transferred to storage; on an output operation, the difference is equal to the number of bytes transferred to the I/O device.



**DEFINE**

Use the DEFINE subcommand to assign a symbolic name to a specific storage address. Once a symbolic name is assigned to a storage address, that symbolic name can be used to refer to that address in any of the other DEBUG subcommands. The format of the DEFINE subcommand is:

```

DEFINE | symbol hexloc [bytecount]
 | [4]

```

where:

**symbol** is the name to be assigned to the storage address derived from the second operand, hexloc. Symbol may be from 1 to 8 characters long, and must contain at least 1 nonhexadecimal character. Any symbolic name longer than 8 characters is left-justified and truncated on the right after the eighth character.

**hexloc** is the hexadecimal storage location, in relation to the current origin, to which the name specified in the first operand (symbol), is assigned.

**bytecount** is a decimal number, between 1 and 56 inclusive, which specifies the length in bytes of the field whose name is specified by the first operand (symbol) and whose starting location is specified by the second operand (hexloc). When bytecount is not specified, 4 is assumed.

Usage Notes

1. Issuing the DEFINE subcommand creates an entry in the debug symbol table. The entry consists of the symbol name, the storage address, and the length of the field. A maximum of 16 symbols can be defined in the debug symbol table at a given time.
2. When a DEFINE subcommand specifies a symbol that already exists in the debug symbol table, the storage address derived from the current request replaces the previous storage address. Several symbols may be assigned to the same storage address, but each of these symbols constitutes one entry in the debug symbol table. The symbols remain defined until they are redefined or until an IPL subcommand loads a new copy of CMS.
3. When you assign a symbolic name to a storage location, you must know the current origin (set by the ORIGIN subcommand). The hexloc you specify is added to the current origin to create the entry in the symbol table used by DEBUG subcommands. If you change the current origin, existing entries are not changed.
4. You can use the symbolic names to refer to storage locations when you issue the DEBUG subcommands BREAK, DUMP, GO, ORIGIN, STORE, and X.

Responses

None.

## DUMP

Use the DUMP subcommand to print part or all of your virtual storage on the printer. The requested information is printed offline as soon as the printer is available. First, a heading:

ident FROM starting location TO ending location

is printed. Next, the general registers 0-7 and 8-15, and the floating-point registers 0-6 are printed, followed by the PSW, CSW, and CAW. Then the specified portion of virtual storage is printed with the storage address of the first byte in the line printed at the left, followed by the alphameric interpretation of 32 bytes of storage. The format of the DUMP subcommand is:

|      |   |          |   |                 |   |   |
|------|---|----------|---|-----------------|---|---|
| DUMP | [ | symbol1  | [ | symbol2         | ] | ] |
|      |   | hexloc1  |   | hexloc2 [ident] |   |   |
|      |   | <u>0</u> |   | *               |   |   |
|      |   |          |   | <u>32</u>       |   |   |
|      |   |          |   |                 |   |   |

### where:

- symbol1 is the name assigned (via the DEFINE subcommand) to the storage address that begins the dump.
- hexloc1 is the hexadecimal storage location, in relation to current origin, that begins the dump.
- symbol2 is the name assigned (via the DEFINE subcommand) to the storage address that ends the dump.
- hexloc2 is the hexadecimal storage location, in relation to the current origin, that ends the dump.
- \* indicates that the dump ends at your virtual machine's last virtual storage address.
- ident is any name (up to eight characters) that identifies the dump.

### Usage Notes

1. If you issue the DUMP subcommand with no operands, 32 bytes of storage are dumped, starting at the current origin.
2. The first and second operands must designate storage addresses that do not exceed your virtual machine storage size. Also, the storage address derived from the second operand must be greater than the storage address derived from the first operand.

### Responses

None.

## GO

Use the GO subcommand to exit from the debug environment and begin program execution. The format of the GO subcommand is:

```

GO | [symbol]
 | [hexloc]

```

### where:

symbol is the symbolic name assigned to the storage location where you want execution to begin.

hexloc is the hexadecimal location, in relation to the current origin, where you want execution to begin.

### Usage Notes

1. When you issue the GO subcommand, the general registers, CAW (channel address word), and CSW (channel status word) are restored either to their contents upon entering the debug environment, or, if they have been modified, to their modified contents. Then the old PSW is loaded and becomes the current PSW. Execution begins at the instruction address contained in bits 40-63 of the PSW.
2. When you specify symbol or hexloc with the GO subcommand, the specified address replaces the instruction address in the old PSW, so execution will begin at that address. If you entered the debug environment with the DEBUG command, you must specify an address with the GO subcommand.
3. The address you specify must be within your virtual machine and it must contain a valid operation code.

### Responses

Program execution is resumed.

## GPR

Use the GPR subcommand to display the contents of one or more general registers at the terminal. The format of the GPR subcommand is:

```
[GPR | reg1 [reg2]
```

### where:

reg1 is a decimal number (from 0-15 inclusive) indicating the first or only general register whose contents are to be displayed.

reg2 is a decimal number (from 0-15 inclusive) indicating the last general register whose contents are to be displayed. reg2 must be larger than reg1.

### Responses

The register or registers specified are displayed, in hexadecimal representation:

```
xxxxxxx
.
.
.
```

## HX

Use the HX subcommand to leave the debug environment, regardless of the reason the debug environment was entered. The format of the HX subcommand is:

```
[HX |
```

### Responses

If you entered the debug environment following a program interrupt, you receive the message

```
CMS
```

to indicate a return to the CMS environment. If you entered the debug environment by issuing the DEBUG command, you receive the message

```
DMSABN148T SYSTEM ABEND 2E4 CALLED FROM xxxxxx
```

where xxxxxx is the address of the debug routine.

## ORIGIN

Use the ORIGIN subcommand to set an origin or base address to be used in the debug environment. The format of the ORIGIN subcommand is:

```
ORigin | { symbol }
 | { hexloc }
 | { 0 }
```

### where:

**symbol** is a symbolic name that was previously assigned (via the DEFINE subcommand) to a storage address.

**hexloc** is a hexadecimal location within the limits of your virtual storage. If you do not explicitly set an origin, then it has a value of 0.

### Usage Notes

1. When the ORIGIN subcommand specifies a symbol, the debug symbol table is searched. If a match is found, the value corresponding to the symbol becomes the new origin. When a hexadecimal location is specified, that value becomes the origin. In either case, the operand cannot specify an address greater than your virtual storage size.
2. Any origin set by an ORIGIN subcommand remains in effect until another ORIGIN subcommand is issued, or until you obtain a new copy of CMS. Whenever a new ORIGIN subcommand is issued, the value specified in that subcommand overlays the previous origin setting. If you obtain a new copy of CMS (via IPL), the origin is set to 0 until a new ORIGIN subcommand is issued.
3. You can use the ORIGIN subcommand to set the origin to your program's base address, and then refer to actual instruction addresses in your program, rather than to virtual storage locations.

### Responses

None.

## DEBUG Subcommands-PSW, RETURN

### PSW

Use the PSW subcommand to display the contents of the PSW (program status word). The format of the PSW subcommand is:

```
| PSW |
```

#### Usage Notes

1. If the debug environment was entered because of a program interrupt, the program old PSW is displayed. If the debug environment was entered because of an external interrupt, the external old PSW is displayed. If the debug environment was entered for any other reason, the following is displayed in response to the PSW subcommand:

```
01000000xxxxxxx
```

where the 1 in the first byte means that external interrupts are allowed and xxxxxxx is the hexadecimal storage address of the debug program.

2. The PSW contains some information not contained in storage or registers but required for proper program execution. In general, the PSW is used to control instruction sequencing and to hold and indicate the status of the system in relation to the program currently executing. Refer to "Appendix A: System/370 Information" in the VM/370: System Programmer's Guide for a description of the PSW.

#### Responses

The PSW is displayed in hexadecimal representation as follows:

```
XXXXXXXXXXXXXXXX
```

### RETURN

Use the RETURN subcommand to exit from the debug environment and enter the CMS command environment. The format of the RETURN subcommand is:

```
| RETurn |
```

#### Usage Notes

1. The RETURN subcommand is valid only when the debug environment was entered via the DEBUG command.

#### Responses

The CMS Ready message indicates that control has been returned to the CMS environment.

**SET**

Use the SET subcommand to change the contents of the control words and general registers. The format of the SET subcommand is:

|     |  |   |     |         |           |           |  |  |  |   |
|-----|--|---|-----|---------|-----------|-----------|--|--|--|---|
| SET |  | { | CAW | hexinfo |           |           |  |  |  | } |
|     |  |   | CSW | hexinfo | [hexinfo] |           |  |  |  |   |
|     |  |   | PSW | hexinfo | [hexinfo] |           |  |  |  |   |
|     |  |   | GPR | reg     | hexinfo   | [hexinfo] |  |  |  |   |

where:

## CAW hexinfo

stores the specified information (hexinfo) in the CAW (channel address word) that existed at the time the debug environment was entered.

## CSW hexinfo [hexinfo]

stores the specified information (hexinfo [hexinfo]) in the CSW (channel status word) that existed at the time the debug environment was entered.

## PSW hexinfo [hexinfo]

stores the specified information (hexinfo [hexinfo]) in the old PSW (program status word) for the interrupt that caused the debug environment to be entered.

## GPR reg hexinfo [hexinfo]

stores the specified information (hexinfo [hexinfo]) in the specified general register (reg).

Usage Notes

1. The SET subcommand can only change the contents of one control word at a time. For example, you must issue the SET subcommand three times:

```
set caw hexinfo
set csw hexinfo [hexinfo]
set psw hexinfo [hexinfo]
```

to change the contents of the three control words.

2. The SET subcommand can change the contents of one or two general registers each time it is issued. When four or fewer bytes of information are specified, only the contents of the specified register are changed. When more than four bytes of information are specified, the contents of the specified register and the next sequential register are changed. For example, the SET subcommand:

```
set gpr 2 xxxxxxxx
```

changes only the contents of general register 2. But, the SET subcommand:

```
set gpr 2 xxxxxxxx xxxxxxxx
```

changes the contents of general registers 2 and 3.

3. Each hexinfo operand should be from 1- to 4 bytes long. If an

operand is less than 4 bytes and contains an uneven number of hexadecimal digits (representing half-byte information), the information is right-justified and the left half of the uneven byte is set to zero. If more than 8 hexadecimal digits are specified in a single operand, the information is left-justified and truncated on the right after the eighth digit.

4. The number of bytes that can be stored using the SET subcommand varies depending on the form of the subcommand. With the CAW form, up to 4 bytes of information may be stored. With the CSW, GPR, and PSW forms, up to 8 bytes of information may be stored, but these bytes must be represented in two operands of 4 bytes each. When two operands of information are specified, the information is stored in consecutive locations (or registers), even if one or both operands contain less than 4 bytes of information.

### Responses

None. To display the contents of control words or registers after you modify them, you must use the CAW, CSW, PSW, and GRP subcommands.

## STORE

Use the STORE subcommand to store up to 12 bytes of hexadecimal information in any valid virtual storage location. The format of the STORE subcommand is:

```

| STORE | {symbol} hexinfo [hexinfo [hexinfo]] |
	{hexloc}

```

### where:

- symbol** is the symbolic name assigned (via the DEFINE subcommand) to the storage address where the first byte of specified information is to be stored.
- hexloc** is the hexadecimal location, relative to the current origin, where the first byte of information is to be stored.
- hexinfo** is the hexadecimal information, four bytes or less in length (that is, 2 to 8 hexadecimal digits), to be stored.

### Usage Notes

1. If an operand is less than 4 bytes long and contains an uneven number of hexadecimal digits (representing half-byte information), the information is right-justified and the left half of the uneven byte is set to zero. If more than 8 hexadecimal digits are specified in a single operand, the information is left-justified and truncated on the right after the eighth digit.
2. The STORE subcommand can store a maximum of 12 bytes at one time. By specifying all three information operands, each containing four bytes of information, the maximum 12 bytes can be stored. If less than four bytes are specified in any or all of the operands, the information given is arranged into a string of consecutive bytes, and that string is stored starting at the location derived from the first operand.



For example, if you have defined a 4-byte symbol named FENCE that currently contains X'FFFFFFFF' and you enter

```
store fence 0
```

FENCE contains X'00FFFFFF'.

### Responses

None. To display the contents of a storage location after you have modified it, you must use the X subcommand.

## X

Use the X subcommand to examine and display the contents of specific locations in virtual storage. The format of the X (examine) subcommand is:

```

X | (symbol [n]
 | | [length])
 | |
 | | (hexloc [n]
 | | | [4])

```

### where:

symbol n is the name assigned (via the DEFINE subcommand) to the storage address of the first byte to be displayed. n is a decimal number from 1 to 56 inclusive, that specifies the number of bytes to be examined. If a symbol is specified without a second operand, the length attribute associated with that symbol in the debug symbol table specifies the number of bytes to be examined.

hexloc n is the hexadecimal location, in relation to the current origin, of the first byte to be examined. If hexloc is specified without a second operand, 4 bytes are displayed.

### Usage Notes

1. The address represented by symbol or hexloc must be within your virtual machine storage size.

### Responses

The requested information is displayed at the terminal in hexadecimal format.



## Section 5. EXEC Control Statements

This section describes the formats, usage rules, and default values for EXEC control words, including

- Control Statements
- Built-in Functions
- Special Variables

An EXEC procedure is a CMS file that contains a sequence of CMS commands and/or EXEC control statements. Control statements determine the logic flow for EXEC, provide terminal communications, and may be used to manipulate CMS disk files. For an introduction to the EXEC facilities, and for complete tutorial information, including examples, consult the VM/370: CMS User's Guide.

EXEC procedures may be invoked with the EXEC command, described in "Section 2. CMS Commands." You may also execute an EXEC procedure by specifying its filename, as long as the implied EXEC function is in effect.

## The Assignment Statement

Use the assignment statement in an EXEC procedure to assign a value to a variable symbol. Variable symbols may be tested and manipulated to control the execution of an EXEC procedure. The format of the assignment statement is:

```

|-----|
| &variable = { string }
| { ae }
| { function }
{ X'xxxxxx }

```

### where:

**&variable** indicates the variable symbol which is assigned the specified value. A variable may contain a maximum of eight alphameric characters, including the initial ampersand, which is required.

**string** is a 1- to 8-character data item. It may also be a variable symbol. Whether a numeric string is treated as numeric or character data depends on how it is used in the EXEC. If a string containing variable symbols expands to more than 8 characters, it is truncated.

**ae** is an arithmetic expression, consisting of a sequence of data items that possess positive or negative integral values and are separated by plus or minus signs:

```
&I - 4 + &CALC - 6
```

**function** is an EXEC built-in function followed by at least one token.

**X'xxxxxx** indicates up to 6 hexadecimal digits to be converted to decimal before assignment. For example:

```
&A = X'C0
```

results in &A having the decimal value 192.

Hexadecimal conversion is not performed unless you have used the &HEX ON control statement.

### Variable Substitution

All variable symbols occurring in executable statements are substituted before the statement is executed. An executable statement is (1) a CMS command line, or (2) an EXEC control statement (including assignment statements).

Variable substitution is not performed on symbols on the left-hand side of an assignment statement. If that variable has already been assigned a value, it is replaced by the new value specified in the assignment statement.

If the special form, X'&symbol is used, the specified symbol is converted to its hexadecimal equivalent. For example,

```

| &A = 192
| &TYPE X'&A

```

| results in the display

| C0

If a variable symbol that has not been defined is used in an executable statement, the symbol is set to a null token, and ignored. In some instances this may cause an EXEC processing error.

### Tokens

All executable statements in an EXEC are scanned into 8-character tokens, and padded or truncated as necessary. Tokens are formed of words delimited by blanks and parentheses, for example, the line

```
&TYPE THIS IS AN EXAGGERATED (MESSAGE
```

scans as

```
&TYPE THIS IS AN EXAGGERA (MESSAGE
```

Variable symbols are substituted after each line is scanned, and each token is scanned repeatedly until all symbols in it are substituted.

### **&ARGS**

Use the &ARGS control statement to redefine the value of one or more of the special variables, &1 through &30. The format of the &ARGS control statement is:

```
| &ARGS | [arg1 [arg2 ... [arg30]]] |
```

where:

[arg1 [arg2 ... [arg30]]]  
specify up to 30 tokens to be assigned to the special variables &1 through &30. If no arguments are specified, all of the variables &1 through &30 are set to blanks. When fewer than 30 arguments are entered, the remaining arguments are set to blanks.

### Usage Notes

1. To enter an argument list from the terminal, use the &READ ARGS control statement.
2. An &ARGS control statement resets the values of the &INDEX, &\* and &\$ special variables.

### | **&BEGEMSG**

| Use the &BEGEMSG control statement to introduce one or more unscanned | lines to be edited as VM/370 error messages. The list of lines to be | displayed must be terminated by an &END control statement, which must

## EXEC Control Statements-&BEGEMSG

appear beginning in column 1. The format of the &BEGEMSG control statement is:

```
| -----|
| | &BEGEMSG | [ALL] |
| | -----|
```

| where:

| ALL specifies, for fixed-length EXEC files, that the entire line (to a maximum of 130 characters) is to be displayed.

### | Usage Notes

| 1. To qualify for error message editing, the first data item on each line following the &BEGEMSG control statement must be 7 characters long, in the format:

| mmmnnns

| where:

| mmmnnn is a 6-character message identification you can supply for the error message. Standard VM/370 error messages use a 3-character module code (mmm) and a 3-character message number (nnn).

| s indicates the severity code. The following codes qualify the message for error message editing:

| <u>Code</u> | <u>Message Type</u> |
|-------------|---------------------|
| I           | Information         |
| E           | Error               |
| W           | Warning             |

| When the severity code is E, I or W, the message is displayed in accordance with the CP EMSG setting (ON, OFF, CODE, or TEXT). You can change this setting with the CP SET command, described in VM/370: CP Command Reference for General Users.

| 2. When you use the &BEGEMSG control statement to display error messages, the character string 'DMS' is inserted in front of the 7-character message identification. For example, if the EMSG setting is ON, the lines

```
| &BEGEMSG
| TEST01E INSURMOUNTABLE ERROR
| &END
```

| result in the display

```
| DMSTEST01E INSURMOUNTABLE ERROR
```

| Note: Since the maximum length of a line that you can display at your terminal is 132 characters, the insertion of the characters DMS will cause lines greater than 129 characters long to be truncated.

| 4. Messages that are displayed as the result of an &BEGEMSG control statement are not scanned by the EXEC interpreter. Therefore, no variable substitution is performed and no data items are truncated. To display variable data, use the &EMSG control statement.

**&BEGPUNCH**

Use the &BEGPUNCH control statement to delimit the beginning of a list of one or more data lines to be spooled to your virtual card punch. The list of lines to be punched is terminated by the control statement &END, which must occur beginning in column 1. The format of the &BEGPUNCH control statement is:

```

&BEGPUNCH | [ALL]
```

where:

**ALL** specifies that data occupying columns 73 through 80 should be punched. If ALL is not specified, input records are truncated at column 72 and columns 73 through 80 of the output record are padded with blanks.

Usage Notes

1. Lines that are punched as the result of an &BEGPUNCH control statement are not scanned by the EXEC interpreter. Therefore, no variable substitution is performed and no data items are truncated. To punch variable data, you must use the &PUNCH control statement.
2. When you are finished punching lines in an EXEC procedure, you should use the CP CLOSE command to close your virtual punch.

**&BEGSTACK**

Use the &BEGSTACK control statement to delimit the beginning of a list of one or more data lines to be placed in the console input stack. The list of lines to be stacked is terminated by the control statement &END which must occur beginning in column 1. The format of the &BEGSTACK control statement is:

```

&BEGSTACK | [FIFO] [ALL]
 | [LIFO] []
```

where:

**FIFO** specifies that the lines that follow are to be stacked on a first in, first out basis. This is the default value.

**LIFO** specifies that the lines that follow are to be stacked on a last in, first out basis.

**ALL** specifies, for fixed-length EXEC files, that the entire line (to a maximum of 130 characters) is to be stacked. If ALL is not specified, the lines are truncated in column 72.

Usage Notes

1. Lines that are stacked as the result of an &BEGSTACK control statement are not scanned by the EXEC interpreter. Therefore, no variable substitution is performed, and data items are not truncated. To stack variable data, you must use the &STACK control statement.
2. To stack a null line in an EXEC file you must use the &STACK control statement. A null line following an &BEGSTACK control statement is interpreted as a line of blanks. To stack an INPUT or REPLACE subcommand to enter input mode from a fixed-length EXEC, you should use the &STACK control statement.

**&BEGTYPE**

Use the &BEGTYPE control statement to delimit the beginning of a list of one or more data lines to be displayed at the terminal. The list of lines to be displayed is terminated by the control statement &END, which must occur beginning in column 1. The format of the &BEGTYPE control statement is:

```
[&BEGTYPE | [ALL]]
```

where:

ALL specifies, for fixed-length EXEC files, that data occupying columns 73 through 130 is to be displayed. If ALL is not specified, the lines are truncated at column 72.

Usage Notes

1. Lines that are displayed as the result of an &BEGTYPE control statement are not scanned by the EXEC interpreter. Therefore, no variable substitution is performed, and data items are not truncated. To display variable data, you must use the &TYPE control statement.

**&CONTINUE**

Use the &CONTINUE control statement to instruct the EXEC interpreter to process the next statement in the EXEC file. The format of the &CONTINUE control statement is:

```
[&CONTINUE |]
```

Usage Notes

1. &CONTINUE is generally used in conjunction with an EXEC label (for example, -LAB &CONTINUE) to provide a branch address for &ERROR, &GOTO, and other branching statements. &CONTINUE is the default action taken when an error is detected in processing a CMS command.



**&CONTROL**

Use the &CONTROL control statement to specify the amount of data to be displayed in the execution summary of an EXEC. The format of the &CONTROL control statement is:

|          |                |                  |                   |                   |
|----------|----------------|------------------|-------------------|-------------------|
| &CONTROL | [ OFF ]        | [ <u>MSG</u> ]   | [ TIME ]          | [ <u>PACK</u> ]   |
|          | [ ERROR ]      | [ <u>NOMSG</u> ] | [ <u>NOTIME</u> ] | [ <u>NOPACK</u> ] |
|          | [ <u>CMS</u> ] |                  |                   |                   |
|          | [ ALL ]        |                  |                   |                   |

where:

- OFF** suppresses the display of CMS commands and of EXEC control statements as they execute, and any return codes that may result from CMS commands.
- ERROR** displays only those CMS commands that result in an error and also displays the error message and the return code.
- CMS** displays each CMS command as it is executed and all nonzero return codes.
- ALL** displays CMS commands and EXEC executable statements as they execute as well as any nonzero return codes from CMS commands.
- MSG** does not suppress the "FILE NOT FOUND" message if it is issued by the following commands when they are invoked from an EXEC procedure: ERASE, LISTFILE, RENAME, or STATE.
- NOMSG** suppresses the "FILE NOT FOUND" message if it is issued when the ERASE, LISTFILE, RENAME, or STATE commands are invoked from an EXEC procedure.
- TIME** includes the time-of-day value with each CMS command printed in the execution summary, for example:
- 14:36:30 TYPE A B
- This operand is effective only if CMS or ALL is also specified.
- NOTIME** does not include the time-of-day value with CMS commands printed in the execution summary.
- PACK** packs the lines of the execution summary so that surplus blanks are removed from the displayed lines.
- NOPACK** does not pack the lines of the execution summary.

Usage Notes

1. The execution summary may consist of CMS commands, responses, error messages, and return codes, as well as EXEC control statements and assignment statements. When EXEC statements are displayed, they are displayed in their scanned format, with all variable symbols substituted.

- Each operand remains set until explicitly reset by another &CONTROL statement which specifies a conflicting operand. When &CONTROL is used with no operands, all operands are reset to their default values.

## | &EMSG

| Use the &EMSG control statement to display a line of tokens to be edited as a VM/370 error message. The format of the &EMSG control statement is:

```
| ┌──┐
| | &EMSG | mmmnnns [tok1 ... [tokn]] |
| └──┘
```

| where:

| mmmnnn is a 6-character identification you may supply for the error message. Standard VM/370 messages are coded using a 3-character module code (mmm) and a 3-character message number (nnn).

| s indicates the severity code. The following codes qualify the message for error message editing:

| <u>Code</u> | <u>Message Type</u> |
|-------------|---------------------|
| I           | Information         |
| E           | Error               |
| W           | Warning             |

| tok1 ...[tokn]  
| is the text of the message to be displayed.

## | Usage Notes

| 1. When the severity code is I, E, or W, the message is displayed in accordance with the CP EMSG setting (ON, OFF, CODE, or TEXT). You can change the setting with the CP SET command, described in VM/370: CP Command Reference for General Users.

| 2. When an &EMSG code is displayed, it is prefixed with DMS. For example, the statement

```
| &EMSG ERRORIE INVALID ARGUMENT
```

| displays as follows when the EMSG setting is ON:

```
| DMSERRORIE INVALID ARGUMENT
```

| 3. To display an error message with unsubstituted data, or to display a line with words of more than 8 characters, use the &BEGEMSG control statement.

**&END**

Use the &END control statement to terminate a list of one or more lines that began with an &BEGMSG, &BEGPUNCH, &BEGSTACK, or &BEGTYPE control statement. The format of the &END control statement is:

```

&END |

```

The word "&END" must be entered beginning in column 1.

**&ERROR**

Use the &ERROR control statement to specify the action to be taken when a CMS command results in an error and returns with a nonzero return code. The format of the &ERROR control statement is:

```

&ERROR | [executable-statement]
 | [&CONTINUE]

```

where:executable-statement

specifies any executable statement, which may be an EXEC control statement or assignment statement or a CMS command. If you specify an EXEC control statement that transfers control to another line in the EXEC, execution continues at the specified line. Otherwise, execution continues with the line following the CMS command line that caused the error.

Usage Notes

1. If your EXEC does not contain an &ERROR control statement, then the default is &CONTINUE, that is, EXEC processing is to continue with the line following the CMS command that caused the error. You can use &ERROR &CONTINUE to reset a previous &ERROR statement.
2. The words following an &ERROR control statement are not scanned until a CMS command returns a nonzero return code. Therefore, if you specify an invalid EXEC statement, the error is not detected until a CMS command failure triggers the &ERROR statement. If the &ERROR statement executes a CMS command that also results in an error, EXEC processing is terminated.



**&GOTO**

Use the &GOTO control statement to transfer control to a specific location in the EXEC procedure. Execution then continues at the location that is branched to. The format of the &GOTO control statement is:

```

|-----|
| &GOTO | { TOP }
| | { line-number }
| | { -label }
|-----|

```

where:

TOP transfers control to the first line of the EXEC file.

line-number transfers control to a specific line in the EXEC file.

-label transfers control to a specific label in the EXEC file. A label must begin with hyphen (minus sign), and it must be the first token on a line. The remainder of the line may contain an executable statement or it may be null.

Usage Notes

1. Scanning for an EXEC label starts on the line following the &GOTO statement, goes to the end of the file, then to the top of the file, and (if unsuccessful) ends on the line above the &GOTO statement. If more than one statement in the file has the same label, the first one encountered by these rules satisfies the search.
2. To provide a branch a specific number of lines up or down in the EXEC, use the &SKIP control statement.

**| &HEX**

| Use the &HEX control statement to initiate or inhibit hexadecimal conversion in an EXEC procedure. The format of the &HEX control statement is:

```

|-----|
| &HEX | { ON }
| | { OFF}
|-----|

```

where:

| ON indicates that tokens beginning with the string X' are to be interpreted as hexadecimal notation.

| OFF indicates that no hexadecimal conversion is to be done by EXEC. OFF is the default setting.

Usage Notes

1. You should use the &HEX control statement when you want to display a hexadecimal value. For example,

EXEC Control Statements-&HEX, &IF

```

| &HEX ON
| &TYPE X'40
| &HEX

```

results in the display

28

If you did not use the &HEX ON control statement, the &TYPE statement would result in the display

X'40

2. To convert a hexadecimal value to its decimal equivalent, use an assignment statement.

**&IF**

Use the &IF control statement to test a condition in an EXEC procedure and to perform a particular action if the test is valid. If the test is invalid, execution continues with the statement following the &IF control statement. The format of the &IF statement is:

```

|-----|
| &IF | { token1 } operator { token2 } executable-statement
| | { &$ } | { &$ }
| | { &* } | { &* }
|-----|

```

where:

token1 may be numeric constants, character strings, or EXEC variable  
token2 symbols. All variable symbols are substituted before the &IF statement is executed.

&\* tests all of the arguments entered when the EXEC was invoked. All of the entered arguments must meet the specified condition in order for the &IF statement to be true.

&\$ tests all of the arguments entered when the EXEC was invoked. If at least one of the arguments satisfies the specified condition, the &IF statement is true.

operator indicates the test to be performed on the tokens. If both tokens are numeric, an arithmetic test is performed. Otherwise, a logical (alphabetic) test is performed. The comparison operators, listed below, may be specified either in symbolic or mnemonic form:

| <u>Symbol</u> | <u>Operation</u>                         |
|---------------|------------------------------------------|
| = or EQ       | equals                                   |
| ≠ or NE       | not equal                                |
| < or LT       | less than                                |
| <= or LE      | less than or equal to (not greater than) |
| > or GT       | greater than                             |
| >= or GE      | greater than or equal to (not less than) |

executable-statement is any valid EXEC executable statement which may be a CMS command, or EXEC control statement or assignment statement. You may also specify another &IF statement; the number of &IF statements that may be nested is limited only by the record

length of the file. In fixed-length EXEC files, only the first 72 characters of the line are scanned.

### Usage Notes

1. The values &\* and &\$ are reset when an &ARGS or &READ ARGS control statement is executed. They are not changed when you reset a specific numeric variable (&1 through &30).
2. If a variable symbol used in an &IF control statement is undefined, the EXEC interpreter cannot properly compare it. In cases where a variable may be null, or to check for a null symbol, you should use a concatenation character when you write the &IF statement, for example

```
&IF .&1 EQ . &GOTO -NOARGS
```

tests for a null symbol &1.

3. If the symbols &\* or &\$ are null because no arguments were entered, the entire &IF statement is treated as a null statement.

### &LOOP

Use the &LOOP control statement to describe a loop in an EXEC procedure, including the conditions for exit from the loop. The format of the &LOOP control statement is:

```

&LOOP | { n } { m }
 | { -label } { condition }
```

#### where:

- n** is a positive integer from 0 to 4095 that indicates the number of lines to be executed in the loop. These lines must immediately follow the &LOOP statement.
- label** specifies that all of the lines following the &LOOP statement down to, and including the line with the specified label, are to be executed in the loop. The first character of the label must be a hyphen, and it must be the first token on a line. The remainder of the line may contain an executable statement, or it may be null.
- m** is a positive integer from 0 to 4095 that indicates the number of times the loop is to be executed.
- condition** specifies the condition that must be met. The syntax of the exit condition is the same as that in the &IF statement, that is:

$$\left. \begin{array}{l} \text{tok1} \\ \&\$ \\ \&* \end{array} \right\} \text{operator} \left. \begin{array}{l} \text{tok2} \\ \&\$ \\ \&* \end{array} \right\}$$

## EXEC Control Statements-&LOOP, &PUNCH

### Usage Notes

1. When loop execution is complete, control passes to the next statement following the end of the loop.
2. The condition is always tested before the loop is executed. If the specified condition is met, then the loop is not executed. For example, the statement

```
&LOOP 3 &COUNT = 100
```

specifies that the next three statements are to be executed until the value of &COUNT is 100.

3. Loops may be nested up to four levels deep. All nested loops may end at the same label.

## &PUNCH

Use the &PUNCH control statement to punch a line of tokens to the virtual card punch. The format of the &PUNCH control statement is:

```
[&PUNCH | [tok1 [tok2 ... [tokn]]]]
```

### where:

tok1 [tok2 ... [tokn]]

specifies the tokens to be punched. All tokens are padded and truncated to 8 characters, as necessary. The punched line is right-padded with blanks to fill an 80-column card. If no tokens are specified, a line consisting of 80 blank characters is punched.

### Usage Notes

1. Lines punched with the &PUNCH control statement are scanned by the EXEC interpreter and variable symbols are substituted before the line is punched. In fixed-length EXEC files, only the first 72 characters of the record are scanned. To punch one or more lines of unscanned data, use the &BEGPUNCH or &BEGPUNCH ALL control statement.
2. When you have finished punching lines in an EXEC procedure, you can use the CP command CLOSE to close the spool punch file and release it for processing.



**&READ**

Use the &READ control statement to read one or more lines from the terminal or console stack. The lines may contain data or executable statements. The format of the &READ control statement is:

```

&READ | [n]
 | [1]
 | | ARGS
 | | VARS [&var1 [&var2 ... [&varn]]]

```

where:

**n** reads the next *n* lines from the terminal and treats them as if they had been in the EXEC file. Reading from the terminal stops when *n* lines have been read, or when an &LOOP statement or a statement that transfers control is encountered. If an &READ statement is encountered, the number of lines to be read by it is added to the number outstanding.

If *n* is not specified, 1 is assumed, and the EXEC continues processing after reading a single line.

**ARGS** reads a single line, assigns the entered tokens to the special variables &1, &2, ..., &*n*, and resets the special variables &INDEX, &\*, and &\$.

**VARS [ &var1 [ &var2 ... [ &varn ] ] ]** reads a single line and assigns the tokens entered to the variable symbols &var1, &var2, ..., &varn (up to 17).

These variables are scanned in the same way as if they appeared on the left-hand side of an assignment statement. If no variable names are specified, any data read from the terminal is lost.

Usage Notes

1. You can test the special variable &READFLAG to determine whether the next &READ statement will result in a physical read to your terminal (the value of &READFLAG is CONSOLE) or in reading a line from the console stack (the value of &READFLAG is STACK).

**&SKIP**

Use the &SKIP control statement to cause a specified number of lines in the EXEC file to be skipped. The format of the &SKIP control statement is:

```

&SKIP | [n]
 | [1]

```

## EXEC Control Statements-&SKIP, &SPACE

### where:

n specifies the number of lines to be skipped:

- If n is greater than 0, the specified number of lines are skipped. Execution continues on the line following the skipped lines. If the value of n surpasses the number of lines remaining in the file, the EXEC terminates processing.
- If n is equal to 0, no lines are skipped, and execution continues with the next line.
- If n is less than 0, execution continues with the line that is n lines above the current line. An attempt to skip beyond the beginning of the file results in an error exit from the EXEC.

n may be coded as a variable symbol; if no value is specified, 1 is assumed.

### Usage Notes

1. To pass control to a particular label in an EXEC procedure, use the &GOTO control statement. The &GOTO control statement provides more flexibility when you want to update your EXEC procedures. The &SKIP statement, however, is more efficient, in terms of execution time.

## &SPACE

Use the &SPACE control statement to display a specified number of blank lines at your terminal. The format of the &SPACE control statement is:

|        |  |   |   |   |
|--------|--|---|---|---|
| &SPACE |  | [ | n | ] |
|        |  | [ | 1 | ] |

### where:

n specifies the number of blank lines to be displayed at the terminal. If no number is specified, &SPACE 1 is assumed by default.

### Usage Notes

1. You may want to use the &SPACE control statement to control the format of the execution summary that displays while your EXEC executes.

**&STACK**

Use the &STACK control statement to stack a single data line in the console input stack. Stacked lines may be read by the EXEC, by CMS, or by the CMS Editor. The format of the &STACK control statement is:

```

|-----|
| &STACK | [FIFO] [tok1 [tok2 ... [tokn]]] |
| | [LIFO] [HT |
| | [] [RT |
| | |
|-----|

```

where:

FIFO specifies that the line is to be stacked in a first in, first out sequence.

LIFO specifies that the line is to be stacked in a last in, first out sequence.

tok1 [ tok2 ... [ tokn ] ] specify the tokens to be stacked. If no tokens are specified, a null line is stacked.

| HT stacks the CMS Immediate command HT (halt typing), which is  
| executed immediately. All terminal display from the EXEC is  
| suppressed until the end of the file or until an RT (resume  
| typing) command is read.

| RT stacks the CMS Immediate command RT (resume typing), which is  
| executed immediately. If terminal display has been suppressed  
| as the result of an HT (halt typing) request, display is  
| resumed.

Usage Notes

1. Lines stacked with the &STACK control statement are scanned by the EXEC interpreter and variable symbols are substituted before the line is stacked. To stack one or more unscanned lines, use the &BEGSTACK or &BEGSTACK ALL control statement.
2. You must use the &STACK control statement when you want to stack a null line.
3. Any CMS Immediate command may be executed in an EXEC, using the &STACK control statement.
4. A complete discussion of techniques you can use to stack commands and data in the console stack is provided in the VM/370: CMS User's Guide.

**&TIME**

Use the &TIME control statement to request timing information to be displayed at the terminal after each CMS command executes. The format of the &TIME control statement is:

```

&TIME | [ON]
 | [OFF]
 | [RESET]
 | [TYPE]

```

where:

- ON** resets the CPU times before every CMS command, and prints the timing information on return. If the &CONTROL control statement is set to CMS or ALL, the display of the timing information is followed by a blank line.
- OFF** does not automatically reset the CPU times before every CMS command, nor does it print the timing information on return.
- RESET** performs an immediate reset of the CPU times.
- TYPE** displays the current timing information (and resets the CPU times).

Usage Notes

1. When timing information is displayed, it is in the format:

T=x.xx/y.yy hh:mm:ss

where:

x.xx is the virtual CPU time used since it was last reset in the current EXEC file.

y.yy is the total CPU time used since it was last reset in the current EXEC file.

hh:mm:ss is the actual time of day in hours:minutes:seconds.

2. The CPU times are set to zero before the execution of the first statement in the EXEC file, and are set to zero (reset) whenever timing information is printed.

**&TYPE**

Use the &TYPE control statement to display a line of tokens at the terminal. The format of the &TYPE control statement is:

```
[&TYPE | [tok1 [tok2 ... [tokn]]]
```

where:

tok1 [tok2... [tokn]]  
 specify the tokens to be displayed. All tokens are padded or truncated to 8 characters, as necessary. If no tokens are specified, a null line is displayed.

Usage Notes

1. Lines displayed with the &TYPE control statement are scanned by the EXEC interpreter and variable symbols are substituted before the line is displayed. To display one or more unscanned lines, use the &BEGTYPE or &BEGTYPE ALL control statements.

## Built-in Functions

You can use the EXEC built-in functions to assign and manipulate variable symbols. With the exception of &LITERAL, built-in functions may only be used on the right-hand side of an assignment statement, as follows:

```
&MIX = &CONCAT &1 &2
```

Built-in functions may not be combined with arithmetic expressions.

Each of the built-in functions: &CONCAT, &DATATYPE, &LENGTH, &LITERAL, and &SUBSTR, is described separately.

## &CONCAT

Use the &CONCAT function to concatenate two or more tokens and assign the result to a variable symbol. The format of the &CONCAT function is:

```
&variable = &CONCAT tok1 [tok2 ... [tokn]]
```

### where:

&variable is the variable symbol whose value is determined by the &CONCAT function.

tok1 [tok2...[tokn]] specifies the tokens that are to be concatenated into a single token, for example:

```
&A = **
.
.
&B = &CONCAT XX &A 45
&TYPE &B
```

results in the printed line:

```
XX**45
```

### Usage Notes

1. If the concatenated token is longer than 8 characters, the data is left justified and truncated on the right.

**&DATATYPE**

Use the &DATATYPE function to determine whether the value of the specified token is alphabetic or numeric data. The format of the &DATATYPE function is:

```
| &variable = &DATATYPE token |
```

where:

&variable is the variable symbol whose value is determined by the &DATATYPE function.

token specifies the target token that is to be examined for alphabetic or numeric data. The result of the &DATATYPE function has the value NUM or CHAR, depending on the data type of the specified token. For example,

```
SCHECK = &DATATYPE ABC
&TYPE SCHECK
```

results in the display:

```
CHAR
```

**&LENGTH**

Use the &LENGTH function to determine the number of characters in a token. The format of the &LENGTH function is:

```
| &variable = &LENGTH token |
```

where:

| &variable is the variable symbol whose value is determined by the &LENGTH function.

| token specifies the target token that is to be examined for nonblank characters. The result of the &LENGTH function is the number of nonblank characters in the specified token. For example,

```
&LEN = &LENGTH ALPHA
&TYPE &LEN
```

results in the display

```
5
```

## &LITERAL

Use the &LITERAL function to inhibit variable substitution on the specified token. The &LITERAL function may appear in any EXEC control statement, as follows:

```
[...] &LITERAL token[...]
```

### where:

token specifies the token whose literal value is to be used without substitution. For example:

```
&X = **
&TYPE &LITERAL &X EQUALS &X
```

results in the printed line:

```
&X EQUALS **
```

## &SUBSTR

Use the &SUBSTR function to extract a character string from a specified token and to assign the substring to a variable symbol. The format of the &SUBSTR function is:

```
[&variable = &SUBSTR token i [j]
```

### where:

&variable is the variable symbol whose value is determined by the &SUBSTR function.

token is the token from which the character string is to be extracted.

i specifies the character position in the token of the first character to be used in the substring.

j specifies the number of characters in the string. If omitted, the remainder of the token is used.

### Usage Notes

1. The values of i and j (if given) must be positive integers. For example:

```
&A = &SUBSTR ABCDE 2 3
&TYPE &A
```

results in the printed line:

```
BCD
```



## Special Variables

Special variables are variable symbols that are assigned values by the EXEC interpreter, and which you can test or display in your EXEC procedures. In some cases, you may assign your own values to EXEC special variables; these cases are noted in the variable descriptions.

### &n

The &n special variable represents the numeric variables &1 through &30. When an EXEC is invoked, the numeric variables from &1 through &30 are initialized according to the arguments that are passed to the EXEC file (if any).

The numeric variables can be reset by either an &ARGS or &READ ARGS control statement; when fewer than 30 arguments are set or reset, the remainder of the &n variables are set to blanks. A particular argument can be set to blanks by assigning it a percent sign (%) when invoking the EXEC procedure, in an &ARGS control statement, or in an &READ ARGS control statement.

You may set the values of specific arguments using assignment statements. Any value of n, however, that is greater than 30 or less than 0 is rejected by the EXEC interpreter.

### &\* and &\$

These variables can be used to perform a collective test on all of the arguments passed to the EXEC procedure. &\* and &\$ may only be used in the &IF and &LOOP control statements, and are described under the description of the &IF control statement.

You may not assign values to the special variables &\* and &\$.

### &0

The &0 special variable contains the filename of the EXEC file. You may test and manipulate this variable.

### | &DISKx

| You can use the &DISKx special variable to determine whether a disk is  
| an OS, DOS or CMS disk. x represents the mode letter at which the disk  
| is accessed. For example, if you access an OS disk with a mode letter  
| of C, then the special variable &DISKC has a value of OS. The possible  
| values for the &DISKx special variable are OS (for an OS disk), DOS (for  
| a DOS disk), CMS (for a CMS disk), and NA (when the disk is not  
| accessed).

| You may set or change the values of an &DISKx special variable; if  
| you do so, however, you will no longer be able to test the status of the  
| disk at mode x.

## EXEC Special Variables

### **| &DISK\***

| The &DISK\* special variable contains the 1-character mode letter of the first read/write disk in the CMS search order. If you have no read/write disks accessed, this special variable contains the value NONE.

| You may assign a value to the &DISK\* special variable for your own use; if you do so, however, you will not be able to use it to obtain the filemode letter of a read/write disk.

### **| &DISK?**

| You can use the &DISK? special variable in an EXEC to determine which read/write disk that you have accessed has the most space on it. If you have no read/write disks accessed, &DISK? contains the value NONE.

| You may assign a value to the &DISK? special variable for your own use; if you do so, however, you will no longer be able to locate the read/write disk with the most space.

### **| &DOS**

| The &DOS special variable contains one of the two character values ON or OFF, depending on whether the CMS/DOS environment is active. If you have issued the command

| set dos on

| then the &DOS special variable contains the value ON.

| You may set or change the value of the &DOS special variable for your own use; if you do so, however, you will not be able to test whether the CMS/DOS environment is active.

### **&EXEC**

The &EXEC special variable is the filename of the EXEC file. You cannot set this variable explicitly but you can examine and test it.

### **&GLOBAL**

| The &GLOBAL special variable contains the recursion level of the EXEC currently executing. Since the EXEC interpreter can handle up to 19 levels of recursion, the value of &GLOBAL ranges from 1 to 19. You cannot set this variable explicitly, but you can examine and test it.

**&GLOBALn**

The **&GLOBALn** special variable represents the variables **&GLOBAL0** through **&GLOBAL9**. You can set these variables only to integral numeric values. They are all initially set to 1. Unlike other EXEC variables, these can be used to communicate between different recursion levels of the EXEC interpreter.

**&INDEX**

The **&INDEX** special variable contains the number of arguments passed to the EXEC procedure. Since up to 30 arguments can be passed to an EXEC procedure, the value of **&INDEX** can range from 0 through 30.

Although you can not set this variable explicitly, it is reset by an **&ARGS** or **&READ ARGS** control statement. **&INDEX** can be examined to determine the number of active arguments in the EXEC procedure.

**&LINENUM**

The **&LINENUM** special variable contains the current line number in the EXEC file. You cannot explicitly set this variable but you can examine and test it.

**&READFLAG**

The **&READFLAG** special variable contains one of the two literal values **CONSOLE** or **STACK**. If there are stacked lines in the terminal input buffer (console stack) **&READFLAG** contains the value **STACK** and the next read request results in a line being read from the stack. If not, then the next read request results in a physical read to the terminal, and the value of **&READFLAG** is **CONSOLE**. You cannot explicitly set this variable but you can examine and test it.

**&RETCODE**

The **&RETCODE** special variable contains the return code from the most recently executed CMS command. **&RETCODE** can contain only integral numeric values (positive or negative), and is set after each CMS command is executed. You can examine, test, and change this variable but changing it is not recommended.

**&TYPEFLAG**

The **&TYPEFLAG** special variable contains one of the two literal values: **RT** (resume typing) or **HT** (halt typing). It contains the value **HT** when terminal display has been suppressed by the Immediate Command **HT**. It contains the value **RT** when the terminal is displaying output. You cannot explicitly set this variable, but you can examine and test it.



## Section 6. CMS Macro Instructions

This section describes the formats of the CMS assembler language macros, which you can use when you write assembler language programs to execute in the CMS environment. To assemble a program using any of these macros, you must issue the GLOBAL command specifying CMSLIB MACLIB, which is the macro library (located on the system disk) which contains CMS macros.

For functional descriptions and usage examples of the CMS macros, see the VM/370: CMS User's Guide.

Coding conventions for CMS macros are the same as those for all assembler language macros. The macro format descriptions show optional operands in the format

[,operand]

indicating that if you are going to use this operand, it must be preceded by a comma (unless it is the first operand coded). If a macro statement overflows to a second line, you must use a continuation character in column 72. No blanks may appear between operands. Incorrect coding of any macro results in assembler errors and MNOTES.

Where applicable, the end of a macro description contains a list of the possible error conditions that may occur during the execution of the macro, and the associated return codes. These return codes are always placed in register 15. The macros that produce these return codes have ERROR= operands, that allow you to specify the address of an error handling routine, so that you can check for particular errors during macro processing. If an error occurs during macro processing and no error address is provided, execution continues at the next sequential instruction following the macro.

**COMPSWT**

Use the COMPSWT macro to turn the compiler switch (COMPSWT) flag on or off. The COMPSWT flag is in the OSSFLAGS byte of the nucleus constant area (NUCON). The format of the COMPSWT macro is:

```
[label] | COMPSWT | { ON }
 | | { OFF }
```

where:

label is an optional statement label.

**ON** turns the COMPSWT flag on. When this flag is on, any program called by a LINK, LOAD, XCTL, or ATTACH macro must be a nonrelocatable module in a file with a filetype of MODULE; it is loaded via the CMS LOADMOD command.

**OFF** turns the COMPSWT flag off. When this flag is off, any program called by a LINK, LOAD, XCTL, or ATTACH macro must be a relocatable object module residing in a file with a filetype of TEXT or TXTLIB; it is loaded via the CMS INCLUDE command.

**FSCB**

Use the FSCB macro to create a file system control block (FSCB) for a CMS input or output disk file. The format of the FSCB macro is:

```
[label] | FSCB | [fileid] [,RECFM=format] [,BUFFER=buffer]
 | | [,BSIZE=size] [,RECNO=number] [,NOREC=numrec]
```

where:

label is an optional statement label.

fileid specifies the CMS file identifier, which must be enclosed in quotation marks and separated by blanks ('filename filetype filemode'). If filemode is omitted, A1 is assumed.

RECFM=format indicates whether the records are fixed- (F) or variable- (V) length format. The default is F.

BUFFER=buffer specifies the address of an I/O buffer, from which records are to be read or written.

BSIZE=size specifies the number of bytes to be read or written for each read or write request.

RECNO=number specifies the record number of the next record to be accessed, relative to the beginning of the file, record 1. The default is 0, which indicates that records are to be accessed sequentially.

NOREC=numrec specifies the number of records to be read in the next read operation. The default is 1.

Usage Notes

1. The options RECFM, BUFFER, BSIZE, RECNO, and NOREC must all be specified as self-defining terms.
2. You can use the same FSCB to reference several different files; you can override the fileid, or any of the options, on the FSOPEN, FSWRITE, or FSREAD macros when you reference a file via its FSCB.
3. You can use multiple FSCBs to reference the same file, for example, if you wanted one FSCB for writing and a different FSCB for reading the file. Keep in mind, however, that the file characteristics are inherent to the file, and not to the FSCB. If you establish a read or write pointer using the RECNO option in one FSCB, that pointer remains unchanged unless you specify the RECNO option again on the same or any other FSCB for that file.

**| FSCBD**

| Use the FSCBD macro to generate a DSECT for the file system control block (FSCB). The format of the FSCBD macro is:

```
| [label] | FSCBD |
```

**| where:**

| label is an optional statement label. The first statement in the FSCBD macro expansion is labeled FSCBD.

**| Usage Notes**

1. You can use the labels established in the FSCB DSECT to modify the fields in an FSCB for a particular file. An FSCB is created explicitly by the FSCB macro, and implicitly by the FSREAD, FSWRITE, and FSOPEN macros.
2. The FSCB macro expands as follows:

|          | FSCBD |     |                                            |
|----------|-------|-----|--------------------------------------------|
|          | DSECT |     |                                            |
| FSCBCOMM | DS    | CL8 | Command                                    |
| FSCBFN   | DS    | CL8 | Filename                                   |
| FSCBFT   | DS    | CL8 | Filetype                                   |
| FSCBFM   | DS    | CL2 | Filemode                                   |
| FSCBITNO | DS    | H   | Relative record (item) number              |
| FSCBBUFF | DS    | A   | Address of read/write buffer               |
| FSCBSIZE | DS    | F   | Length of buffer                           |
| FSCBFV   | DS    | CL2 | Record format (F or V)                     |
| FSCBNOIT | DS    | H   | Number of records to be read/written       |
| FSCBNORD | DS    | A   | Number of <del>records</del> actually read |

*bytes*

## FSCLOSE

Use the FSCLOSE macro to close an open file and save its current status on disk. The format of the FSCLOSE macro is:

```
[label] | FSCLOSE | { fileid[,FSCB=fscb] } [,ERROR=erraddr]
 | { FSCB=fscb }
```

where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.  
 (reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label on the FSCB macro.  
 (reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. Although CMS routines close files when a command or program completes execution, you can use the FSCLOSE macro when you are executing a program from within an EXEC, or when you are going to read and write records in the same file.
2. If you specify both fileid and FSCB, the fileid is used to fill in the FSCB.

Error Conditions

If an error occurs, register 15 contains the following error code:

| <u>Code</u> | <u>Meaning</u> |
|-------------|----------------|
| 6           | File not open  |



**FSERASE**

Use the FSERASE macro to delete a CMS disk file. The format of the FSERASE macro is:

```
[label] | FSERASE | { fileid[,FSCB=fscb] } [,ERROR=erraddr]
 | | { FSCB=fscb }
```

where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.  
 (reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label of an FSCB macro.  
 (reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error occurs. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. On return from the FSERASE macro, register 1 points to a parameter list. The second, third, and fourth words of the list contain the filename, filetype, and filemode of the file.
2. If fileid and FSCB= are both coded, the fileid is used to fill in the FSCB.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>       |
|-------------|----------------------|
| 24          | Parameter list error |
| 28          | File not found       |
| 36          | Disk not accessed    |

## FSOPEN

Use the FSOPEN macro to ready a file for either input or output. The format of the FSOPEN macro is:

```
[[label] | FSOPEN | { fileid [,FSCB=fscb] } [,ERROR=erraddr][,options] |
| | { FSCB=fscb }]
```

### where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' the fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.

(reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label on an FSCB macro.

(reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

### Options

You can specify any of the following FSCB macro options on the FSOPEN macro:

```
BUFFER=buffer
RECNO=number
BSIZE=size
RECFM=format
NOREC=numrec
```

These options may be specified either as self-defining terms or in register notation.

When you use any of these options, the associated field in the FSCB is modified.

### Usage Notes

1. On return from the FSOPEN macro, register 1 points to the FSCB for the file. If no FSCB exists, one is created in the FSOPEN macro expansion.
2. If you code both fileid and FSCB=, the fileid is used to fill in the FSCB.
3. You can use the FSOPEN macro to verify the existence of a file to be opened for reading or writing and to create an FSCB for it.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>          |
|-------------|-------------------------|
| 20          | Invalid file identifier |
| 28          | File does not exist     |

**FSREAD**

Use the FSREAD macro to read a record from a disk file into an I/O buffer. The format of the FSREAD macro is:

```
[label] | FSREAD | { fileid[,FSCB=fscb] } [,ERROR=erraddr] [,options] |
 | | { FSCB=fscb } |
```

where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' the fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.

(reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label of an FSCB macro.

(reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Options

You can specify any of the following FSCB macro options on the FSREAD macro:

```
BUFFER=buffer
NOREC=numrec
BSIZE=size
RECNO=number
```

These options may be specified as self-defining terms or in register notation.

When you use any of these options, the associated field in the FSCB is modified.

## FSREAD Macro

### Usage Notes

1. If an FSCB macro has not been coded for a file (and the FSCB= operand is not coded), you must specify the BUFFER= and BSIZE= options.
2. On return from the FSREAD macro, register 1 points to the FSCB for the file. If no FSCB exists, one is created following the FSREAD macro instruction.
3. If you specify both fileid and FSCB=, the fileid is used to fill in the FSCB.
4. Register 0 contains, after the read operation is complete, the number of bytes actually read. This information is also contained in the FSCBNORD field of the FSCB.
5. To read records sequentially beginning with a particular record number, use the RECNO option to specify the first record to be read. On the next FSREAD instruction, use RECNO=0 so that reading continues sequentially following the first record read.

### Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                                                                 |
|-------------|--------------------------------------------------------------------------------|
| 1           | File not found                                                                 |
| 2           | Invalid buffer address                                                         |
| 3           | Permanent I/O error                                                            |
| 5           | Number of records is less than or equal to zero, or greater than 32,768        |
| 7           | Invalid record format (only checked when the file is first opened for reading) |
| 8           | Incorrect length                                                               |
| 9           | File open for output                                                           |
| 11          | Number of records greater than 1 for variable-length file                      |
| 12          | End-of-file                                                                    |
| 13          | Variable-length file has invalid displacement in active file table             |
| 14          | Invalid character in filename                                                  |
| 15          | Invalid character in filetype                                                  |

**FSSTATE**

Use the FSSTATE macro to determine whether a particular file exists. The format of the FSSTATE macro is:

```
[label] | FSSTATE | { fileid [,FSCB=fscb] } [,ERROR=erraddr]
 | | { FSCB=fscb } }
```

where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' the fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.

(reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label on an FSCB macro.

(reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. If the specified file exists, register 15 contains a 0 return code.
2. When the FSSTATE macro completes execution, register 1 contains the address of the file status table (FST) for the specified file.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>              |
|-------------|-----------------------------|
| 20          | Invalid character in fileid |
| 24          | Invalid filemode            |
| 28          | File not found              |
| 36          | Disk not accessed           |

## FSWRITE

Use the FSWRITE macro to write a record from an I/O buffer to a CMS disk file. The format of the FSWRITE macro is:

```
[[label] | FSWRITE | { fileid[,FSCB=fscb] } [,ERROR=erraddr][,options] |
| | { FSCB=fscb }]
```

### where:

label is an optional statement label.

fileid specifies the CMS file identifier. It may be:

'fn ft fm' the fileid enclosed in quotation marks and separated by blanks. If fm is omitted, A1 is assumed.

(reg) a register other than 0 or 1 containing the address of the fileid (18 characters).

FSCB=fscb specifies the address of an FSCB. It may be:

label the label on an FSCB macro.

(reg) a register containing the address of an FSCB.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

### Options

You can specify any of the following FSCB macro options on the FSWRITE macro:

```
BUFFER=buffer
RECNO=number
BSIZE=size
NOREC=numrec
RECFM=format
```

These options may be specified as either self-defining terms or in register notation.

When you use any of these options, the associated field in the FSCB for the file is filled in or modified.

### Usage Notes

1. If an FSCB macro has not been coded for a file (and the FSCB= operand is not coded on the FSWRITE macro), you must specify the BUFFER= and BSIZE= options. For the filemode, you must specify both a letter and a number. If the file is a variable-length file, you must also specify the RECFM option.
2. On return from the FSWRITE macro, register 1 contains the address of the FSCB for the file. If no FSCB exists, one is created following the FSWRITE macro instruction.

3. If you specify both fileid and FSCB=, the fileid is used to fill in the FSCB.
4. If the RECNO option is specified (either on the FSWRITE macro or in the FSCB), that specified record is written. Otherwise, the next sequential record is written. For new files, writing begins with record 1; for existing files, writing begins with the first record following the end of the file.
5. To write records sequentially beginning with a particular record number, use the RECNO option to specify the first record to be written. On the next FSWRITE instruction, use RECNO=0 so that writing continues sequentially, following the first record written.
6. To write blocked records (valid for fixed-length files only), use the BSIZE and NOREC options to specify the blocksize and number of records per block, respectively. For example, to write 80-byte records into 800-byte blocks, you should specify BSIZE=800 and NOREC=10. The buffer you use must be at least 800 bytes long.

### Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                                                                                   |
|-------------|--------------------------------------------------------------------------------------------------|
| 2           | Invalid buffer address                                                                           |
| 4           | First character of filemode is illegal                                                           |
| 5           | Second character of filemode is illegal                                                          |
| 6           | Item number too large                                                                            |
| 7           | Attempt to skip over unwritten variable-length item                                              |
| 8           | Buffer size not specified                                                                        |
| 9           | File open for input                                                                              |
| 10          | Maximum number files reached                                                                     |
| 11          | Record format not F or V                                                                         |
| 12          | Attempt to write on read-only disk                                                               |
| 13          | Disk is full                                                                                     |
| 14          | Number of bytes to be written is not integrally divisible by the number of records to be written |
| 15          | Length of fixed-length item not the same as previous item                                        |
| 16          | Record format specified not the same as file                                                     |
| 17          | Variable-length item greater than 65K bytes                                                      |
| 18          | Number of records greater than 1 for variable-length file                                        |
| 19          | Maximum number of data blocks per file reached (16060)                                           |
| 20          | Invalid character detected in filename                                                           |
| 21          | Invalid character detected in filetype                                                           |
| 22          | Virtual storage capacity exceeded                                                                |
| 25          | Insufficient free storage available for file directory buffers                                   |

**HNDEXT**

Use the HNDEXT macro to trap external interrupts and pass control to an internal routine for processing. External interrupts are caused, in a virtual machine, by the CP EXTERNAL command. The format of the HNDEXT macro is:

```
[label] | HNDEXT | { SET, address }
 | | { CLR
```

where:

label is an optional statement label.

SET specifies that you want to trap external interrupts.

address specifies the address in your program of the routine to be given control when an external interrupt occurs.

CLR specifies that you no longer want to trap external interrupts.

Usage Notes

1. External interrupts (other than timer interrupts) normally place your virtual machine in the debug environment.
2. When your interrupt handling routine is given control, all virtual interrupts, except multiplexor, are disabled. If you are using the CMS blip function, all blips are stacked.
3. You are responsible for providing proper entry and exit linkage for your interrupt handling routine. When your routine receives control, register 1 points to a save area in the format:

| <u>Label</u> | <u>Displacement</u> |            |
|--------------|---------------------|------------|
|              | <u>Dec</u>          | <u>Hex</u> |
| GRS          | 0                   | 0          |
| FRS          | 64                  | 40         |
| PSW          | 96                  | 60         |
| UAREA        | 108                 | 68         |
| END          | 180                 | B4         |

Register 13 points to the user save area at label UAREA.

Register 15 contains the entry point address of your routine; it must return control to the address in register 14.



## HNDINT

Use the HNDINT macro to trap interrupts for a specified I/O device. The format of the HNDINT macro is:

|         |        |                                                          |
|---------|--------|----------------------------------------------------------|
| [label] | HNDINT | { SET, (dev1, {addr}, cuu, {ASAP}) [ , (dev2...) ... ] } |
|         |        | { CLEAR, (dev1) [ , (dev2) [...] ] }                     |
|         |        | [ , ERROR=erraddr ]                                      |

### where:

- label is an optional statement label.
- SET specifies that you want to trap interrupts for the specified device.
- dev specifies a 4-character symbolic name for the device whose interrupts are to be trapped.
- addr specifies the address in your program of the routine to be given control when the interrupt occurs. An address of 0 indicates that interrupts for the device are to be ignored.
- cuu specifies the virtual device address, in hexadecimal, of the device whose interrupts are to be trapped.
- ASAP specifies that the routine at addr is to be given control as soon as the interrupt occurs.
- WAIT specifies that the routine at addr is to be given control after the WAITD macro is issued for the device.
- CLR specifies that you no longer want to trap interrupts for the specified device.
- ERROR=erraddr specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

### Usage Notes

1. You can define interrupt handling routines for more than one device in a single HNDINT macro. The argument list for each device must be enclosed in parentheses and separated from the next list by a comma.
2. If you specify WAIT, then the routine at the specified address in your program receives control when a WAITD macro that specifies the same symbolic device name is issued. If the WAITD macro has already been issued for the device when the interrupt occurs, then the routine at the specified address receives control immediately.
3. You are responsible for establishing proper entry and exit linkage for your interrupt handling routine. When your routine receives control, the significant registers contain:

| <u>Registers</u> | <u>Contents</u>                |
|------------------|--------------------------------|
| 0-1              | I/O old PSW                    |
| 2-3              | Channel status word (CSW)      |
| 4                | Address of interrupting device |
| 14               | Return address                 |
| 15               | Entry point address            |

Your routine must return control to the address in register 14, and indicate, via register 15, whether processing is complete. A 0 in register 15 means that you are through handling the interrupt; any nonzero return code indicates that you expect another interrupt.

4. The interrupt handling routine that you code should not perform any I/O operations. When it is given control, all I/O interrupts and external interrupts are disabled.

#### Error Conditions

If an error occurs, register 15 contains a 1, indicating that either the device address (cuu) or the address of the interrupt handling routine (addr) is invalid.

## HNDSVC

Use the HNDSVC macro to trap interrupts caused by specific supervisor call (SVC) instructions. The format of the HNDSVC macro is:

```
[label] | HNDSVC | { SET, (svcnum, address) [, (svcnum, address) ...] }
 | | { CLEAR, svcnum [, svcnum ...] }
 | |
 | | [, ERROR=erraddr]
```

#### where:

- label is an optional statement label.
- SET specifies that you want to trap SVCs of the specified number (s).
- svcnum specifies the number of the SVC you want to trap. SVC numbers 0 through 200 and 206 through 255 are valid.
- address specifies the address of the routine in your program that should receive control whenever the specified SVC is issued.
- CLR specifies that you no longer want to trap the specified SVC (s).
- ERROR=erraddr specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. You are responsible for providing the proper entry and exit linkage for your SVC-handling routine. When your program receives control, the following registers contain:

| <u>Register</u> | <u>Contents</u>                                    |
|-----------------|----------------------------------------------------|
| 12              | Address of your SVC-handling routine               |
| 13              | Address of an 18-fullword save area (for your use) |
| 14              | Return address                                     |

Your routine must return control to the address in register 14.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                                |
|-------------|-----------------------------------------------|
| 1           | Invalid SVC number or address                 |
| 2           | SVC number set replaced previously set number |
| 3           | SVC number cleared was not set                |

**LINEDIT**

Use the LINEDIT macro to convert decimal values into EBCDIC or hexadecimal and to display the results at your terminal. The format of the LINEDIT macro is:

```

[label] LINEDIT [,TEXT='message-text']
 [,TEXTA=address]
 [,DOT={ YES }] [,COMP={ YES }]
 [{ NO }] [{ NO }]
 [,SUB=(substitution-list)]
 [,DISP= (TYPE) [,BUFFA=address]
 NONE
 SIO
 PRINT
 CPCOMM
 ERRMSG]
 [,MF= { I
 L
 (E,address) }]
 [,RENT={ YES }]
 [{ NO }]
 [,MAXSUBS=number]

```

The LINEDIT macro operands are listed below, briefly. For detailed formats, descriptions, and examples, refer to the appropriate heading following "LINEDIT Macro Operands."

TEXT='message-text'  
 specifies the text of the message to be edited.

## LINEDIT Macro

### TEXTA=address

specifies the address of the message text. It may be:

label the symbolic address of the message text.

(reg) a register containing the address of the message text.

- DOT specifies whether a period is to be placed at the end of the line.
- COMP specifies whether multiple blanks are to be removed from the line.
- SUB specifies a substitution list describing the conversions to be performed on the line.
- DISP specifies how the edited line is to be used. When DISP is not coded, the message text is displayed at the terminal.
- BUFFA specifies the address of the buffer in which the line is to be copied.
- MF specifies the macro format.
- MAXSUBS specifies the maximum number of substitutions (MAXSUBS is used with the list form of the macro).
- RENT specifies whether reentrant code must be generated.

### Usage Notes

1. You should never use registers 1 or 15 as address registers when you code the LINEDIT macro; these registers are used by the macro.
2. When message text for the LINEDIT macro contains two or more consecutive periods, it indicates that a substitution is to be performed on that portion of the message. The number of periods you code indicates the number of characters that you want to appear as output. To indicate what values are to replace the periods, code a substitution list using the SUB operand.
3. When you use the standard (default) form of the LINEDIT macro, reentrant code is produced, except when you specify more than one substitution list, or when you use register notation to indicate an address on the TEXTA or BUFFA operands. When any of these conditions occur, an MNOTE message is produced, indicating that the code is not reentrant.

If you do not care whether the code is reentrant, you can specify the RENT=NO operand to suppress the MNOTE message. Otherwise, you can use the list and execute forms of the macro to write reentrant code (see "MF Operand").

### *LINEDIT Macro Operands*

#### TEXT Operand

Use the TEXT operand to specify the exact text of the message on the macro instruction. The message text must appear within single quotation marks, as follows:

TEXT='message text'

If you want a single quotation mark to appear within the actual message text, you must code two of them.

Text specified on the LINEDIT macro is edited so that multiple blanks appear as only a single blank, and a period is placed at the end of the line, for example:

LINEDIT TEXT='IT ISN'T READY'

results in the display:

IT ISN'T READY.

### TEXTA Operand

Use the TEXTA operand when you want to display a line that is contained in a buffer. You may specify either a symbolic address or use register notation, as follows:

TEXTA={label}  
{(reg)}

In either case, the first byte at the address specified must contain the length of the message text, for example:

```

LINEDIT TEXTA=MESSAGE
.
.
.
MESSAGE DC X'16'
 DC CL22'THIS IS A LINE OF TEXT'

```

If you use register notation with either the standard or list forms of the macro, the code generated is not reentrant. To suppress the MNOTE that informs you that code is not reentrant, use the RENT=NO operand.

### DOT Operand

Use the DOT operand when you do not want a period placed at the end of the message text. The format of the DOT operand is:

DOT={YES}  
{NO}

For example, if you code

LINEDIT TEXT='HI!',DOT=NO

the line is displayed as

HI!

### COMP Operand

Use the COMP operand when you want to display multiple blanks within your message text. The format of the COMP operand is:

COMP={YES}  
{NO}

## LINEDIT Macro

For example, if you code

```
LINEDIT TEXT='TOTAL 5',COMP=NO
```

The line is displayed as

```
TOTAL 5.
```

### SUB Operand

Use the SUB operand to specify the type of substitution to be performed on those portions of the message that contain periods. For each set of periods, you must specify the type of substitution and the value to be substituted or its address. The format of the SUB operand is:

```
SUB= (
 HEX{ , (reg) }
 DEC{ ,expression }
)
 (
 HEXA{ ,address }
 DECA{ , (reg) }
)
 (
 HEX4A { ,address }
 CHARA { , (reg) }
 CHAR8A { { ,address } , {length} }
 { , (reg) } { (reg) }
)
```

Each of the possible substitution pairs are described below, followed by discussions of length specification and multiple substitution lists.

#### HEX, (reg)

converts the value in the specified register to graphic hexadecimal format and substitutes it in the message text. If you code fewer than eight consecutive periods in the message text, then leading digits are truncated; leading zeros are not suppressed.

For example, if register 3 contains the value C0031FC8, then the macro

```
LINEDIT TEXT='VALUE = ...',SUB=(HEX,(3))
```

results in the display

```
VALUE = FC8.
```

#### HEX,expression

converts the given expression to graphic hexadecimal format and substitutes it in the message text. The variable, expression, may be a symbolic address or symbol equate; it is evaluated by means of a LOAD ADDRESS (LA) instruction. For example, if your program has a label BUFF1, the line

```
LINEDIT TEXT='BUFFER IS LOCATED AT',SUB=(HEX,BUFF1)
```

might result in the display:

```
BUFFER IS LOCATED AT 0201AC.
```

If you code fewer than eight periods in the message text, leading digits are truncated; leading zeros are not suppressed.

**DEC, (reg)**

converts the value in the specified register into graphic decimal format and substitutes it in the message text. Leading zeros are suppressed. If the number is negative, a leading minus sign is inserted. For example, if register 3 contains the decimal value 10,345, then the macro

```
LINEDIT TEXT='REG 3 =',SUB=(DEC,(3))
```

results in the line

```
REG 3 = 10345.
```

**DEC, expression**

converts the given expression to graphic decimal format and substitutes it in the message text. The variable, expression, may be a symbolic label in your program or a symbol equate. For example, if your program contains the statement

```
VALUE EQU 2003
```

then the macro

```
LINEDIT TEXT='VALUE IS',SUB=(DEC,VALUE+5)
```

results in the display:

```
VALUE IS 2008.
```

**HEXA, address**

converts the fullword at the specified address to graphic hexadecimal format and substitutes it in the message text. If you code fewer than eight periods in the message text, leading digits are truncated; leading zeros are not removed. For example, if you code

```
LINEDIT TEXT='HEX VALUE IS',SUB=(HEXA,CODE)
```

then the last five hexadecimal digits of the fullword at the label CODE are substituted into the message text.

**HEXA, (reg)**

converts the fullword at the address indicated in the specified register into graphic hexadecimal format and substitutes it in the message text. For example, if you code

```
LINEDIT TEXT='REGISTER 5 ->',SUB=(HEXA,(5))
```

then the last six hexadecimal digits of the fullword whose address is in register 5 are substituted in the message text.

If you code fewer than eight digits, leading digits are truncated; leading zeros are not suppressed.

**DECA, address**

converts the fullword at the specified address to graphic decimal format. Leading zeros are suppressed; if the number is negative, a minus sign is inserted. For example, if you code

```
LINEDIT TEXT='COUNT =',SUB=(DECA,COUNT)
```

then the fullword at the location COUNT is converted to graphic decimal format and substituted in the message text.

## LINEDIT Macro

### DECA, (reg)

converts the fullword at the address specified in the indicated register into graphic decimal format and substitutes it in the message text. For example,

```
LINEDIT TEXT='SUM =',SUB=(DECA,(3))
```

causes the value in the fullword whose address is in register 3 to be displayed in graphic decimal format.

### HEX4A, address

converts the data at the specified address into graphic hexadecimal format, and inserts a blank character following every 4 bytes (8 characters of output). The data to be converted does not have to be on a fullword boundary.

When you code periods in the message text for substitution, you must code sufficient periods to allow for the blanks. Thus to display 8 bytes of information (16 hexadecimal digits), you must code 17 periods in the message text.

For example, to display 7 bytes of hexadecimal data beginning at the location STOR in your program, you could code:

```
LINEDIT TEXT='STOR:',SUB=(HEX4A,STOR)
```

This might result in a display:

```
STOR: 0A23F115 78ACFE
```

Note that 15 periods were coded in the message text, to allow for the blank following the first 4 bytes displayed.

### HEX4A, (reg)

converts the data at the address indicated in the specified register into graphic hexadecimal format and inserts a blank character following every 4 bytes displayed (8 characters of output).

When you code the message text for substitution, you must code sufficient periods to allow for the blank characters to be inserted.

For example, the line

```
LINEDIT TEXT='BUFFER:',SUB=(HEX4A,(6))
```

results in the display of the first 9 bytes at the address in register 6, in the format

```
hhhhhhhh hhhhhhhh hh
```

### CHARA, address

substitutes the character data at the specified address into the message text. For example,

```
LINEDIT TEXT='NAME IS ''.....'',SUB=(CHARA,NAME)
```

causes the 10 characters at location NAME to be substituted into the message text. Multiple blanks are removed.



**CHARA, (reg)**  
 substitutes the character data at the address indicated in the specified register into the message text. For example,

```
LINEDIT TEXT='CODE IS',SUB=(CHARA,(7))
```

the first 4 characters at the address indicated in register 7 are substituted in the message line.

**CHAR8A, address**  
 substitutes the character data at the specified address into the message text, and inserts a blank character following each 8 characters of output.

When you code the message text, you must code enough periods to allow for the blanks that will be substituted.

This substitution list is convenient for displaying CMS parameter lists. For example, to display a fileid in an FSCB, you might code

```
LINEDIT TEXT='FILEID IS',
SUB=(CHAR8A,OUTFILE+8)
```

where **OUTFILE** is the label on an FSCB macro. If the fileid for this file were **TEST OUTPUT A1**, then the **LINEDIT** macro would result in the display

```
FILEID IS TEST OUTPUT A1.
```

In the final edited line, multiple blanks are reduced to a single blank.

**CHAR8A, (reg)**  
 substitutes the character data at the address indicated in the specified register and inserts a blank character following each eight characters of output.

When you code the message text, you must include sufficient periods to allow for the blanks. For example,

```
LINEDIT TEXT='PLIST:',
SUB=(CHAR8A,(7))
```

results in a display of 4 doublewords of character data, beginning at the address indicated in register seven.

**SPECIFYING THE LENGTH FOR LINEDIT MACRO SUBSTITUTION:** In all the examples shown, the length of the argument being substituted was determined by the number of periods in the message text. The number of periods indicated the size of the output field, and indirectly determined the size of the input data area.

For hexadecimal and decimal substitutions, the input data is truncated on the left. To ensure that a decimal number will never be truncated, you can code 10 periods (11 for negative numbers) in the message text where it will be substituted. For hexadecimal data, code 8 periods to ensure that no characters are truncated when a fullword is substituted.

When you are coding substitution lists with the **CHARA**, **CHAR8A**, and **HEX4A** options, however, you can specify the length of the input data field. You must code the **SUB** operand as follows:

```
SUB=(type,(address,length))
```

## LINEDIT Macro

Both address and length may be specified using register notation. For example:

```
SUB=(HEX4A,(LOC,(4)))
```

In this example, the characters at location LOC are substituted into the message text; the number of characters is determined by the value contained in register 4, but it cannot be larger than the number of periods coded in the message text.

You can use this method in the special case where only 1 character is to be substituted. Since you must always code at least two periods to indicate that substitution is to be performed, you can code two periods and specify a length of one, as follows:

```
LINEDIT TEXT='ILLEGAL MODE LETTER ..',SUB=(CHARA,(PLIST+24,1))
```

**SPECIFYING MULTIPLE SUBSTITUTION LISTS:** When you want to make several substitutions in the same line, you must enter a substitution list for each set of periods in the message text. For example,

```
LINEDIT TEXT='VALUES ARE and',
SUB=(DEC,(3),HEXA,LOC)
```

might generate a line as follows:

```
VALUES ARE -45 AND FFE3C2.
```

You should remember, however, that if you are using the standard form of the macro, and you want to perform more than one substitution in a single line, the LINEDIT macro will not generate reentrant code. If you code RENT=NO on the macro line, then you will not receive the MNOTE message indicating that the code is non-reentrant. If you want reentrant code, you must use the list and execute forms of the macro.

### DISP Operand

Use the DISP operand to specify the output disposition of the edited line. The format of the DISP operand is:

```
DISP=(TYPE
 {
 NONE
 PRINT
 CPCOMM
 ERRMSG
 SIO
 })
```

#### where:

DISP=TYPE  
specifies that the message is to be displayed on the terminal.  
This is the default disposition.

DISP=NONE  
specifies that no output occurs. This option is useful with the BUFFA operand.

DISP=PRINT  
| specifies that the line is to be printed on the virtual printer.  
| The first character of the line is interpreted as a carriage  
| control character. (See the discussion of the PRINTL macro for a  
| list of valid ASA control characters.)

**DISP=CPCOMM**

specifies that the line is to be passed to CP to be executed as a CP command. For example,

LINEDIT TEXT='QUERY USERS',DOT=NO

results in the CP command line being passed to CP and executed.

**DISP=ERRMSG**

specifies that the line is to be checked to see if it qualifies for error message editing. If it does, it is displayed as an error message rather than as a regular line.

The standard format of VM/370 error messages is:

xxxxxxxxnns

where xxxmm is the name of the module issuing the message, nnn is the message number, and s is the severity code. You can code whatever you want for the first 9 characters of the code when you write error messages for your programs, but the tenth character must specify one of the following VM/370 message types:

| <u>Code</u> | <u>Message</u> | <u>Type</u> |
|-------------|----------------|-------------|
| I           | Information    |             |
| W           | Warning        |             |
| E           | Error          |             |

Then, the line is displayed in accordance with the CP EMSG setting. If EMSG is set to ON, then the entire message is displayed; if EMSG is set to TEXT, then only the message portion is displayed; if EMSG is set to CODE, then only the 10-character code is displayed.

**DISP=SIO**

specifies that the message is to be displayed, at the terminal, using SIO instead of TYPLIN, which is normally used. This option is used by CMS routines in cases where free storage pointers may be destroyed. Since lines are not stacked in the console buffer, no CONWAIT function is performed.

**BUFFA Operand**

Use the BUFFA operand to specify the address of a buffer into which the edited message is to be written. The message is copied into the indicated buffer, as well as being used as specified in the DISP operand. The format of the BUFFA operand is:

BUFFA={address }  
 {, (reg) }

When the text is copied into the buffer, the length of the message text is inserted into the first byte of the buffer, and the remainder of the text is inserted in subsequent bytes.

If you use register notation to indicate the buffer address, the code generated will not be reentrant. To suppress the MNOTE that informs you that code is not reentrant, use the RENT=NO operand.

## LINEDIT Macro

### MF Operand

Use the MF operand to specify the macro format when you want to code list and execute forms when you write reentrant programs. The format of the MF operand is:

$$MF = \left\{ \begin{array}{l} I \\ L \end{array} \right\} (E, \{ \text{addr} \} ) \left\{ \begin{array}{l} \\ (reg) \end{array} \right\}$$

#### where:

**MF=I** (Standard form)

generates an inline operand list for the LINEDIT macro, and calls the routine that displays the message. This is the default. It generates reentrant code, except under the following circumstances:

- When you specify more than one substitution list.
- When you use register notation with the TEXTA or BUFFA operands.

**MF=L** (List form)

generates a parameter list to be filled in when the execute form of the macro is used.

The size of the area reserved depends upon the number of substitutions to be made, which you can specify with the MAXSUBS operand. For example,

```
LINEDIT MF=L,MAXSUBS=5
```

reserves space for a parameter list which may hold up to five substitution lists. This same list may be used by several LINEDIT macros.

**MF=(E,address)** (Execute form)

generates code to fill in the parameter list at the specified address, and calls the routine that displays the message text.

The address specified (either a symbolic address or in register notation) indicates the location of the list form of the macro. The following example shows how you might use the list and execute forms of the LINEDIT macro to write reentrant code:

```
WRITETOT LINEDIT TEXT='SUBTOTAL TOTAL',
 SUB=(DEC,(4),DEC,(5)),MF=(E,LINELIST)
```

```
·
·
·
```

```
LINELIST LINEDIT MF=L,MAXSUBS=6
```

When the execute form of the LINEDIT macro is used, the parameter list for the message is built at label LINELIST, where the list form of the macro was coded.

### MAXSUBS Operand

Use the MAXSUBS operand when you code the list form (MF=L) form of the LINEDIT macro. The format of the MAXSUBS operand is:

```
MAXSUBS=number
```

where number specifies the maximum number of substitutions that will be made when the execute form of the macro is used.

### RENT Operand

Use the RENT operand when you are going to use the standard form of the LINEDIT macro and you do not care whether the code that is generated is reentrant. The format of the RENT operand is:

```
RENT={YES }
 {NO }
```

When RENT=YES (the default) is in effect, the LINEDIT macro expansion issues an MNOTE message indicating that nonreentrant code is being generated. This occurs when you use the standard form of the macro and you specify one of the following:

- TEXTA=(reg)
- BUFFA=(reg)
- More than one substitution pair

If you do not care whether the code is reentrant, and you do not wish to have the MNOTE appear, code RENT=NO. The RENT=NO coding merely suppresses the MNOTE statement; it has no effect on the expansion of the LINEDIT macro.

### **PRINTL**

Use the PRINTL macro to write a line to a virtual printer. The format of the PRINTL macro is:

```
[[label] | PRINTL | line [,length] [,ERROR=erraddr]]
```

#### where:

label is an optional statement label.

line specifies the line to be printed. It may be:

```
'linetext' text enclosed in quotation marks.
lineaddr the symbolic address of the line.
(reg) a register containing the address of the line.
```

length specifies the length of the line to be printed. (See Note 1.) It may be:

```
(reg) a register containing the length.
n a self-defining term indicating the length.
```

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

## PRINTL Macro

### Usage Notes

1. The maximum length allowed is 151 characters on a virtual 3211 or 133 characters on a virtual 1403. If you do not specify the length, it defaults to 133 characters, unless 'linetext' is specified. In this case, the length is taken from the length of the line text.
2. The first character of the line is interpreted as a carriage control character, which may be either ASA (ANSI) or machine code. The valid ASA control characters are:

| <u>Character</u> | <u>Hex Code</u> | <u>Meaning</u>                 |
|------------------|-----------------|--------------------------------|
| ␣                | 40              | Space 1 line before printing   |
| 0                | F0              | Space 2 lines before printing  |
| -                | 60              | Space 3 lines before printing  |
| +                | 4E              | Suppress space before printing |
| 1                | F1              | Skip to channel 1              |
| 2                | F2              | Skip to channel 2              |
| 3                | F3              | Skip to channel 3              |
| 4                | F4              | Skip to channel 4              |
| 5                | F5              | Skip to channel 5              |
| 6                | F6              | Skip to channel 6              |
| 7                | F7              | Skip to channel 7              |
| 8                | F8              | Skip to channel 8              |
| 9                | F9              | Skip to channel 9              |
| A                | C1              | Skip to channel 10             |
| B                | C2              | Skip to channel 11             |

3. Hex codes X'C1' and X'C3' are used in both machine code and ASA code. CMS recognizes these codes as ASA control characters, not as machine control characters.
4. If the line does not begin with a valid carriage control character, the line is printed with a write command to space one line before printing (ASA X'40').
5. When the macro completes, register 15 may contain a 2 or a 3, indicating that a channel 9 or channel 12 punch was sensed, respectively. You can use these codes to determine whether the end of the page is near (channel 9), or if the end of the page has been reached (channel 12). You might want to check for these codes if you want to print particular information at the bottom or at the end of each page being printed.

When the channel 9 or channel 12 punch is sensed, the write operation terminates after carriage spacing but before writing the line. If you want to write the line without additional space, you must modify the carriage control character in the buffer to a code that writes without spacing (ASA code + or machine code 01).

6. You must issue the CP CLOSE command to close the virtual printer file. Issue the CLOSE command either from your program (using an SVC 202 instruction or a LINEDIT macro) or from the CMS environment after your program completes execution. The printer is automatically closed when you log off or when you use the CMS PRINT command.

Error Conditions

If an error occurs register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                              |
|-------------|---------------------------------------------|
| 1           | Line too long                               |
| 2           | Channel 12 punch sensed (virtual 3211 only) |
| 3           | Channel 9 punch sensed (virtual 3211 only)  |
| 4           | Intervention required                       |
| 5           | Unknown error                               |
| 100         | Printer not attached.                       |

**PUNCHC**

Use the PUNCHC macro to write a line to a virtual card punch. The format of the PUNCHC macro is:

```
[label] | PUNCHC| line [,ERROR=erraddr]
```

where:

label is an optional statement label.

line specifies the line to be punched. It may be:

'linetext' text enclosed in quotation marks.  
 lineaddr the symbolic address of the line.  
 (reg) a register containing the address of the line.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. No stacker selecting is allowed. The line length must be 80 characters.
2. You must issue the CP CLOSE command to close the virtual punch file. Issue the CLOSE command either from your program (using an SVC 202 instruction) or from the CMS environment when your program completes execution. The punch is closed automatically when you log off or when you use the CMS PUNCH command.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>     |
|-------------|--------------------|
| 2           | Unit check         |
| 3           | Unknown error      |
| 100         | Punch not attached |

**RDCARD**

Use the RDCARD macro to read a line from a virtual card reader. The format of the RDCARD macro is:

```
[[label] | RDCARD | buffer[,length][,ERROR=erraddr]
```

where:

**label** is an optional statement label.

**buffer** specifies the buffer address into which the card is to be read. It may be:

**bufaddr** the symbolic address of the buffer.  
(reg) a register containing the address of the buffer.

**length** specifies the length of card to be read. If omitted, 80 is assumed. The length may be specified in one of two ways:

**n** a self-defining term indicating the length.  
(reg) a register containing the length.

**ERROR=erraddr** specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

Usage Notes

1. No stacker selecting is allowed.
2. When the macro completes, register 0 contains the length of the card that was read.

Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                       |
|-------------|--------------------------------------|
| 1           | End-of-file                          |
| 2           | Unit check                           |
| 3           | Unknown error                        |
| 5           | Length not equal to requested length |
| 100         | Device not attached                  |



**RDTAPE**

Use the RDTAPE macro to read a record from the specified tape drive. The format of the RDTAPE macro is:

```
[[label] | RDTAPE | buffer,length [,device] [,MODE=mode]
| | | [,ERROR=erradr]
```

where:

- label** is an optional statement label.
- buffer** specifies the buffer address into which the record is to be read. It may be specified in either of two ways:
- lineaddr** the symbolic address of the buffer.  
**(reg)** a register containing the address of the buffer.
- length** specifies the length of the largest record to be read. A 65,535-byte record is the largest record that can be read. It may be specified in either of two ways:
- n** a self-defining term indicating the length.  
**(reg)** a register containing the length.
- device** specifies the device from which the line is to be read. If omitted, TAP1 (virtual address 181) is assumed. It may be specified in either of two ways:
- TAPn** indicates the symbolic tape number (TAP1 through TAP4).  
**cuu** indicates the virtual device address.
- MODE=mode** specifies the number of tracks, density, and tape recording technique options. It must be in the following form:
- ([track],[density],[trtch])
- track** 7 indicates a 7-track tape (implies density=800 and trtch=0).  
9 indicates a 9-track tape (implies density=800).
- density** 200, 556, or 800 for a 7-track tape.  
800, 1600, or 6250 for a 9-track tape.
- trtch** indicates the tape recording technique for 7-track tape. One of the following must be specified:
- 0 - odd parity, converter off, translator off.  
OC - odd parity, converter on, translator off.  
OT - odd parity, converter off, translator on.  
E - even parity, converter off, translator off.  
ET - even parity, converter off, translator on.
- ERROR=erraddr** specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.



**LENGTH=length**  
 specifies the length of the buffer. If not specified, 130 is assumed. When EDIT=PHYS, as many as 2030 bytes may be read.

**ATTREST=YES|NO**  
 specifies whether an attention interrupt during a read should result in a restart of the read operation. (See Note 2.)

#### Usage Notes

1. When the macro completes, register 0 contains the number of characters read.
2. You can use ATTREST only when you are reading physical lines (EDIT=PHYS) and you specify an explicit length of the line. When ATTREST=NO, an attention interrupt during a read operation signals the end of the line and does not result in a restart of the read. These operands are used primarily in writing VS APL programs.
3. You may wish to use the WAITT macro to ensure that terminal I/O is completed before you modify or use the read buffer.

#### Error Conditions

When an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                                                              |
|-------------|-----------------------------------------------------------------------------|
| 2           | Invalid parameter                                                           |
| 4           | Read was terminated by an attention signal (Possible only when ATTREST=NO.) |

## REGEQU

Use the REGEQU macro to generate a list of EQU (equate) statements to assign symbolic names for the general, floating-point, and extended control registers. The format of the REGEQU macro is:

```

|-----|
REGEQU

```

## REG EQU, TAPECTL Macros

### Usage Notes

1. The REG EQU macro causes the following equate statements to be generated:

| <u>General Registers</u> |     |    | <u>Extended Control Registers</u> |     |    |
|--------------------------|-----|----|-----------------------------------|-----|----|
| R1                       | EQU | 1  | C0                                | EQU | 0  |
| R1                       | EQU | 1  | C1                                | EQU | 1  |
| R2                       | EQU | 2  | C2                                | EQU | 2  |
| R3                       | EQU | 3  | C3                                | EQU | 3  |
| R4                       | EQU | 4  | C4                                | EQU | 4  |
| R5                       | EQU | 5  | C5                                | EQU | 5  |
| R6                       | EQU | 6  | C6                                | EQU | 6  |
| R7                       | EQU | 7  | C7                                | EQU | 7  |
| R8                       | EQU | 8  | C8                                | EQU | 8  |
| R9                       | EQU | 9  | C9                                | EQU | 9  |
| R10                      | EQU | 10 | C10                               | EQU | 10 |
| R11                      | EQU | 11 | C11                               | EQU | 11 |
| R12                      | EQU | 12 | C12                               | EQU | 12 |
| R13                      | EQU | 13 | C13                               | EQU | 13 |
| R14                      | EQU | 14 | C14                               | EQU | 14 |
| R15                      | EQU | 15 | C15                               | EQU | 15 |

| <u>Floating-Point Registers</u> |     |   |
|---------------------------------|-----|---|
| F0                              | EQU | 0 |
| F2                              | EQU | 2 |
| F4                              | EQU | 4 |
| F6                              | EQU | 6 |

## TAPECTL

Use the TAPECTL macro to position the specified tape according to the specified function code. The format of the TAPECTL macro is:

```
[[label] | TAPECTL | function [,device][,MODE=mode][,ERROR=erraddr] |
```

### where:

label is an optional statement label.

function specifies the control function to be performed. It must be one of the following codes:

| <u>Code</u> | <u>Function</u>            |
|-------------|----------------------------|
| REW         | Rewind the tape            |
| RUN         | Rewind and unload the tape |
| ERG         | Erase a gap                |
| BSR         | Backspace one record       |
| BSF         | Backspace one file         |
| FSR         | Forward space one record   |
| FSF         | Forward space one file     |
| WTM         | Write a tape mark          |

device specifies the tape on which the control operation is to be performed. If omitted, TAP1 (virtual address 181) is assumed. It may be:

TAPn indicates the symbolic tape number (TAP1 through TAP4).

cuu indicates the virtual device address.

MODE=mode specifies the number of tracks, density, and tape recording technique options. It must be in the following form:

(( [track],[density],[trtch] ))

track 7 indicates a 7-track tape (implies density=800 and trtch=0).

9 indicates a 9-track tape (implies density=800).

density 200, 556, or 800 for a 7-track tape.  
800, 1600, or 6250 for a 9-track tape.

trtch indicates the tape recording technique for 7-track tape. One of the following must be specified:

O - odd parity, converter off, translator off.

OC - odd parity, converter on, translator off.

OT - odd parity, converter off, translator on.

E - even parity, converter off, translator off.

ET - even parity, converter off, translator on.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

#### Usage Notes

1. You do not need to specify MODE when you are manipulating a 9-track tape and you are using the default density for the tape drive, nor when you are writing a 7-track tape with a density of 800 bpi, odd parity, with data convertor and translator off.

#### Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                      |
|-------------|-------------------------------------|
| 1           | Invalid function or parameter list. |
| 2           | End-of-file or end-of-tape          |
| 3           | Permanent I/O error                 |
| 4           | Invalid device id                   |
| 5           | Tape is not attached                |
| 6           | Tape is file protected              |

## WAITD

Use the WAITD macro to cause the program to wait until the next interrupt occurs on the specified device. The format of the WAITD macro is:

```
[[label] | WAITD | device...[,devicen] [,ERROR=erraddr]]
```

### where:

label is an optional statement label.

devicen specifies the device(s) to be waited for. One of the following may be specified:

symn indicates the symbolic device name and number, where:

sym is CON, DSK, PRT, PUN, RDR, or TAP.  
n indicates a device number.

user is a 4-character symbolic name specified a HNDINT macro issued for the same device.

ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

### Usage Notes

1. Use the WAITD macro to ensure completion of an I/O operation. If an interrupt has been received and not processed from a device specified in the WAITD macro the interrupt is processed before program execution continues.
2. When the interrupt has been completely processed, control is returned to the caller with the name of the interrupting device in register 1.
3. If an HNDINT macro issued for the same device specified ASAP and an interrupt has already been processed for the device, the wait condition is satisfied.
4. If an HNDINT macro issued for the same device specified WAIT and an interrupt for the device has been received, the interrupt handling routine is given control.
5. The interrupt routine determines if an interrupt is considered processed or if more interrupts are necessary to satisfy the wait condition. For additional information see the discussion of the HNDINT macro.

### Error Conditions

When an error is detected, register 15 contains a 1 to indicate that an invalid device number was specified.

## WAITT

Use the WAITT macro to cause the program to wait until all of the pending terminal I/O is complete. The format of the WAITT macro is:

```
[[label] | WAITT |
```

where:

label is an optional statement label.

Usage Notes

1. The WAITT macro synchronizes input and output to the terminal; it ensures that the console stack is cleared before the program continues execution. Also, you can ensure that a read or write operation is finished before you modify an I/O buffer.

## WRTAPE

Use the WRTAPE macro to write a record on the specified tape drive. The format of the WRTAPE macro is:

```
[[label] | WRTAPE | buffer,length [,device] [,MODE=mode] |
| | | [,ERROR=erraddr]
```

where:

label is an optional statement label.

buffer specifies the address of the record to be written. It may be:  
 lineaddr the symbolic address of the line.  
 (reg) a register containing the address of the time.

length specifies the length of the line to be written. It may be specified in either of two ways:

n a self-defining term indicating the length.  
 (reg) a register containing the length.

device specifies the device to which the record is to be written. If omitted, TAP1 (virtual address 181) is assumed. It may be:

TAPn indicates the symbolic tape number (TAP1 through TAP4).  
 cuu indicates the virtual device address.

MODE=mode specifies the number of tracks, density, and tape recording technique. It must be in the following form:

([track],[density],[trtch])

track 7 indicates a 7-track tape (implies density=800 and trtch=0).  
 9 indicates a 9-track tape (implies density=800).

## WRTAPE Macro

| density 200, 556, or 800 for a 7-track tape  
| 800, 1600, or 6250 for a 9-track tape.

trtch indicates the tape recording technique for 7-track tape. One of the following must be specified:

- O - odd parity, converter off, translator off.
- OC - odd parity, converter on, translator off.
- OT - odd parity, converter off, translator on.
- E - even parity, converter off, translator off.
- ET - even parity, converter off, translator on.

### ERROR=erraddr

specifies the address of an error routine to be given control if an error is found. If ERROR= is not coded and an error occurs, control returns to the next sequential instruction in the calling program, as it does if no error occurs.

### Usage Notes

1. You do not need to specify the MODE option if you are writing to a 9-track tape and want to use the default density, nor if you are writing to a 7-track tape with a density of 800 bpi, odd parity, with data convertor and translator off.

### Error Conditions

If an error occurs, register 15 contains one of the following error codes:

| <u>Code</u> | <u>Meaning</u>                     |
|-------------|------------------------------------|
| 1           | Invalid function or parameter list |
| 2           | End-of-file or end-of-tape         |
| 3           | Permanent I/O error                |
| 4           | Invalid device identification      |
| 5           | Tape not attached                  |
| 6           | Tape is file protected             |



**WRTERM**

Use the WRTERM macro to display a line at the terminal. The format of the WRTERM macro is:

```
[[label] | WRTERM | line [,length] [,EDIT=code] [,COLOR=color]]
```

where:

label is an optional statement label.

line specifies the line to be displayed. It may be one of three forms:

'linetext' the actual text line enclosed in quotation marks.  
 lineaddr the label on the statement containing the line.  
 (reg) a register containing the address of the line.

length specifies the length of the line. If the line is specified within quotation marks in the macro, the length operand may be omitted. The length may be specified in either of two ways:

n a self-defining term indicating the length.  
 (reg) a register containing the length.

EDIT=code specifies whether the line is to be edited:

| YES indicates that trailing blanks are to be removed and a  
 | carriage return added to the end of the line. YES is the  
 | default value.

NO indicates that trailing blanks are not to be removed and no carriage return is to be added.

LONG indicates the line may exceed 130 bytes, and is to be transmitted from the caller's buffer area. No editing is performed.

COLOR=color

indicates the color in which the line is to be typed, if the typewriter terminal has a two-color ribbon:

| B indicates that the line is to be typed in black. This is  
 | the default.

R indicates that the line is to be typed in red.

Usage Notes

1. The maximum line length is 130 characters for a black line and 126 characters for a red line.
2. If EDIT=LONG, COLOR must be specified as 'B'. In this case, you may write as many as 1760 bytes with a single WRTERM macro. You are responsible for embedding the proper terminal control characters in the data, and for the integrity of the data from issuance of WRTERM until the data has been sent. (This operand is for use primarily with VS APL programs.)
3. You may want to use the WAITT macro to ensure that terminal I/O is complete before continuing program execution.



# Appendixes

The following appendixes are provided for your convenience:

Appendix A: Reserved Filetype Defaults

Appendix B: DOS/VS Access Method Services and VSAM Functions Not Supported In CMS

Appendix C: OS/VS Access Method Services and VSAM Functions Not Supported In CMS



## Appendix A: Reserved Filetype Defaults

| Filetype                                                                                  | RECFM | LRCL | ZONE | TRUNC | VERIFY | SERIAL | TABS                                                              | Usage                                                        |
|-------------------------------------------------------------------------------------------|-------|------|------|-------|--------|--------|-------------------------------------------------------------------|--------------------------------------------------------------|
| default                                                                                   | F     | 80   | 1 *  | *     | 1 *    | OFF    | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71,81<br>91,101,111,121,131 | All other filetypes                                          |
| AMSERV                                                                                    | F     | 80   | 2 72 | 72    | 1 72   | OFF    | 2,6,11,16,21,26,31,<br>36,41,46,51,61,71,80                       | Input Control statements for<br>Access Method Services       |
| ASSEMBLE                                                                                  | F     | 80   | 1 71 | 71    | 1 72   | ON     | 1,10,16,31,36,41,46,<br>69,72,80                                  | Assembler language source<br>statements.                     |
| BASIC<br>BASDATA                                                                          | F     | 80   | 7 *  | *     | 1 *    | L/L    | 7,10,15,20,25,30,80                                               | BASIC source statements; and<br>execution-time files.        |
| COBOL                                                                                     | F     | 80   | 1 72 | 72    | 1 72   | ON     | 1,8,12,20,28,36,44,<br>68,72,80                                   | COBOL source statements.                                     |
| DIRECT                                                                                    | F     | 80   | 1 72 | 72    | 1 72   | ON     | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71                          | VM/370 user directory entries.                               |
| EXEC                                                                                      | V     | 80   | 1 *  | *     | 1 *    | OFF    | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71                          | EXEC procedures.                                             |
| FREEFORT                                                                                  | V     | 81   | 9 *  | *     | 1 *    | L/L    | 9,15,18,23,28,33,38,<br>81                                        | FREEFORM FORTRAN source<br>statements.                       |
| FORTRAN                                                                                   | F     | 80   | 1 72 | 72    | 1 72   | ON     | 1,7,10,15,20,25,30,80                                             | FORTRAN source statements.                                   |
| LISTING                                                                                   | V     | 121  | 1 *  | *     | 1 *    | OFF    | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71,81<br>91,101,111,121,131 | Command, program, and compiler<br>listings.                  |
| MACRO                                                                                     | F     | 80   | 1 71 | 71    | 72     | ON     | 1,10,16,31,36,41,46,<br>69,72,80                                  | Macro definitions.                                           |
| MEMO                                                                                      | F     | 80   | 1 *  | *     | 1 *    | OFF    | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71                          | Documentation. (Default CASE<br>value is M.)                 |
| PLI<br>PLIOPT                                                                             | F     | 80   | 2 72 | 72    | 1 72   | ON     | 2,4,7,10,13,16,19,22,<br>25,31,37,43,49,55,<br>79,80              | PL/I Source statements.                                      |
| SCRIPT                                                                                    | V     | 132  | 1 *  | *     | 1 *    | OFF    | (IMAGE setting is<br>CANON.)                                      | SCRIPT text processor input.<br>(Default CASE setting is M.) |
| UPDATE                                                                                    | F     | 80   | 1 71 | 71    | 72     | ON     | 1,10,16,31,36,41,46,<br>69,72,80                                  | Update files for assembler<br>language programs.             |
| UPDTxxxx                                                                                  | F     | 80   | 1 71 | 71    | 72     | ON     | 1,10,16,31,36,41,46,<br>69,72,80                                  | Update files for assembler<br>language programs.             |
| VS BASIC                                                                                  | F     | 80   | 7 *  | *     | 1 *    | L/L    | 7,10,15,20,25,30,80                                               | VS BASIC source statements.                                  |
| VS BDATA                                                                                  | V     | 132  | 1 *  | *     | 1 *    | OFF    | 1,6,11,16,21,26,31,<br>36,41,46,51,61,71,<br>81...131             | VS BASIC execution-time files.                               |
| * indicates that the ZONE, TRUNC, or VERIFY setting is equal to the current record length |       |      |      |       |        |        |                                                                   |                                                              |
| L/L indicates that the LINEMODE setting is LEFT, with serial numbers on the left.         |       |      |      |       |        |        |                                                                   |                                                              |

Figure 19. Default EDIT Subcommand Settings for CMS Reserved Filetypes



## Appendix B: DOS/VS Access Method Services and VSAM Functions Not Supported in CMS

Refer to the DOS/VS Utilities Access Method Services, GC33-5382, for a description of Access Method Services functions available under DOS/VS, and, therefore, under CMS. This knowledge of Access Method Services is assumed throughout this publication.

All of the DOS/VS Access Method Services are supported by CMS, except for the following:

- Non-VSAM data sets with data formats that are not supported by CMS/DOS (for example, BDAM and ISAM files are not supported).
- The SHAREOPTIONS operand has no function in CMS. However, you should specify SHAREOPTIONS 3 in your DEFINE control statement for more efficient operations. When you specify SHAREOPTIONS 3, CMS does not execute the code that attempts to reserve and release system resources.





## Appendix C: OS/VS Access Method Services and VSAM Functions Not Supported in CMS

In CMS, an OS user is defined as a user that has not issued the command:

```
SET DOS ON (VSAM)
```

OS users can use all of the Access Method Services functions that are supported by DOS/VS, with the following exceptions:

- Non-VSAM data sets with data formats that are not supported by CMS/DOS (for example, BDAM and ISAM files are not supported).
- The SHAREOPTIONS operand has no function in CMS. However, you should specify SHAREOPTIONS 3 in your DEFINE control statement for more efficient operation. When you specify SHAREOPTIONS 3, CMS does not execute the code that attempts to reserve and release system resources.
- Do not use the AUTHORIZATION (entrypoint) operand in the DEFINE and ALTER commands unless your own authorization routine exists on the DOS core image library, the private core image library, or in a CMS DOSLIB file. In addition, results are unpredictable if your authorization routine issues an OS SVC instruction.
- Unlike OS, CMS Access Method Services supports the 3330-11 as a virtual 3330-1; only a maximum of 404 cylinders are used.
- The secondary space allocation parameter in the following DEFINE commands is not used by Access Method Services or DOS/VS VSAM: DEFINE SPACE, DEFINE USERCATALOG, and DEFINE CLUSTER with the UNIQUE parameter. However, you may code this parameter to make your control statement file compatible with an OS/VS VSAM control file.
- The OS Access Method Services GRAPHICS TABLE options and the TEST option of the PARM command are not supported.
- The filename in the FILE (filename) operands is limited to 7 characters. If an eighth character is specified, it is ignored.
- The OS Access Method Services CNVTCAT and CHKLIST commands are not supported in DOS/VS Access Method Services. In addition, all OS Access Method Services commands that support the 3850 Mass Storage System are not supported in DOS/VS Access Method Services.
- Figure 20 is a list of OS operands, by control statement, that are not supported by the CMS interface to DOS/VS Access Method Services.

If any of the unsupported operands or commands in Figure 20 are specified, the AMSERV command terminates and displays an appropriate error message.

When you use the PRINT, EXPORT, IMPORT, IMPORTRA, EXPORTRA, and REPRO control statements for sequential access method (SAM) data sets, you must specify the ENVIRONMENT operand with the required DOS options (that is, PRIME DATA DEVICE, BLOCKSIZE, RECORDSIZE, or RECORDFORMAT). You must have previously issued a DLBL for the SAM file.

AMSERV can write SAM data sets only to a CMS disk, but can read them from DOS, OS, or CMS disks.

| OS Access Method Services Control Statement | Operands not supported in CMS                                                                                                                                         |
|---------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ALTER                                       | EMPTY/NOEMPTY<br>SCRATCH/NOSCRATCH<br>DESTAGEWAIT/NODESTAGEWAIT<br>STAGE/BIND/CYLINDERFAULT                                                                           |
| BLDINDEX                                    | INDATASET<br>OUTDATASET                                                                                                                                               |
| DEFINE                                      | ALIAS<br>EMPTY/NOEMPTY<br>GENERATIONDATAGROUP<br>PAGESPACE<br>SCRATCH/NOSCRATCH<br>DESTAGEWAIT/NODESTAGEWAIT<br>STAGE/BIND/CYLINDERFAULT<br>TO/FOR/OWNER <sup>1</sup> |
| DELETE                                      | ALIAS<br>GENERATIONDATAGROUP<br>PAGESPACE<br>SCRATCH/NOSCRATCH                                                                                                        |
| EXPORT                                      | OUTDATASET                                                                                                                                                            |
| IMPORT                                      | INDATASET<br>OUTDATASET<br>IMPORTA                                                                                                                                    |
| LISTCAT                                     | ALIAS<br>GENERATIONDATAGROUP<br>LEVEL<br>OUTFILE <sup>2</sup><br>PAGESPACE                                                                                            |
| PRINT                                       | INDATASET<br>OUTFILE <sup>2</sup>                                                                                                                                     |
| REPRO                                       | INDATASET<br>OUTDATASET                                                                                                                                               |
| VERIFY                                      | DATASET                                                                                                                                                               |

<sup>1</sup>The TO/FOR/OWNER operands are supported for the Access Method Services interface, but are not supported for the DEFINE NONVSAM control statement.

<sup>2</sup>The OUTFILE operand is supported by the Access Method Services interface, but is not supported for the LISTCAT and PRINT control statements.

Figure 20. OS Access Method Services Operands Not Supported in CMS

# Index

- &\$ special variable 299
  - in &IF control statement 288
  - setting 279
- &\* special variable 299
  - in &IF control statement 288
  - setting 279
- &ARGS control statement, description 279
- &BEGMSG control statement
  - ALL operand 280
  - description 279
- &BEGPUNCH control statement
  - ALL operand 281
  - description 281
- &BEGSTACK control statement
  - ALL operand 281
  - description 281
  - FIFO operand 281
  - LIFO operand 281
- &BEGTYPE control statement
  - ALL operand 282
  - description 282
- &CONCAT built-in function, description 297
- &CONTINUE control statement 282
  - used with &ERROR control statement 285
- &CONTROL control statement
  - ALL operand 283
  - CMS operand 283
  - description 283
  - ERROR operand 283
  - MSG operand 283
  - NOMSG operand 283
  - NOPACK operand 283
  - NOTIME operand 283
  - OFF operand 283
  - PACK operand 283
  - TIME operand 283
- &DATATYPE built-in function, description 297
- &DISK\* special variable 300
- &DISK? special variable 300
- &DISKx special variable 299
- &DOS special variable 300
- &EMSG control statement, description 284
- &END control statement 285
  - with &BEGMSG control statement 279
  - with &BEGPUNCH control statement 281
  - with &BEGSTACK control statement 281
  - with &BEGTYPE control statement 282
- &ERROR control statement, description 285
- &EXEC special variable 300
- &EXIT control statement, description 286
- &GLOBAL special variable 300
- &GLOBALn special variable 301
- &GOTO control statement
  - description 287
  - TOP operand 287
- &HEX control statement
  - description 287
  - OFF operand 287
  - ON operand 287
- &IF control statement, description 288
- &INDEX special variable 301
  - setting 279,291
- &LENGTH built-in function, description 297
- &LINENUM special variable 301
- &LITERAL built-in function, description 298
- &LOOP control statement, description 289
- &n special variable 299
- &PUNCH control statement, description 290
- &READ control statement
  - ARGS operand 291
  - description 291
  - VARS operand 291
- &READFLAG special variable 301
  - testing 291
- &RETCODE special variable 301
- &SKIP control statement, description 291
- &SPACE control statement, description 292
- &STACK control statement
  - description 293
  - FIFO operand 293
  - LIFO operand 293
- &SUBSTR built-in function, description 298
- &TIME control statement
  - description 294
  - OFF operand 294
  - ON operand 294
  - RESET operand 294
  - TYPE operand 294
- &TYPE control statement, description 295
- &TYPEFLAG special variable 301
- &0 special variable 299
  
- \$DUP edit macro 261
- \$LISTIO EXEC file
  - creating 123
  - format 123
- \$MOVE edit macro 262
  - DOWN operand 262
  - TO operand 262
  - UP operand 262
  
- \* (asterisk)
  - entered in fileid 15
  - in ACCESS command 26
  - in ALTER subcommand 220
  - in CHANGE subcommand 224
  - in COPYFILE command 43
    - examples 47
  - in DELETE subcommand 227
  - in DLBL command 68
  - in DSERV command 84
  - in EDIT command 86
  - in FILEDEF command 96
  - in GETFILE subcommand 233
  - in LISTDS command 116
  - in LISTFILE command 121
  - in PRINT command 144
  - in PUNCH command 149
  - in READCARD command 160
  - in RENAME command 164
  - in SCROLL/SCROLLUP subcommand 249
  - in START command 179

in STATE and STATEW commands 180  
 in TAPPDS command 197  
 in TRUNC subcommand 253  
 in TYPE subcommand 254  
 in VERIFY subcommand 256  
 in ZONE subcommand 258  
 with DISK operand, of CMS QUERY command 156  
 with REPEAT subcommand 244  
 with RESET option  
     of INCLUDE command 113  
     of LOAD command 125  
 \* (comment) command 13  
 \*COPY statement 136

/ (diagonal), used in ACCESS command 26

./ \* (comments) UPDATE control statement 209  
 ./ D (DELETE) UPDATE control statement 208  
 ./ I (INSERT) update control statement 207  
 ./ S (SEQUENCE) UPDATE control statement 206  
 ./ R (REPLACE) UPDATE control statement 208

%, used to pass a null argument to an EXEC procedure 299

?  
     subcommand, description 259  
     used with DSN operand of DLBL command 69  
     used with the FILEDEF DISK operand 101

= (equal sign)  
     in COPYFILE command 43  
         examples 46,47  
     in RENAME command 165  
 = subcommand (see REUSE subcommand)

**A**  
 A operand of LISTIO command 123  
 ABBREV operand  
     of CMS QUERY command 153  
     of CMS SET command 172  
     relationship to SYNONYM command 189  
 abbreviating commands 14  
 abbreviations  
     determine whether abbreviations are accepted for command names 153  
     for CMS and user-written command names 172,187  
     make command abbreviations acceptable as input 172  
     make command abbreviations unacceptable as input 172  
     used with synonyms 189  
 abnormal termination (abend)  
     effect on DLBL definitions 69  
     effect on FILEDEF definitions 100  
     entering debug environment after 263  
 ACCESS command  
     description 26  
     ERASE option 26,27  
     examples 27  
     first command after IPL 26  
     NODISK option 26  
     NOPROF option 26  
 Access Method Services  
     allocating VSAM space 75  
     allocating VSAM space in CMS/DOS 72  
     control statements, operands not supported in CMS (OS users) 348  
     determine free space extents for 117  
     invoking in CMS 29  
     LISTING file created by 29  
     restrictions  
         for DOS/VS users 345  
         for OS/VS users 347  
 accessing  
     CMS files, FSREAD macro 309  
     CMS with no virtual disks attached to your virtual machine 26  
     disks, after the LINK command 27  
     only particular files on a disk 27  
     OS and DOS disks 28  
     virtual disks 26  
 ADD operand  
     of the MACLIB command 135  
     of TXTLIB command 200  
 adding  
     a member to a TXTLIB 200  
     members to a macro library 135  
     phases to a DOSLIB 82  
 A-disk, accessed after IPLing CMS 27  
 ALIGN option, of ASSEMBLE command 35  
 alignment of boundaries in assembler program statements 35  
**ALL**  
     operand  
         of &BEGMSG control statement 280  
         of &BEGPUNCH control statement 281  
         of &BEGSTACK control statement 281  
         of &BEGTYPE control statement 282  
         of &CONTROL control statement 283  
         of LISTIO command 123  
         of SERIAL subcommand 250  
         option, of GENMOD command 109  
 ALLOC option, of LISTFILE command 121  
 ALOGIC option, of ASSEMBLE command 33  
**ALTER** subcommand  
     description 220  
     effect of zone setting 258  
 altering  
     characters in a CMS file  
         with the ALTER subcommand 220  
         with the CHANGE subcommand 223  
         with the COPYFILE command 51  
     constants, with LOAD command 132  
     instructions, with LOAD command 132  
**AMSERV**  
     command  
         description 29  
         LISTING file 29  
         PRINT option 29  
         TAPIN option 29  
         TAPOUT option 29

filetype 30  
    default editor settings 343  
annotating, console sheet 13  
APPEND option  
    of COPYFILE command 45  
    of LISTFILE command 121  
    of LISTIO command 123  
appending  
    information to \$LISTIO EXEC 123  
    information to a CMS EXEC file 121  
    one file to another 45  
ARGS operand of &READ control statement  
291  
arguments  
    in an EXEC procedure 279  
    reading from the terminal or console  
    stack 291  
    testing how many were passed 301  
    on the RUN command 168  
    on the START command 179  
    passed to an EXEC procedure 92  
arrange, records in a file in EBCDIC  
sequence 175  
ASA carriage control characters 328  
ASAP operand of HNDINT macro 315  
ASSEMBLE  
    assembler input ddname 36  
    command 11  
        ALIGN option 35  
        ALOGIC option 33  
        BUFSIZE option 35  
        DECK option 34  
        description 32  
        DISK option 34  
        ESD option 33  
        FLAG option 33  
        LIBMAC option 33  
        LINECOUN option 33  
        LIST option 33  
        listing control options for 33  
        MCALL option 33  
        MLOGIC option 33  
        NOALIGN option 35  
        NOALOGIC option 33  
        NODECK option 34  
        NOESD option 33  
        NOLIBMAC option 33  
        NOLIST option 33  
        NOMCALL option 33  
        NOMLOGIC option 33  
        NONUM option 34  
        NOOBJECT option 34  
        NOPRINT option 34  
        NORENT option 35  
        NORLD option 33  
        NOSTMT option 34  
        NOTERM option 35  
        NOXREF option 34  
        NUMBER option 34  
        OBJECT option 34  
        PRINT option 34  
        RENT option 35  
        RLD option 33  
        STMT option 34  
        SYSPARM option 35  
        SYSTEM listing 34  
        TERMINAL option 34  
        TEST option 34  
        XREF option 33  
filetype  
    created by TAPPDS command 197  
    default editor settings 343  
    used as input to the assembler 32  
ASSEMBLE command  
    NOTEEST option 34  
    NOYFLAG option 35  
    YFLAG option 35  
assembler  
    conditional assembly statements, listing  
    33  
    overriding CMS file defaults 36  
    using under CMS 11,32  
assembling  
    source files  
        identifying macro libraries 36,111  
ASSGN command  
    DEN option 38  
    description 37  
    IGN operand 37  
    LOWCASE option 38  
    PRINTER operand 37  
    PUNCH operand 37  
    READER operand 37  
    SYSxxx operand 37  
    TAPn operand 37  
    TERMINAL operand 37  
    TRTCH option 38  
    UPCASE option 38  
    7TRACK option 38  
    9TRACK option 38  
assigning  
    logical units in CMS/DOS 37  
    symbolic names, to storage locations in  
    the debug environment 267  
    values to variable symbols, in EXEC  
    procedures 278  
assignment statement 278  
assignments  
    logical unit, listing 123  
    system and programmer, unassigning 162  
attention interrupt, causing 19  
ATTREST operand of RDTERM macro 333  
AUTO option  
    of INCLUDE command 114  
    of LOAD command 126  
automatic read function, setting 172  
automatic save function of the CMS Editor  
221  
AUTOREAD operand, of CMS SET command 172  
AUTOSAVE subcommand  
    description 221  
    OFF operand 221  
auxiliary directory, creating 107  
AUXPROC, option of FILEDEF command 100  
  
B  
backspace  
    characters, how the editor handles 235  
    key, used with OVERLAY subcommand 240  
backward space a tape 191  
BACKWARD subcommand, description 222  
BASDATA filetype, default editor settings  
343

base address, for debugging, set with  
 ORIGIN subcommand 271

BASIC filetype, default editor settings  
 343

BCD characters, converting to EBCDIC 45

BDAM files, specifying in CMS 97

beginning  
 character string on a line, locating a  
 line by 229  
 program execution  
 in CMS/DOS 94  
 with the INCLUDE command 114  
 with the LOAD command 126

blank lines, displaying at the terminal  
 during EXEC processing 292

blanks  
 as delimiters 12  
 FIND subcommand 229  
 displaying in LINEDIT message text 319  
 overlaying characters with 240  
 trailing  
 removing with WRTERM macro 339  
 truncating from variable-length file  
 242

blip  
 characters  
 for virtual machine 170  
 for virtual machine, displaying 152  
 function  
 query the setting of 152  
 setting 170

BLIP operand  
 of CMS QUERY command 152  
 of CMS SET command 170

BLKSIZE option, of FILEDEF command 98

BLOCK option, of FILEDEF command 98

blocking CMS files 98  
 FSWRITE macro 313

blocksize, specifying with FILEDEF command  
 100

books, from DOS/VS source statement  
 libraries, copying 177

BOTTOM subcommand, description 222

boundary alignment, of statements in an  
 assembler program 35

branching  
 in an EXEC procedure  
 &GOTO control statement 287  
 &SKIP control statement 292

BREAK subcommand, description 264

breakpoints, setting 264

BSF, tape control function 191

BSIZE operand, of FSCB macro 304

BSR, tape control function 191

BUFFA operand, of LINEDIT macro 325

buffer  
 specifying for RDTERM macro 332  
 specifying for read/write operations,  
 FSCB macro 304  
 to copy LINEDIT message text 325

BUFFER operand, of FSCB macro 304

buffer size  
 assembler, controlling size of 35  
 for VSAM programs 70  
 specifying, FSCB macro 304

BUFSIZE option, of ASSEMBLE command 35

BUFSP option, of DLBL command 70

built-in functions, EXEC 296

C

canceling  
 automatic save function of the editor  
 221  
 changes made during edit session 242  
 system and programmer logical unit  
 assignments in CMS/DOS 38

CANON operand, of IMAGE subcommand 234

card reader  
 reading files from, READCARD command  
 159  
 reading records from, RDCARD macro 330

carriage control characters  
 ASA, summary 328  
 handling by PRINT command 144,145  
 machine code 328

CASE subcommand  
 description 223  
 M operand 223  
 U operand 223

CAT option of DLBL command 70  
 example of usage 77  
 example of usage in CMS/DOS 74

catalogs (see VSAM catalogs)

CAW  
 operand of SET subcommand 273  
 subcommand, description 265

CAW (Channel Address Word)  
 changing in the debug environment 273  
 displaying in debug environment 265  
 format 265

CC option, of PRINT command 144

CD operand, of DSERV command 84

CHANGE  
 option, of FILEDEF command 98  
 option of DLBL command 69  
 subcommand  
 description 223  
 effect of zone setting 258

changing  
 CAW (Channel Address Word), in debug  
 environment 273  
 CSW (Channel Status Word), in debug  
 environment 273  
 file identifier  
 on SAVE subcommand 248  
 with the FILE subcommand 229  
 with the RENAME command 164  
 filemode of a file, with the FMODE  
 subcommand 230  
 filename of a file 231  
 general registers in the debug  
 environment 273  
 PSW (Program Status Word), in debug  
 environment 273  
 record format of a file 242  
 record length of a file 87  
 special characters, on a 3270 225

Channel Address Word (see CAW (Channel  
 Address Word))

Channel Status Word (see CSW (Channel  
 Status Word))

CHAR, result of &DATATYPE built-in  
 functions 297

character  
 data  
 determining if a token contains 297  
 displaying with LINEDIT macro 323

sets, used in CMS 14

strings

- assigning to variable symbols 278
- changing 223
- copying 49
- extracting in an EXEC procedure 298
- locating 238
- translation 50

characters

- altering
  - with the ALTER subcommand 220
  - with the CHANGE subcommand 223
  - with the COPYFILE command 51
- blip, displaying 152
- for a blip string 170
- number in a token, determining 297
- valid in CMS command lines 14

CLEAR

- operand
  - of DLBL command 69
  - of FILEDEF command 97
- option
  - of INCLUDE command 113
  - of LOAD command 125
  - of SYNONYM command 186

clearing

- DLBL definitions 69
  - for released disks before program execution 75
- FILEDEF definitions 98,100
- phase libraries to binary zeroes, in CMS/DOS 83
- storage to zeros
  - with the INCLUDE command 113
  - with the LOAD command 125
- synonym table 186

closing

- CMS files 306
  - in EXEC procedures 306
- virtual card punch after PUNCHC macro 329
- virtual printer after using PRINTL macro 328

CLR operand

- of HNDEXT macro 314
- of HNDINT macro 315
- of HNDSVC macro 316

CMS

- loader (see loader)
- operand of &CONTROL control statement 283
- operand of DLBL command 69
- subcommand, description 226

CMS (Conversational Monitor System) 11

- basic description of 12
- Batch Facility (see CMS Batch Facility)
- command language, basic description 11
- commands (see CMS commands)
- Editor 12
- file identifier
  - default for DLBL command 71
  - default for FILEDEF command 100
- files (see also files)
  - format 98
- macros (see CMS macro instructions)

CMS Batch Facility 40

- halting 216

CMS commands

- ACCESS 26
- AMSERV 29
- ASSEMBLE 32
- ASSGN 37
- CMSBATCH 40
- COMPARE 41
- COPYFILE 43
- CP 53
- DDR 54
- DEBUG 65
- DISK 66
- displaying during EXEC processing 283
- DLBL 68
- DOSLIB 79
- DOSLKED 81
- DSERV 84
- EDIT 86
- entering 12
- ERASE 88
- ESERV 90
- EXEC 92
- FETCH 94
- FILEDEF 96
- FORMAT 104
- GENDIRT 107
- GENMOD 108
- GLOBAL 111
- INCLUDE 113
- LISTDS 116
- LISTFILE 120
- LISTIO 123
- LOAD 125
- LOADMOD 134
- MACLIB 135
- MODMAP 138
- MOVEFILE 139
- not for general users 17
- nucleus resident 17
- OPTION 142
- PRINT 144
- PSERV 147
- PUNCH 149
- QUERY 152
- READCARD 159
- RELEASE 162
- RENAME 164
- RSERV 166
- RUN 168
- search order 18
- SORT 175
- SSERV 177
- START 179
- STATE 180
- STATEW 180
- summary 20
- SVCTRACE 182
- SYNONYM 186
- TAPE 190
- TAPEMAC 195
- TAPPDS 197
- transient area 16
- TXTLIB 200
- TYPE 202
- UPDATE 204
- valid in CMS subset 226

CMS EXEC file  
   adding to 121  
   creating 120  
   format 121  
 CMS files (see files)  
 CMS Immediate commands (see Immediate commands)  
 CMS macro instructions 303  
   COMPSWT 304  
   FSCB 304  
   FSCBD 305  
   FSCLOSE 306  
   FSERASE 307  
   FSOPEN 308  
   FSREAD 309  
   FSSTATE 311  
   FSWRITE 312  
   HNDEXT 314  
   HNDINT 315  
   HNDSVC 316  
   LINEDIT 317  
   PRINTL 327  
   PUNCHC 329  
   RDCARD 330  
   RDTAPE 331  
   RDTERM 332  
   REGEQU 333  
   TAPECTL 334  
   WAITD 336  
   WAITT 337  
   WRTAPE 337  
   WRTERM 339  
 CMS subset 226  
   RETURN command 246  
   returning to edit mode 246  
 CMSAMS, saved system name 172  
 CMSBATCH command, description 40  
 CMSDOS, saved system name 172  
 CMS/DOS environment  
   description 12  
   initializing 173  
   leaving 173  
   test whether it is active 158  
     in an EXEC procedure 300  
 CMSLIB, assembler macro library ddname 36  
 CMSSEG, saved system name 172  
 CMSUT1 file  
   created by READCARD command 159  
   created by TAPE LOAD command 193  
   created by TAPPDS command 197  
 CMSVSAM, saved system name 172  
 COBOL  
   compiler  
     querying options in effect for 158  
     specifying options for in CMS/DOS 142  
   filetype, default editor settings 343  
 COL option  
   of COMPARE command 41  
   of TYPE command 202  
 COLOR operand of WRTERM macro 339  
 columns  
   comparing disk files by 41  
   displaying particular  
     with the TYPE command 202  
     with the TYPE subcommand 255  
   specifying  
     for copy operations 49  
     for verification setting 256  
     for zone setting for an edit session 258  
 COL1 option, of TAPPDS command 198  
 command  
   defaults, shown by underscore in command format box 15  
   environment  
     CMS 11  
     CP 11  
     definition 11  
     execution, halting 217  
     language, CMS 12  
     languages, VM/370 11  
     modules, creating 108  
     operands 13  
     options 13  
   commands  
     abbreviating 14  
     entering 12  
     truncating 14  
     valid in CMS subset 226  
     when to enter 19  
   comments, in CMS command lines 13  
 COMP  
   operand  
     of DOSLIB command 79  
     of LINEDIT macro 319  
     of MACLIB command 135  
   option, of FETCH command 94  
 COMPARE command  
   COL option 41  
   description 41  
 comparing  
   contents of CMS files 41  
   tokens in an EXEC procedure 288  
 comparison operators, in EXEC procedure 288  
 compile and execute programs, with the RUN command 168  
 compilers, using under CMS 11  
 components, of VM/370 11  
 compressing  
   CMS disk files 45  
   MACLIB files 135  
   TXTLIB files 200  
 COMPSWT macro, description 304  
 CONCAT option, of FILEDEF command 99  
 concatenating  
   OS macro libraries 99  
   periods with EXEC variables 289  
   tokens in an EXEC procedure, &CONCAT built-in function 297  
 conditional execution  
   &IF control statement 288  
   &LOOP control statement 289  
 CONSOLE, value of &READFLAG special variable 301  
 console read, after CMS command execution, controlling 172  
 console stack  
   reading data in an EXEC procedure 291  
   stacking lines  
     &BEGSTACK control statement 281  
     &STACK control statement 293  
     STACK subcommand 251  
   testing whether it is empty 301



- constants
  - altering
    - with LOAD command 132
    - with the STORE subcommand 274
- continuation character
  - on COPYFILE specification list 50
  - on COPYFILE translation list 51
- Control Program (see CP (Control Program))
- control statements
  - for Access Method Services 30
  - for DDR command 54
  - for the UPDATE command 206
- controlling, tapes 191
- conventions, notational 14
- Conversational Monitor System (see CMS (Conversational Monitor System))
- converting
  - BCD characters to EBCDIC characters 45
  - decimal data to EBCDIC, LINEDIT macro 321
  - decimal data to hexadecimal, LINEDIT macro 321
  - fixed-length files to variable-length format 48,242
  - hexadecimal data to EBCDIC, LINEDIT macro 317
  - keypunch characters 45
  - lowercase letters to uppercase, with the COPYFILE command 45
  - uppercase letters to lowercase, with the COPYFILE command 45
  - variable-length files to fixed-length format 48,242
- COPY
  - filetype
    - adding to MACLIBS 136
    - created by the SSERV command 177
    - function statement, of DDR command 57
- COPYFILE command
  - APPEND option 45
  - description 43
  - EBCDIC option 45
  - examples 46
  - FILL option 45
  - FOR option 44
  - FRLABEL option 44
  - FROM option 44
  - incompatible options 46
  - LOWCASE option 45
  - LRECL option 45
  - NEWDATE option 44
  - NEWFILE option 44
  - NOPROMPT option 44
  - NOSPECS option 44
  - NOTRUNC option 45
  - NOTYPE option 44
  - OLDATE option 44
  - OVLY option 44
  - PACK option 45
  - PROMPT option 44
  - RECFM option 45
  - REPLACE option 44
  - specification list 49
  - SPECS option 44
  - TOLABEL option 44
  - TRANS option 45
  - TRUNC option 45
  - TYPE option 44
  - UNPACK option 45
  - UPCASE option 45
  - usage 46
- copying
  - books from DOS/VS source statement libraries 177
  - character strings 49
  - CMS files 43
    - from one disk to another 47,230
    - to files with different filenames 231
  - columns of data 50
  - data from one device to another 139
  - data from one file to another 43
  - files from one device to another 54
  - lines in a CMS file 261
  - lines in a file being edited, from one position to another 262
  - macros from DOS/VS E sublibraries 90
  - modules from DOS/VS relocatable libraries 166
  - parts of a CMS file
    - with the COPYFILE command 47
    - with the GETFILE subcommand 233
  - procedures from a DOS/VS procedure library 147
  - unloaded OS partitioned data sets into CMS MACLIBS 195
- core image
  - libraries (DOS/VS), displaying the directories of 84
  - phases, in CMS/DOS 79
- COUNT option, of DDR command TYPE/PRINT function control statement 60
- CP (Control Program)
  - basic description 11
  - commands (see CP commands)
- CP command
  - description 53
  - implied 172
  - when to use 53
- CP commands
  - DETACH 162
  - entering in CMS 53
  - executing in CMS command environment 172
  - executing with LINEDIT macro 325
  - CPU time, displaying in an EXEC procedure 294
- creating
  - auxiliary directories 107
  - CMS EXEC file with the LISTFILE command 120
  - CMS files
    - from tapes created by OS utility programs 197
    - FWRITE macro 312
    - using the CMS Editor 86
    - with the COPYFILE command 43
    - with the READCARD command 159
  - CMS macro libraries 135
  - from OS partitioned data sets on tape 195
  - CMS TEXT libraries 200
  - file system control block (FSCB) 304
  - load map of a file
    - with the INCLUDE command 114
    - with the LOAD command 126

MODULE files 108  
   user file directory (ACCESS command) 26  
 cross-reference table, assembler, listing 33  
 CSECTs, duplicate, for the LOAD command 127  
 CSW  
   operand of SET subcommand 273  
   subcommand, description 266  
 CSW (Channel Status Word)  
   changing in the debug environment 273  
   displaying in the debug environment 266  
   format 266  
 CTL option, of UPDATE command 205,210  
 current line pointer  
   position after deleting lines 227  
   positioning  
     at top-of-file 253  
     BACKWARD subcommand 222  
     based on character string 238  
     BOTTOM subcommand 222  
     DOWN subcommand 227  
     FIND subcommand 229  
     FORWARD subcommand 232  
     LOCATE subcommand 238  
     NEXT subcommand 239  
     nnnnn subcommand 260  
     UP subcommand 255  
 cylinder  
   extents for VSAM files 75  
   in CMS/DOS 72  
 cylinders  
   counting number of on a virtual disk 104  
   on a virtual disk, resetting 104  
  
 D  
 DASD Dump Restore program, invoking via the DDR command 54  
 data, overlaying in a file 44  
 DATE option, of LISTFILE command 121  
 DD (data definition), simulating in CMS 96  
 D-disk, accessed after IPL of CMS 27  
 ddnames  
   defining  
     with the DLBL command 68  
     with the FILEDEF command 96  
   entering tape ddnames for AMSERV 30  
   for DLBL command, restrictions for OS users 75  
   to identify VSAM catalogs 77  
     in CMS/DOS 73  
   used by the assembler 36  
   used in CMS/DOS, for DOS/VS libraries 71  
   used in MOVEFILE command 139  
 DDR  
   command  
     COPY function statement 57  
     COUNT option of TYPE/PRINT function control statement 60  
     description 54  
     DUMP function statement 57  
     example of TYPE/PRINT output 61  
     GRAPHIC option of TYPE/PRINT function control statement 60  
     HEX option of TYPE/PRINT function control statement 60  
     INPUT control statement 55  
     PRINT function statement 59  
     RESTORE function statement 57  
     SYSPRINT control statement 56  
     TYPE function statement 59  
   control statements, entering 54  
 DEBUG  
   command 12  
   description 65  
   subcommands  
     BREAK 264  
     CAW 265  
     CSW 266  
     DEFINE 267  
     DUMP 268  
     GO 269  
     GPR 270  
     HX 270  
     ORIGIN 271  
     PSW 272  
     RETURN 272  
     SET 273  
     STORE 274  
     X 275  
   debug environment 12,65,263  
   leaving  
     with the GO subcommand 269  
     with the RETURN subcommand 272  
   setting origin value 271  
   debugging, MODULE files 134  
   decimal  
     converting to EBCDIC, LINEDIT macro 321  
     converting to hexadecimal, LINEDIT macro 321  
 DECK  
   option  
     of ASSEMBLE command 34  
     of OPTION command 142  
 default  
   file identifier  
     for DLBL command 71  
     for FILEDEF command 100  
   settings for the CMS Editor  
     image 234  
     preserving 241  
     restoring 245  
     summary 343  
     TABSET 252  
     TRUNC 254  
     ZONE 258  
 defaults, command, shown by underscore in command format box 15  
 DEFINE subcommand, description 267  
 defining  
   data sets, with FILEDEF command 101  
   files for CMS/DOS 68  
   OS data sets under CMS 96  
   VSAM files, with the DLBL command 68  
 DEL operand  
   of DOSLIB command 79  
   of MACLIB command 135  
   of TXTLIB command 200  
 DELETE  
   control statement, for UPDATE command 208  
   subcommand, description 227

- deleting
  - CMS disk files 88
  - lines in a file being edited 227
    - to a particular line 228
  - members of a macro library 135
  - members of a TXTLIB 200
  - phases from a CMS/DOS phase library 79
  - READ control cards 160
  - records from a source file with the UPDATE command 208
- delimiters
  - on a CHANGE subcommand 223
  - on a command line 13
  - on a DSTRING subcommand 228
  - on LOCATE subcommand 238
- DEN option
  - of ASSGN command 38
  - of FILEDEF command 99
  - of TAPE command 192
- density of tapes, specifying 192
- DET option of RELEASE command 162
- DETACH command 162
- detaching, disks 162
- device types
  - default attributes for MOVEFILE command 140
  - valid for FILEDEF command operands 97
- devices, waiting for interrupts 336
- DIRECT, filetype, default editor settings 343
- directories
  - CMS auxiliary 107
  - CMS file, writing to disk 162
  - of DOS/VS libraries, obtaining information from 84
- discontiguous shared segment, saved system names 172
- DISK
  - command
    - DUMP operand 66
    - LOAD operand 66
  - operand
    - of CMS QUERY command 155
    - of FILEDEF command 97
    - of FILEDEF command, examples 101
    - of FILEDEF command, interactive use of 101
  - option
    - of ASSEMBLE command 34
    - of DOSLIB command 79
    - of DOSLKED command 81
    - of DSERV command 84
    - of MACLIB command 136
    - of PSERV command 147
    - of RSERV command 166
    - of SSERV command 177
    - of TAPE command 192
    - of TXTLIB command 200
    - of UPDATE command 205
- disk files (*see* files)
- disk storage capacity, displaying status of 155
- disks
  - accessing 26
  - A-disk 27
  - D-disk 27
  - deleting files from 88
  - determine
    - if a disk is accessed, in an EXEC procedure 299
    - if a disk is CMS OS or DOS, in an EXEC procedure 299
    - if a disk is full 155
    - the read/write status of 155
  - DOS, accessing 28
  - formatting 104
  - OS, accessing 28
  - releasing from your virtual machine 162
  - S-disk 27
  - writing labels on 104
  - Y-disk 27
- DISP
  - operand, of LINEDIT macro 324
  - option, of FILEDEF command 99
- display
  - mode, of the CMS Editor 87
  - terminal, display mode 87
- DISPLAY operand of FORMAT subcommand 232
- display terminals
  - display mode 231
  - line mode 87
- displaying
  - blank lines at the terminal during EXEC processing 292
  - blanks in LINEDIT message text 319
  - blip characters for virtual machine 152
  - CAW (Channel Address Word), in debug environment 265
  - CMS commands during EXEC processing 283
  - CMS files 202
    - in hexadecimal format 202
  - CMS files on a 3270 screen 248
  - columns of a CMS file 202
  - contents of storage, LINEDIT macro 322
  - contents of virtual storage, in debug environment 275
  - CSW (Channel Status Word), in debug environment 266
  - data at the terminal
    - &BEGTYPE control statement 282
    - LINEDIT macro 317
  - data lines at the terminal
    - &TYPE control statement 295
    - determining if terminal is displaying 301
    - WRTERM macro 339
  - DLBL definitions 70,157
  - error messages
    - during EXEC processing 283
    - with the LINEDIT macro 325
  - EXEC statements during EXEC processing 283
  - extents occupied by OS and DOS files 116
  - FILEDEF definitions 102,157
  - filenames on a tape 191
  - general registers, in the debug environment 270
  - hexadecimal values in an EXEC procedure 288
  - information
    - about CMS files 120
    - about files on OS and DOS disks 116
    - about MACLIB members 135
    - about OS and DOS disks 116

last executed EDIT subcommand 259  
 line numbers during line-number editing  
 237  
 list of CMS files on a tape 192  
 load maps 126  
   of MODULE files 138  
 members of CMS libraries 203  
 parameter lists during program  
 execution, LINEDIT macro 323  
 particular columns of a file, during  
 edit session 256  
 particular records in a CMS file 202  
 procedure from a DOS/VS procedure  
 library 147  
 PSW (Program Status Word), in debug  
 environment 272  
 records in a CMS file, with the TYPE  
 subcommand 254  
 return code from EXEC, on Ready message  
 286  
 return codes during EXEC processing 283  
 screensful of data in a file 248  
 short form of editor error message 251  
 time-of-day during EXEC processing 283  
 timing information in an EXEC procedure,  
 &TIME control statement 294

**DLBL**  
 command  
   CAT option 70  
   CHANGE option 69  
   CLEAR operand 69  
   CMS operand 69  
   ddname restrictions (OS users) 75  
   description 68  
   DSN operand 69  
   DUMMY operand 68  
   entering SYSxxx operand 70  
   establishing file definitions for the  
   STATE command 180  
   EXTENT option 69  
   MULT option 69  
   NOCHANGE option 69  
   PERM option 69  
   SYSxxx option 69  
   to identify files for AMSERV 30  
   VSAM option 69  
   when to use (OS users) 75  
 definitions  
   cleared by the ESERV EXEC 90  
   clearing before program execution 75  
   operand of CMS QUERY command 157

**DMSLDR** SYSUT1 file 126

**DOS**  
 disks, accessing 28  
 files  
   listing information 116  
   specifying FILEDEF options for 100  
 operand  
   of CMS QUERY command 158  
   of CMS SET command 173  
   option of GENMOD command 109

**DOSLIB**  
 command  
   COMP operand 79  
   DEL operand 79  
   description 79  
   DISK option 79  
   MAP operand 79  
   PRINT option 79  
   TERM option 79  
 files 79  
   adding phases to 82  
   fetching phases from 94  
   identify for fetching 111  
   output filemode 81  
   size considerations 80  
   space considerations 82  
   which DOSLIBS will be searched 158  
 operand  
   of CMS QUERY command 158  
   of GLOBAL command 111

**DOSLKED** command  
   description 81  
   DISK option 81  
   PRINT option 81  
   TERM option 82

**DOSLNK** filetype  
   CMS/DOS linkage editor input 81  
   creating 82

**DOSPART** operand  
   of CMS QUERY command 158  
   of CMS SET command 173

**DOT** operand of LINEDIT macro 319

**DOWN**  
   operand, of \$MOVE edit macro 262  
   subcommand, description 227

**DSECT**, for file system control block (FSCB)  
 305

**DSERV** command  
   CD operand 84  
   description 84  
   DISK option 84  
   PD operand 84  
   PRINT option 84  
   RD operand 84  
   SD operand 84  
   SORT option 84  
   TD operand 84  
   TERM option 84

DSN operand of DLBL command 69  
 DSORG option, of FILEDEF command 99  
 DSTRING subcommand, description 228

**DUMMY**  
   operand  
     of DLBL command 68  
     of DLBL command, restrictions for OS  
     VSAM user 70  
     of DLBL command, using in CMS/DOS 71  
     of FILEDEF command 97

**DUMP**  
   function statement, of DDR command 57  
   operand  
     of DISK command 66  
     of TAPE command 191  
   option, of OPTION command 142  
   subcommand, description 268

**dumping**  
   CMS files  
     to tape 191  
     to the virtual card punch 66  
   contents of virtual storage 268  
   mindisks to tape 54

**DUP** option  
   of INCLUDE command 114  
   of LOAD command 126,127

duplicate CSECTs, for the LOAD command 127  
duplicating, lines in a CMS file 261

**E**  
**EBCDIC**  
display a file in 202  
option, of COPYFILE command 45

**EDIT**  
command 12  
description 86  
LRECL option 87  
NODISP option 87  
operand  
of RDTERM macro 332  
of WRTERM macro 339  
subcommand environment 12  
subcommands (see EDIT subcommands)  
edit environment 219  
edit macros  
\$DUP 261  
\$MOVE 262  
edit mode 219  
leaving with the FILE subcommand 229  
of CMS Editor 12  
**EDIT** subcommands 12  
? 259  
= 246  
affected by zone setting 258  
ALTER 220  
AUTOSAVE 221  
BACKWARD 222  
BOTTOM 222  
CASE 223  
CHANGE 223  
CMS 226  
DELETE 227  
DOWN 227  
DSTRING 228  
FILE 229  
FIND 229  
FMODE 230  
FNAME 231  
FORMAT 231  
FORWARD 232  
GETFILE 233  
IMAGE 234  
INPUT 235  
LINEMODE 236  
LOCATE 238  
LONG 238  
NEXT 239  
nnnnn 260  
OVERLAY 240  
PRESERVE 241  
PROMPT 241  
QUIT 242  
RECFM 242  
RENUM 243  
REPEAT 244  
REPLACE 245  
RESTORE 245  
REUSE 246  
SAVE 248  
SCROLL 248  
SCROLLUP 248  
SERIAL 249  
settings saved by PRESERVE subcommand 241  
SHORT 251  
STACK 251  
TABSET 252  
TOP 253  
TRUNC 253  
TYPE 254  
UP 255  
VERIFY 256  
X 257  
Y 257  
ZONE 258  
edited  
error messages  
displaying with the LINEDIT macro 325  
in an EXEC procedure 280  
macros, DOS/VS copying 90  
editing  
CMS files 219  
lines read with the RDTERM macro 332  
editor  
invoking 86  
settings for reserved filetypes, summary 343  
**END** option, of TAPPDS command 198  
end-of-file  
effect of LOCATE subcommand 238  
position current line pointer at 222  
entering  
bytes of data on a SET subcommand 273  
CMS commands 12  
using synonyms 187  
commands, keyboard differences 19  
CP commands from the CMS command environment 53  
debug environment  
via breakpoint 263  
via DEBUG command 263  
via external interrupt 263  
edit environment 86  
**EDIT** subcommands, re-entering 246  
file identifications  
for the LISTDS command 117  
on the DLBL command 69  
on the FILEDEF command 101  
input lines by prompting 237  
operands on CMS assembler language macro instructions 303  
VSAM extent information 75  
in CMS/DOS 71  
**ENTRY**, loader control statement 129  
entry point  
determined by the loader 127  
displayed with FETCH command 94  
specifying  
with the **ENTRY** statement 129  
with the GENMOD command 108  
with the INCLUDE command 113  
with the LOAD command 125  
with the START command 179  
environments of CMS 12  
CMS Editor 12  
CMS/DOS 12  
debug 12  
EXEC facilities 12  
EOF option, of TAPE command 192

EOT option, of TAPE command 192  
EQU statements, generating for registers,  
  REGEQU macro 334  
ERASE  
  command  
    description 88  
    NOTYPE option 88  
    TYPE option 88  
  option of ACCESS command 26,27  
erasing  
  all the CMS files on a disk 26  
  CMS files 88  
    during program execution 307  
ERG, tape control function 191  
ERROR  
  operand  
    of &CONTROL control statement 283  
    of FSCLOSE macro 306  
    of FSERASE macro 307  
    of FSOPEN macro 308  
    of FSREAD macro 309  
    of FSSTATE macro 311  
    of FSWRITE macro 312  
    of HNDINT macro 315  
    of HND SVC macro 316  
    of PRINTL macro 327  
    of PUNCHC macro 329  
    of RDCARD macro 330  
    of RDTAPE macro 331  
    of TAPECTL macro 335  
    of WAITD macro 336  
    of WRTAPE macro 338  
error messages  
  CMS  
    displaying during EXEC processing  
      283  
    suppressing display during EXEC  
      processing 283  
  displayed by CMS Editor 238  
  displayed by the CMS Editor 251  
  displaying with LINEDIT macro 325  
  issued in an EXEC procedure 280  
    &EMSG control statement 284  
  type in red 172  
  VM/370 format 280  
errors  
  encountered in macro instruction  
    execution 303  
  from Access Method Services 29,30  
  in an EXEC procedure, specifying action  
    to be taken 285  
ERRS, option, of OPTION command 142  
ESD option, of ASSEMBLE command 33  
ESERV command, description 90  
examining, virtual storage locations 275  
EXEC  
  built-in functions 296  
    &CONCAT 297  
    &DATATYPE 297  
    &LENGTH 297  
    &LITERAL 298  
    &SUBSTR 298  
  command 12  
    description 92  
    implied 172  
  control statements 277  
    &ARGS 279  
    &BEGEMSG 279  
    &BEGPUNCH 281  
    &BEGSTACK 281  
    &BEGTYPE 282  
    &CONTINUE 282  
    &CONTROL 283  
    &EMSG 284  
    &END 285  
    &ERROR 285  
    &EXIT 286  
    &GOTO 287  
    &HEX 287  
    &IF 288  
    &LOOP 289  
    &PUNCH 290  
    &READ 291  
    &SKIP 291  
    &SPACE 292  
    &STACK 293  
    &TIME 294  
    &TYPE 295  
    assignment statement 278  
    displaying during EXEC processing  
      283  
  files  
    \$LISTIO EXEC created by LISTIO  
      command 123  
    CMS EXEC created by the LISTFILE  
      command 120  
      executing with the RUN command 168  
  filetype  
    default editor settings 343  
    record format 92  
  option  
    of LISTFILE command 120  
    of LISTIO command 123  
  procedures  
    defining synonyms for 186  
    ESERV 90  
    RUN 168  
  special variables 299  
    &\$ 299  
    &\* 299  
    &DISK\* 300  
    &DISK? 300  
    &DISKx 299  
    &DOS 300  
    &EXEC 300  
    &GLOBAL 300  
    &GLOBALn 301  
    &INDEX 301  
    &INDEX, setting 279  
    &LINENUM 301  
    &n 279,299  
    &READFLAG 301  
    &RETCODE 301  
    &TYPEFLAG 301  
    &0 299  
    &1 through &30 279  
  executable statements 278  
    in &IF control statement 288  
    on &ERROR control statement 285  
  execute, form of the LINEDIT macro 326  
  executing  
    conditional statements in an EXEC  
      procedure 288  
  CP commands  
    in EXEC procedures 53  
    in jobs for CMS Batch Facility 53

CP commands during program execution 325  
 EXEC procedures 16,92,277  
 MODULE files 17,134  
 programs  
   in CMS/DOS 94  
   with the INCLUDE command 114  
   with the LOAD command 126  
   with the RUN command 168  
   with the START command 179  
 programs in EXEC procedures,  
   considerations for closing files 306  
 TEXT files  
   setting the starting point for 125  
   with the RUN command 168  
 execution  
   entry point, resetting, with the INCLUDE  
   command 113  
   of a CMS command, halting 217  
   summary in an EXEC procedure 283  
 exiting, from an EXEC procedure 286  
 extending, one disk from another 26  
 extensions  
   read-only 26  
     accessing 27  
     editing files on 86  
 EXTENT option  
   of DLBL command 69,75  
   in CMS/DOS 72  
   of LISTDS command 116  
 extents  
   for VSAM files  
     determining free space for 116  
     entering 75  
     entering in CMS/DOS 72  
 EXTERNAL command 263  
 external interrupts  
   effect in CMS 263  
   provide processing routine for 314  
 External Symbol Dictionary (ESD) 33  
  
 F  
 FETCH command  
   COMP option 94  
   description 94  
   identify DOSLIBS to be searched 111  
   ORIGIN option 94  
 FIFO operand of &STACK control statement  
   293  
 file  
   definitions  
     displaying DLBL definitions 157  
     displaying FILEDEF definitions 157  
     for the MOVEFILE command 139  
     for the STATE command 180  
   directories  
     auxiliary 107  
     set up with the ACCESS command 26  
   identifier  
     assigned with the TAPPDS command 197  
     changing with the FILE subcommand  
     229  
     changing with the RENAME command 164  
     changing with the SAVE subcommand  
     248  
     CMS, assigned with the READCARD  
     command 159  
     in command syntax 15  
   file identification (see file identifier)  
   FILE NOT FOUND error message, suppressing  
   during EXEC processing 283  
   file status table (FST) 311  
   FILE subcommand, description 229  
   file system control block (FSCB) (see  
   FSCB)  
   FILEDEF  
     command  
       BLKSIZE option 98  
       BLOCK option 98  
       CHANGE option 98  
       CLEAR operand 97  
       CONCAT option 99  
       default FILEDEF commands issued by  
       the assembler 36  
       definitions for MOVEFILE command 139  
       DEN option 99  
       description 96  
       DISK operand 97  
       DISP option 99  
       DSORG option 99  
       DUMMY operand 97  
       establishing file definitions for the  
       STATE command 180  
       examples 101,102  
       KEYLEN option 98  
       LIMCT option 98  
       LOWCASE option 99  
       LRECL option 98  
       MEMBER option 99  
       NOCHANGE option 98  
       OPTCD option 99  
       PERM option 98  
       PRINTER operand 97  
       PUNCH operand 97  
       READER operand 97  
       RECFM option 98  
       TAPn operand 97  
       TERMINAL operand 96  
       TRTCH option 99  
       UPCASE option 99  
       when to use (OS users) 75  
       when to use in CMS/DOS 71  
       XTENT option 98  
       7TRACK option 99  
       9TRACK option 99  
     definitions  
       clearing 100  
       displaying 157  
       operand of CMS QUERY command 157  
   fileid, in command syntax 15  
   filemode  
     changing  
       FMODE subcommand 230  
       with the COPYFILE command 47  
     displaying, FMODE subcommand 230  
   letter  
     establishing 26  
     replacing 162  
   numbers  
     changing 165  
     2 27  
   specifying, for FSWRITE macro 312  
   specifying on READCARD command 160

filename  
 changing, FNAME subcommand 231  
 of an EXEC file  
 testing 299,300

files  
 calculating blocksize 100  
 calculating logical record length 100  
 comparing 41  
 copying 43  
 creating from OS partitioned data sets 139  
 creating from OS tapes 197  
 deleting from a CMS disk 88  
 displaying 202  
 dumping to tape 191  
 erasing 88  
 during program execution 307  
 loading from tape 191  
 modifying 43  
 moving from device to device 139  
 opening, during program execution 308  
 overlaying 44  
 printing 144  
 in hexadecimal 144  
 processed by TAPE command, listing 192  
 punched  
 restoring to disk 66,159  
 punching to a virtual card punch 66,149  
 relating to OS ddname 96  
 renaming 164  
 displaying new names for 164  
 sorting records in 175  
 tape, writing to disk 191  
 verifying the existence of 180

filetypes, reserved, default editor settings for 343

filing, edited files on disk 229

FILL option, of COPYFILE command 45

FIND subcommand  
 description 229  
 effect of image setting 234

first-in first-out stacking, in an EXEC procedure 281,293

fixed-length file, converting to variable-length, using the RECFM subcommand 242

fixed-length files, converting to variable-length 48

FLAG option, of ASSEMBLE command 33

FMODE  
 option, of LISTFILE command 121  
 subcommand, description 230

fn ft fm, used for to represent file identifier 15

FNAME  
 option, of LISTFILE command 121  
 subcommand, description 231

FOR option, of COPYFILE command 44

FORMAT  
 command  
 description 104  
 examples 105  
 LABEL option 104  
 performance consideration 105  
 RECOMP option 104

option  
 of LISTDS command 117  
 of LISTFILE command 121

subcommand  
 description 231  
 DISPLAY operand 232  
 LINE operand 232

formatting, CMS disks 104

FORTLAN filetype, default editor settings 343

forward space a tape 191

FORWARD subcommand, description 232

FREE option, of LISTDS command 116

FREEFORT filetype, default editor settings 343

FRLABEL option, of COPYFILE command 44

FROM option  
 of COPYFILE command 44  
 of GENMOD command 108

FSCB  
 macro  
 BUFFER operand 304  
 description 304  
 NOREC operand 304  
 RECNO operand 304

operand  
 of FSCLOSE macro 306  
 of FSERASE macro 307  
 of FSOPEN macro 308  
 of FSREAD macro 309  
 of FSSTATE macro 311  
 of FSWRITE macro 312

FSCB (file system control block)  
 creating 304  
 format 305

FSCBD macro, description 305

FSCLOSE macro  
 description 306  
 ERROR operand 306  
 FSCB operand 306

FSERASE macro  
 description 307  
 ERROR operand 307  
 FSCB operand 307

FSF, tape control function 191

FSOPEN macro  
 description 308  
 ERROR operand 308  
 FSCB operand 308

FSR, tape control function 191

FSREAD macro  
 description 309  
 ERROR operand 309  
 FSCB operand 309

FSSTATE macro  
 description 311  
 ERROR operand 311  
 FSCB operand 311

FST (see file status table)

FSWRITE macro  
 description 312  
 ERROR operand 312  
 FSCB operand 312

G

GEN operand  
 of MACLIB command 135  
 of TXTLIB command 200

GENDIRT command, description 107



general registers  
   changing, in the debug environment 273  
   displaying, in the debug environment 270  
   generating list of EQU statements for 334  
   printing contents of 268  
 generating  
   macro libraries 135  
   MODULE files 108  
 GENMOD command  
   ALL option 109  
   description 108  
   DOS option 109  
   FROM option 108  
   MAP option 108  
   NOMAP option 108  
   NOSTR option 109  
   OS option 109  
   STR option 109  
   SYSTEM option 109  
   TO option 108  
 GETFILE subcommand, description 233  
 global changes  
   with the ALTER subcommand 220  
   with the CHANGE subcommand 224  
   with the OVERLAY subcommand 240  
 GLOBAL command  
   description 111  
   DOSLIB operand 111  
   MACLIB operand 111  
   querying which DOSLIBs were last specified 158  
   querying which MACLIBs were last specified 157  
   querying which TXTLIBs were last specified 157  
   TXTLIB operand 111  
 GO subcommand, description 269  
 GPR  
   operand of SET subcommand 273  
   subcommand, description 270  
 GRAPHIC option, of DDR command TYPE/PRINT function control statement 60  
  
 H  
 halting  
   execution of a CMS command 217  
   recording of trace information 216  
   terminal output 217  
     in an EXEC procedure 293  
   the CMS batch virtual machine 216  
 HB Immediate command 216  
 header  
   card  
     as a READ control card 159  
     punched by the PUNCH command 149,150  
   for LISTFILE command output 120  
   format 122  
 HEADER option  
   of LISTFILE command 120  
   of PUNCH command 149  
 HEX option  
   of DDR command TYPE/PRINT function control statement 60  
   of PRINT command 144  
   of TYPE command 202  
  
 hexadecimal  
   conversion  
     in an assignment statement 278  
     LINEDIT macro 320  
   display a file in 202  
   print a file in 144  
   representations of characters, translating 171  
   substitution  
     in an EXEC procedure 278  
     in an EXEC procedure, initializing 287  
 HNDEXT macro  
   CLR operand 314  
   description 314  
   SET operand 314  
 HNDINT macro  
   ASAP operand 315  
   CLR operand 315  
   description 315  
   ERROR operand 315  
   SET operand 315  
   used with WAITD macro 336  
 HNDSVC macro  
   CLR operand 316  
   description 316  
   ERROR operand 316  
   SET operand 316  
 HO Immediate command 216  
 HT Immediate command 217  
   stacking in an EXEC procedure 293  
 HX  
   DEBUG subcommand 270  
   Immediate command 217  
     effect on DLBL definitions 69  
     effect on FILEDEF definitions 100  
  
 I  
 ICS control statement (see Include Control Section (ICS) statement)  
 ID card, CP, example 160  
 identifying  
   CMS/DOS phase libraries to search 111  
   macro libraries to search 111  
   TEXT libraries to search 111  
   VSAM catalogs 77  
     in CMS/DOS 73  
 IEBTPCH utility program, creating CMS files from tapes created by 197  
 IEBUPDTE utility program, creating CMS files from tapes created by 197,198  
 IEHMOVE utility program  
   creating CMS files from tapes created by 197  
   creating CMS MACLIBs from tapes created by 195  
 IGN operand of ASSGN command 37  
   with DUMMY data sets 71  
 ignore, logical unit assignment 37  
 IJSYSCL, defining in CMS/DOS 71  
 IJSYSCT  
   defining 77  
   in CMS/DOS 73  
 IJSYSRL, defining in CMS/DOS 71  
 IJSYSSL, defining in CMS/DOS 71

**IJSYSUC**  
 defining 77  
     in CMS/DOS 73  
**image setting**  
     effect on FIND subcommand 229  
     effect on logical tab settings 253  
**IMAGE subcommand**  
     CANON operand 234  
     description 234  
     OFF operand 234  
     ON operand 234  
**Immediate commands**  
     HB 216  
     HO 216  
     HT 217  
     HX 217  
     RO 217  
     RT 218  
     SO 218  
     summary 19  
**IMPCP operand**  
     of CMS QUERY command 153  
     of CMS SET command 172  
**IMPEX operand**  
     of CMS QUERY command 153  
     of CMS SET command 172  
**implied**  
     CP function 53  
         query the status of 153  
         setting 172  
     EXEC function 92  
         query the status of 153  
         setting 172  
**INC option, of UPDATE command 205**  
**INCLUDE command**  
     AUTO option 114  
     called to load files dynamically 304  
     CLEAR option 113  
     description 113  
     DUP option 114  
     effect on loader tables 171  
     examples 115  
     following a LOAD command 115  
     identify TXTLIBS to be searched 111  
     INV option 114  
     LIBE option 114  
     MAP option 114  
     NOAUTO option 114  
     NOCLEAR option 113  
     NODUP option 114  
     NOINV option 114  
     NOLIBE option 114  
     NOREP option 114  
     NOTYPE option 114  
     ORIGIN option 113  
     REP option 114  
     RESET option 113  
     SAME option 114  
     START option 114  
     TYPE option 114  
**Include Control Section (ICS), loader control statement 130**  
**increment**  
     specifying for line-number editing 241  
     specifying for sequence numbers in a file 250  
**inhibiting, variable substitution in an EXEC procedure 298**  
**initializing**  
     arguments in an EXEC procedure 279  
     CMS disks 104  
     hexadecimal substitution in an EXEC procedure 287  
     the CMS/DOS environment 173  
**INMOVE, MOVEFILE command ddname 139**  
**INPUT**  
     control statement, for DDR command 55  
     operand  
         of CMS QUERY command 154  
         of CMS SET command 171  
     subcommand  
         description 235  
         effect of image setting 234  
         on = subcommand line 247  
**input mode 219**  
     during line-number editing 237  
     entering 235,245  
     leaving 219  
     of CMS Editor 12  
**INSERT control statement, for UPDATE command 207**  
**inserting**  
     lines in a file being edited 235  
     records in a file with the UPDATE command 207  
**instruction, addresses, halting program execution at 264**  
**instructions**  
     altering  
         with LOAD command 132  
         with the STORE subcommand 274  
**Interactive Problem Control System (IPCS) 11**  
**interrupts**  
     entering debug environment after 263  
     handling  
         external 314  
         I/O 315  
         SVC 316  
     I/O, waiting 336  
**INV option**  
     of INCLUDE command 114  
     of LOAD command 126  
**invalid, card images in a load map 127**  
**invoking**  
     a synonym table 186  
     the CMS Editor 12  
**I/O devices, handling interrupts for 315**  
**IPCS (Interactive Problem Control System) 11**  
     issuing, error messages in an EXEC 280,284  
  
**J**  
     job catalog  
         identifying 77  
         in CMS/DOS 73  
  
**K**  
     keyboard, unlock to enter commands 19  
     KEYLEN option, of FILEDEF command 98  
     keypunch characters, converting 45

L

**LABEL** option  
of **FORMAT** command 104  
of **LISTFILE** command 121

**labels**  
for a file system control block,  
generating 305  
in an **EXEC** procedure  
object of **&LOOP** control statement  
289  
using **&CONTINUE** 282  
in **EXEC** procedures, object of **&GOTO**  
control statement 287  
on CMS disks, writing 104

language processors, using under **CMS** 11

last-in first-out stacking, in an **EXEC**  
procedure 281,293

**LDRTBLS** operand  
of **CMS QUERY** command 153  
of **CMS SET** command 171

**LDT** statement (see **Loader Terminate (LDT)**  
statement)

**LEAVE** option, of **DDR** command **INPUT/OUTPUT**  
control statement 56

leaving  
**CMS** subset 246  
debug environment  
**RETURN** subcommand 272  
with the **GO** subcommand 269  
with the **HX** subcommand 270  
edit environment  
**FILE** subcommand 229  
**QUIT** subcommand 242  
**EXEC** procedure 286

**LEFT** operand of **LINEMODE** subcommand 236

length  
of a token in an **EXEC** procedure,  
determining 297  
specifying for **LINEDIT** macro  
substitution list 323

**LENGTH** operand of **RDTERM** macro 333

**LIBE** option  
of **INCLUDE** command 114  
of **LOAD** command 126

**LIBMAC** option, of **ASSEMBLE** command 33

libraries  
**CMS** (see also **DOSLIB**, **MACLIB**, **TXTLIB**)  
displaying member names 203  
displaying those to be searched  
during processing 157  
identifying 111  
macro libraries 135  
printing members 144  
querying 157  
used when processing **CMS** commands  
111

**DOS/VS**  
assigning logical units 38  
obtain information about 84

**DOS/VS** core image  
defining **IJSYSCL** 71  
fetching phases from 94

**DOS/VS** procedure, copying procedures  
147

**DOS/VS** relocatable  
assigning **SYSRLB** 166  
copying modules from 166  
defining **IJSYSRL** 71  
displaying modules from 166  
link-editing modules from 81  
printing modules from 166  
punching modules from 166

**DOS/VS** source statement  
assigning **SYSSLB** 177  
copying books 177  
copying macros from 90  
defining **IJSYSSL** 71  
displaying books 177  
printing books 177  
punching books 177

**OS** macro libraries (see macro  
libraries, **OS**)  
punching member files in 149

**LIBRARY**  
loader control statement 129  
operand, of **CMS QUERY** command 157

**LIFO** operand  
of **&BEGSTACK** control statement 281  
of **&STACK** control statement 293

**LIMCT** option, of **FILEDEF** command 98

line  
image, of a record 234  
mode  
of the **CMS** Editor 87  
of 3270 232  
number, of an **EXEC** statement, testing  
301

**LINE** operand of **FORMAT** subcommand 232

**LINECOUN** option  
of **ASSEMBLE** command 33  
of **PRINT** command 145

**LINEDIT** macro  
**BUFFA** operand 325  
**COMP** operand 319  
description 317  
**DISP** operand 324  
**DOT** operand 319  
**MAXSUBS** operand 326  
**MF** operand 326  
**RENT** operand 327  
**SUB** operand 320  
substitution list, specifying 320  
**TEXT** operand 318  
**TEXTA** operand 319

**LINEMODE** subcommand  
description 236  
**LEFT** operand 236  
**OFF** operand 237  
**RIGHT** operand 236

line-number editing  
inserting a single line 260  
left-handed 236  
reserializing records in a file 250  
right-handed 236  
setting a prompting increment for 241

lines  
printing with the **PRINTL** macro 327  
punching with the **PUNCHC** macro 329

**LINK** command, accessing disks after 27

linkage editor control statements  
**DOS/VS** supported in **CMS/DOS** 82  
**OS**  
read by **TXTLIB** command 201  
required format for **TXTLIB** command  
201

link-editing  
  in CMS/DOS 81  
  modules from DOS/VS relocatable  
  libraries 82  
  TEXT files in storage 125  
  TXTLIB members 201  
list form of the LINEDIT macro 326  
LIST option  
  of ASSEMBLE command 33  
  of OPTION command 142  
LISTDS command  
  description 116  
  examples 117  
  EXTENT option 116  
  FORMAT option 117  
  FREE option 116  
  PDS option 117  
LISTFILE command  
  ALLOC option 121  
  APPEND option 121  
  DATE option 121  
  description 120  
  examples 121  
  EXEC option 120  
  FMODE option 121  
  FNAME option 121  
  FORMAT option 121  
  HEADER option 120  
  LABEL option 121  
  NOHEADER option 120  
listing  
  extents occupied by OS and DOS files  
  116  
  files processed by the TAPE command 192  
LISTING, filetype, default editor settings  
343  
listing  
  free extents on OS and DOS disks 116  
  information  
  about CMS files 120  
  about DOSLIB members 79  
  about files on OS and DOS disks 116  
  about MACLIB members 135  
  about MODULE files 138  
  members of an OS partitioned data set  
  117  
  names of TXTLIB members 200  
  status of current logical unit  
  assignments 123  
LISTING filetype  
  created by Access Method Services 29  
  created by the ASSEMBLE command 33  
  controlling 33  
  created by the ESERV program 90  
  printing 144  
LISTIO command  
  A operand 123  
  ALL operand 123  
  APPEND option 123  
  description 123  
  EXEC option 123  
  PROG operand 123  
  STAT option 123  
  SYS operand 123  
  SYSxxx operand 123  
  UA operand 123  
LISTX option, of OPTION command 142  
literal values, using in an EXEC 298

LOAD  
  command  
  AUTO option 126  
  called to load files dynamically 304  
  CLEAR option 125  
  description 125  
  DUP option 126,127  
  duplicate CSECTs 127  
  effect on loader tables 171  
  executing a program using 126  
  identify TXTLIBs to be searched 111  
  INV option 126  
  MAP option 126  
  NOAUTO option 126  
  NOCLEAR option 125  
  NODUP option 126  
  NOINV option 126  
  NOLIBE option 126  
  NOMAP option 126  
  NOREP option 126  
  NOTYPE option 126  
  ORIGIN option 125  
  REP option 126  
  RESET option 125  
  START option 126  
  TYPE option 126  
  used with GENMOD command 109  
  operand  
  of DISK command 66  
  of TAPE command 191  
  load map  
  creating 127  
  displaying at your terminal 126  
  generated by the GENMOD command 108  
  of a MODULE file, displaying 138  
  replace card image in 114  
  load module, creating a map of 114  
  load point of a file, specifying 125  
  loader  
  CMS 127  
  control statements  
  ENTRY statement 129  
  Include Control Section (ICS)  
  statement 130  
  LIBRARY statement 129  
  Loader Terminate (LDT) statement 130  
  Replace (REP) statement 132  
  Set Location Counter (SLC) statement  
  131  
  search order, for unresolved references  
  128  
  tables  
  defining storage for 171  
  displaying the number of 153  
  Loader Terminate (LDT), loader control  
  statement 130  
  loading  
  CMS files dumped with the DISK DUMP  
  command 66  
  CMS files from tape 191  
  MODULE files 134  
  phases into storage for execution 94  
  programs into storage  
  INCLUDE command 113  
  while using the editor 226  
  TEXT files into storage, dynamically  
  during program execution 304

TEXT files into storage for execution 113, 125

LOADMOD command  
called to load files dynamically 304  
CMS/DOS considerations 134  
description 134

LOCATE subcommand  
description 238  
effect of zone setting 258

logical, operators, in an EXEC procedure 288

logical record length, of a CMS file, defaults used by the CMS Editor 87

logical units  
assigning 37  
listing 123

long, form of editor's error message 238

LONG subcommand, description 238

looping, in an EXEC procedure 289

LOWCASE option  
of ASSGN command 38  
of COPYFILE command 45  
of FILEDEF command 99

lowercase letters  
converting to uppercase 45  
meaning in command format box 15  
suppressing translation to uppercase 223  
translating to uppercase  
using the editor 223  
with the PRINT command 144

LRECL option  
of COPYFILE command 45  
example 48  
of FILEDEF command 98  
of the EDIT command 87

**M**

M operand, of CASE subcommand 223

MACLIB  
command  
ADD operand 135  
COMP operand 135  
DEL operand 135  
description 135  
DISK option 136  
GEN operand 135  
MAP operand 135  
PRINT option 136  
reading files created by the ESERV program 91  
REP operand 135  
TERM option 135

files  
creating 135  
distributed with the CMS system 136  
identifying for assembly or compilation 111  
which MACLIBs will be searched 157

operand  
of CMS QUERY command 157  
of GLOBAL command 111

MACRO  
files, created by the ESERV program 90  
filetype  
adding to MACLIBs 136  
default editor settings 343  
invalid records in, handling by MACLIB command 136

macro definitions  
in an assembler listing 33  
in MACRO files 136

macro libraries  
CMS  
adding to 135  
compacting members of 135  
creating 135  
deleting members of 135  
displaying information about members in 135  
replacing members of 135  
creating, from tapes created by IEHMOVE utility program 195  
DOS/VS, copying macros from 90  
identifying 111  
identifying for assembly 36

OS  
concatenating 99  
using in CMS 36

**MAP**  
filetype  
created by DOSLIB command 79  
created by DSERV command 84  
created by MACLIB command 135  
created by the LOAD command 127  
created by the TAPE command 192  
created by TXTLIB command 200

operand  
of DOSLIB command 79  
of MACLIB command 135  
of TXTLIB command 200

option  
of GENMOD command 108  
of INCLUDE command 114  
of LOAD command 126

maps  
created by DOSLIB command 79  
created by the GENMOD command 108  
created by the LOAD command 127  
created by the MACLIB command 135  
created by TXTLIB command 200  
linkage editor, in CMS/DOS 81

margins, setting left margin for input with the editor 253

master catalog (VSAM)  
identifying 77  
identifying in CMS/DOS 73

master file directory  
contents of 27  
suppress updating after RENAME command 165  
updating entries in 164  
writing on disk 162

MAXTEN option, TAPPDS command 198

MAXUBS operand, of LINEDIT macro 326

MCALL option, of ASSEMBLE command 33

MEMBER option  
of FILEDEF command 99  
of PRINT command 144  
of PUNCH command 149  
of TYPE command 203

MEMO filetype, default editor settings 343

message, text for LINEDIT macro 318

MF operand, of LINEDIT macro 326

- minidisks (see also disks)
  - copying 54
  - counting cylinders on 104
  - dumping to tape devices 54
- minimum abbreviation for commands, controlling 153,172
- MLOGIC option, of ASSEMBLE command 33
- MODE
  - operand
    - of RDTAPE macro 331
    - of TAPECTL macro 335
    - of WRTAPE macro 337
  - option, of DDR command INPUT/OUTPUT control statement 56
- mode letter (see filemode letter)
- MODESET operand, of TAPE command 191
- MODMAP command, description 138
- MODULE files
  - creating 108
  - defining synonyms for 186
  - executing, with the RUN command 168
  - format 108
  - generating 108
  - loading dynamically during program execution 304
  - loading into storage for execution 134
  - mapping 138
- modules, DOS/VS relocatable, link-editing 81
- MOVEFILE command
  - default device attributes 140
  - description 139
  - examples 139
  - PDS option 139
- moving
  - data from one device to another 139
  - lines in a file being edited 262
- MSG, operand of &CONTROL control statement 283
- MULT, option of DLBL command 69
- multilevel updates using the UPDATE command, examples of 212
- multiple
  - extents for VSAM files
    - specifying 76
    - specifying in CMS/DOS 72
  - FSCBs 305
  - input files
    - for the UPDATE command 205
    - with the COPYFILE command 47
  - output files
    - with the COPYFILE command 43,47,49
    - with the RENAME command 165
  - substitution lists, LINEDIT macro 324
- multivolume VSAM extents
  - identifying with the DLBL command 76
    - in CMS/DOS 72
  - maximum number of disks 76
    - in CMS/DOS 73
  - rules for specifying 76
    - in CMS/DOS 73
- passing variable data 301
  - testing recursion level 300
  - loops in an EXEC procedure 290
- never-call function, specifying in CMS TEXT file 129
- NEWDATE option, of COPYFILE command 44
- NEWFILE option, of COPYFILE command 44
- NEXT subcommand, description 239
- nnnnn subcommand, description 260
- NOALIGN option, of ASSEMBLE command 35
- NOALOGIC option, of ASSEMBLE command 33
- NOAUTO option
  - LOAD command 126
    - of INCLUDE command 114
- NOCC option, of PRINT command 144
- NOCHANGE option
  - of DLBL command 69
  - of FILEDEF command 98
- NOCLEAR option
  - of INCLUDE command 113
  - of LOAD command 125
- NOCOL1 option, of TAPPDS command 198
- NOCTL option, of UPDATE command 205
- NODECK option
  - of ASSEMBLE command 34
  - of OPTION command 142
- NODISK option, of ACCESS command 26
- NODISP option
  - of EDIT command 87
    - effect on FORMAT subcommand 232
- NODUMP option, of OPTION command 142
- NODUP option
  - of INCLUDE command 114
  - of LOAD command 126
- NOEND option, of TAPPDS command 198
- NOERRS, option, of OPTION command 142
- NOESD option, of ASSEMBLE command 33
- NOHEADER option
  - of LISTFILE command 120
  - of PUNCH command 149
- NOINC option, of UPDATE command 205
- NOINV option
  - of INCLUDE command 114
  - of LOAD command 126
- NOLIBE option
  - of INCLUDE command 114
  - of LOAD command 126
- NOLIBMAC option, of ASSEMBLE command 33
- NOLIST option
  - of ASSEMBLE command 33
  - of OPTION command 142
- NOLISTX option, of OPTION command 142
- NOMAP option
  - GENMOD command 108
    - of LOAD command 126
- NOMAXTEN option, of TAPPDS command 198
- NOMCALL option, of ASSEMBLE command 33
- NOMLOGIC option, of ASSEMBLE command 33
- NOMSG, operand of &CONTROL control statement 283
- nonrelocatable, modules, in CMS 108
- NONSHARE operand, of CMS SET command 173
- nonshared copy
  - of a named system, obtaining 173
  - of saved system, obtained during debug 265
- NONUM option, of ASSEMBLE command 34
- NOOBJECT option, of ASSEMBLE command 34

NOPACK, operand of &CONTROL control statement 283  
 NOPDS option, of TAPPDS command 197  
 NOPRINT option  
     of ASSEMBLE command 34  
     of TAPE command 192  
 NOPROF option, of ACCESS command 26  
 NOPROMPT option, of COPYFILE command 44  
 NOREC operand, of FSCB macro 304  
 NORENT option, ASSEMBLE command 35  
 NOREP option  
     of INCLUDE command 114  
     of LOAD command 126  
     of UPDATE command 204  
 NORL option, of ASSEMBLE command 33  
 NOSEQ8 option, of UPDATE command 205  
 NOSPECS option, of COPYFILE command 44  
 NOSTD option, of SYNONYM command 186  
 NOSTK option  
     of UPDATE command 205  
     UPDATE command 212  
 NOSTMT option, of ASSEMBLE command 34  
 NOSTOR option, of UPDATE command 205  
 NOSTR option, of GENMOD command 109  
 NOSYM option, of OPTION command 142  
 notational conventions 14  
 NOTERM option  
     of ASSEMBLE command 35  
     of UPDATE command 205  
 NOTEST option, of ASSEMBLE command 34  
 NOTIME, operand of &CONTROL control statement 283  
 NOTRUNC option, of COPYFILE command 45  
 NOTYPE option  
     of COPYFILE command 44  
     of ERASE command 88  
     of INCLUDE command 114  
     of LOAD command 126  
     of RENAME command 164  
 NOUPDIRT option, of the RENAME command 164  
 NOWTM option, of the TAPE command 192  
 NOXREF option  
     of ASSEMBLE command 34  
     of OPTION command 142  
 NOYFLAG option, of ASSEMBLE command 35  
 nucleus  
     CMS, protected storage 172  
     protection against writing over 172  
     protection feature, displaying status of 154  
     resident commands, list 17  
 null  
     arguments in an EXEC procedure, setting with % 299  
     symbols in an EXEC statement 289  
 null line  
     stacking, in an EXEC 293  
     stacking in the console stack 251  
     to return to edit mode from input mode 219  
     when entering VSAM extents 76  
         in CMS/DOS 72  
 NUM, result of &DATATYPE built-in function 297  
 number  
     of characters in a token in an EXEC procedure, determining 297  
     of records to be read or written, specifying 304  
 NUMBER option, of ASSEMBLE command 34  
 numbering  
     records in a file being edited, SERIAL subcommand 249  
     records in a source file with the UPDATE command 204  
 numeric  
     data, determining if a token contains 297  
     variables in an EXEC procedure 299  
 O  
 object deck, assembler, generating 34  
 OBJECT option, of ASSEMBLE command 34  
 OFF  
     operand  
         of &CONTROL control statement 283  
         of &HEX control statement 287  
         of &TIME control statement 294  
         of AUTOSAVE subcommand 221  
         of IMAGE subcommand 234  
         of LINEMODE subcommand 237  
         of SERIAL subcommand 249  
 OLDATE option, of COPYFILE command 44  
 ON  
     operand  
         of &HEX control statement 287  
         of &TIME control statement 294  
         of IMAGE subcommand 234  
         of SERIAL subcommand 250  
 opening, CMS files, during program execution 308  
 operands, command 13  
 operators, comparison, in an EXEC procedure 288  
 OPTCD option, of FILEDEF command 99  
 OPTION  
     command  
         DECK option 142  
         description 142  
         DUMP option 142  
         ERRS option 142  
         LIST option 142  
         LISTX option 142  
         NODECK option 142  
         NODUMP option 142  
         NOERRS option 142  
         NOLIST option 142  
         NOLISTX option 142  
         NOSYM option 142  
         NOXREF option 142  
         SYM option 142  
         XREF option 142  
         48C option 142  
         60C option 142  
     operand of CMS QUERY command 158  
 options  
     command 13  
     for the DOS/VS COBOL compiler, specifying 142  
     for the DOS/VS COBOL compiler in CMS/DOS, querying 158  
     LOAD and INCLUDE command, retaining 114

origin  
   for debug environment  
     setting 271  
   used to compute symbol location 267

ORIGIN  
   option  
     of FETCH command 94  
     of INCLUDE command 113  
     of LOAD command 125  
   subcommand, description 271

OS  
   data sets  
     defining in CMS 96  
     listing information 116  
   disks, accessing 28  
   linkage editor control cards, adding to  
     TEXT files 201  
   macro libraries, used in assembly 36  
   option of GENMOD command 109  
   partitioned data sets (see partitioned  
   data sets)  
   tapes, containing partitioned data sets  
     197  
   utility programs  
     creating CMS files from tapes created  
       by 197  
     IEBPTPCH 197  
     IEBUPDTE 197  
     IEHMOVE 197

OUTMOVE, MOVEFILE command ddname 139

OUTPUT  
   control statement, for DDR command 55  
   operand  
     of CMS QUERY command 154  
     of CMS SET command 171

OVERLAY subcommand  
   description 240  
   effect of image setting 234

overlaying  
   character strings 240  
   columns of data in a file, with the  
     COPYFILE command 50  
   data in a file  
     specifying number of lines to overlay  
       244  
     with the COPYFILE command 44  
     with the OVERLAY subcommand 240  
   files 44

OVLY option  
   of COPYFILE command 44  
   example 50

P

PACK  
   operand of &CONTROL control statement  
     283  
   option  
     of COPYFILE command 45  
     of COPYFILE command, example 49

packing  
   CMS files 45  
     specifying a fill character 49  
   execution summary of an EXEC 283

parameter list  
   displaying with the LINEDIT macro 323  
   passed by START command 179

  passed by the RUN command 169  
   passed to an SVC instruction, recorded  
     182

parent disk, of read-only extension 26

parentheses  
   before an option list 13  
   scanned by EXEC interpreter 279

partition size, for CMS/DOS, setting 173

partitioned data sets  
   copying into CMS files 139  
   displaying member names 119  
   on tapes, creating CMS files 197

passing  
   arguments, to nested EXEC procedures  
     301  
   control in an EXEC procedure  
     &GOTO control statement 287  
     &SKIP control statement 292

PD operand of DSERV command 84

PDS (see partitioned data sets)

PDS option  
   of LISTDS command 117  
   of MOVEFILE command 139  
   of TAPPDS command 197

periods  
   as concatenation character for EXEC  
     variables 289  
   indicating message substitution in  
     LINEDIT macro 318  
   placing at end of message text in  
     LINEDIT macro 319

PERM option  
   of DLBL command 69  
   of FILEDEF command 98

permanent file definitions 98

phase library, CMS/DOS 79

phases  
   executing in CMS/DOS 94  
   in DOS/VS core image libraries,  
     obtaining information about 85

PLI filetype, default editor settings 343

PLIOPT filetype, default editor settings  
   343

positioning  
   current line pointer  
     at top-of-file (TOP subcommand) 253  
     BACKWARD subcommand 222  
     based on character string 238  
     BOTTOM subcommand 222  
     DOWN subcommand 227  
     FIND subcommand 229  
     FORWARD subcommand 232  
     NEXT subcommand 239  
     nnnn subcommand 260  
     UP subcommand 255  
   read/write pointer  
     FILEDEF command 99  
     FSWRITE macro 313  
   tapes 191  
     TAPECTL macro 334

prefixes  
   identifying sets of files  
     with the ACCESS command 27  
     with the LISTFILE command 121

prefixing, error messages issued in EXEC  
   with DMS 280,284

PRESERVE subcommand, description 241

preserving, settings for the editor 241



**PRINT**  
 command  
   CC option 144  
   description 144  
   HEX option 144  
   LINECOUN option 145  
   MEMBER option 144  
   NOCC option 144  
 function statement of DDR command 59  
 option  
   of AMSERV command 29  
   of ASSEMBLE command 34  
   of DOSLIB command 79  
   of DOSLKED command 81  
   of DSERV command 84  
   of MACLIB command 136  
   of PSERV command 147  
   of RSERV command 166  
   of SSERV command 177  
   of TAPE command 192  
   of TXTLIB command 200  
   of UPDATE command 205  
 printer, virtual, closing after using  
   PRINTL macro 328  
 PRINTER operand  
   of ASSGN command 37  
   of FILEDEF command 97  
 printing  
   CMS files 144  
     specifying number of lines per page 145  
   CMS files in hexadecimal format 144  
   contents of general registers, from debug environment 268  
   contents of virtual storage 268  
   hexadecimal listing of a file 144  
   lines  
     with the LINEDIT macro 324  
     with the PRINTL macro 327  
   list of CMS files on a tape 192  
   members of CMS libraries 144  
   procedures from a DOS/VS procedure library 147  
   records  
     at the printer 54  
     at the terminal 54  
 PRINTL macro  
   description 327  
   ERROR operand 327  
 private libraries (see libraries, DOS/VS)  
 PROC files, creating in CMS/DOS 147  
 procedure libraries, DOS/VS, displaying the directories of 84  
 procedures, DOS/VS, copying into CMS files 147  
 PROFILE EXEC, suppressing execution of 26  
 PROG operand of LISTIO command 123  
 program  
   entry point, specifying 125  
   entry point selection, during CMS loader processing 127  
   execution  
     displaying data at the terminal 317  
     displaying parameter lists 323  
     displaying storage 322  
     halting 217,264  
     handling external interrupts 314  
     handling I/O interrupts 315  
     handling SVC interrupts 316  
     in CMS subset 226  
     in CMS/DOS 94  
     modifying control words 273  
     modifying general registers 273  
     modifying storage 274  
     resuming after a breakpoint 269  
     with the LOAD command 126  
     with the START command 179  
   Program Status Word (see PSW (Program Status Word))  
   programmer logical units  
     for job catalogs 73  
     listing assignments for in CMS/DOS 123  
     valid assignments in CMS/DOS 37  
 PROMPT  
   option, of COPYFILE command 44  
   subcommand, description 241  
 prompting  
   increment for line-number editing 237  
   setting 241  
 PROTECT operand  
   of CMS QUERY command 154  
   of CMS SET command 172  
 protecting  
   against writing on nucleus 172  
   data in a file during an edit session 258  
 PSERV command  
   description 147  
   DISK option 147  
   PRINT option 147  
   PUNCH option 147  
   TERM option 147  
 PSW  
   operand of SET subcommand 273  
   subcommand, description 272  
 PSW (Program Status Word)  
   changing, in the debug environment 273  
   displaying in the debug environment 272  
 PUNCH  
   assembler punch output ddname 36  
   command  
     description 149  
     HEADER card format 150  
     HEADER option 149  
     MEMBER option 149  
     NOHEADER option 149  
   operand  
     of ASSGN command 37  
     of FILEDEF command 97  
   option  
     of PSERV command 147  
     of RSERV command 166  
     of SSERV command 177  
   punch, virtual, closing after PUNCHC macro 329  
 PUNCHC macro  
   description 329  
   ERROR operand 329  
 punched files, restoring to disk 66  
 punching  
   CMS files to the virtual card punch 149  
   CMS files to the virtual punch 66  
   header card 149  
   lines in an EXEC procedure, &PUNCH control statement 290  
   lines with the PUNCHC macro 329

members of CMS libraries 149  
procedure from a DOS/VS procedure  
library 147  
statements in an EXEC, &BEGPUNCH control  
statement 281

## Q

QUERY command (CMS)  
ABBREV operand 153  
BLIP operand 152  
description 152  
DISK operand 155  
DLBL operand 157  
DOS operand 158  
DOSLIB operand 158  
DOSPART operand 158  
FILEDEF operand 157  
IMPCP operand 153  
IMPEX operand 153  
INPUT operand 154  
LDRTBLS operand 153  
LIBRARY operand 157  
MACLIB operand 157  
OPTION operand 158  
OUTPUT operand 154  
PROTECT operand 154  
RDYMSG operand 153  
REDTYPE operand 154  
RELPAGE operand 153  
SEARCH operand 155  
SYNONYM ALL operand 156  
SYNONYM SYSTEM operand 156  
SYNONYM USER operand 156  
SYSNAMES operand 154  
TXTLIB operand 157  
UPSI operand 158  
QUIT subcommand, description 242

## R

RD operand of DSERV command 84  
RDCARD macro  
description 330  
ERROR operand 330  
RDTAPE macro  
description 331  
ERROR operand 331  
MODE operand 331  
RDTERM macro  
ATTREST operand 333  
description 332  
EDIT operand 332  
LENGTH operand 333  
RDYMSG operand  
CMS SET command 171  
of CMS QUERY command 153  
read, console read after CMS command  
execution 172  
READ control card 159  
deleting 160  
format 160  
READCARD command, description 159  
reader, virtual, read a file from 159  
READER operand  
of ASSGN command 37  
of FILEDEF command 97

reading  
CMS files  
during program execution 309  
from the virtual card reader 66  
sequentially 310  
from the terminal  
during EXEC processing 291  
RDTERM macro 332  
lines from the console stack 251  
OS macro libraries into CMS MACLIBS 195  
records from a virtual card reader 159  
RDCARD macro 330  
records from tape, RDTAPE macro 331  
tape files created by OS utility  
programs 197  
variable symbols from the terminal  
during EXEC processing 291  
read-only  
disks, editing files on 221  
extensions  
editing files on 86  
releasing 162  
read/write  
status of disks  
controlling 27  
finding the first read/write disk in  
the standard search order 300  
finding the read/write disk with the  
most space 300  
listing for disk assignments in  
CMS/DOS 123  
querying 155  
Ready message  
displaying return code from EXEC  
processing 286  
format 171  
long form 171  
query the setting of 153  
setting 171  
short form 171  
special format in EXEC 92  
RECFM  
operand, of FSCB macro 304  
option  
of COPYFILE command 45  
of COPYFILE command, examples 48  
of FILEDEF command 98  
subcommand  
description 242  
F operand 242  
V operand 242  
RECNO operand, of FSCB macro 304  
RECOMP option, of FORMAT command 104  
record format  
of a CMS file  
changing 45,48  
listing 121  
of a file, specifying 98  
records that can be punched 150  
specifying, for FSWRITE macro 312  
record length  
default used by the CMS Editor 87  
modifying 87  
of a CMS file  
changing 45,48  
listing 121  
maximum lengths for the PRINT command  
145

- specifying truncation setting for input 254
- specifying with FILEDEF command 100
- record number, specifying next record to be accessed 304
- recording
  - information about supervisor calls in your virtual machine 182
  - technique for a tape, specifying 192
  - trace information for SVC instructions 182
  - halting 216
- records
  - displaying selected positions of 202
  - in a file, numbering with the UPDATE command 204
- red type
  - display lines with WRTERM macro 339
  - for error messages 172
- REDTYPE operand
  - of CMS QUERY command 154
  - of CMS SET command 172
- reentrant code, for LINEDIT macro instruction 326
- re-executing
  - EDIT subcommands 246
  - X/Y subcommands 257
- references
  - unresolved
    - resolving with INCLUDE command 114
    - resolving with LOAD command 126
- REGQU macro, description 333
- registers (see general registers)
- relating, an OS dname to a CMS file 96
- RELEASE command
  - description 162
  - DET option 162
- releasing
  - disks 162
    - effect on logical unit assignments in CMS/DOS 38
    - in CMS/DOS 162
    - when DLBL definitions are active 75
  - page frames from storage 171
    - after command execution 153
  - read-only extensions 162
- relocatable
  - libraries (DOS/VS), displaying the directories of 84
  - modules, link-editing in CMS/DOS 81
- relocation dictionary, assembler 33
- RELPAGE operand
  - of CMS QUERY command 153
  - of CMS SET command 171
- Remote Spooling Communications Subsystem (RSCS) 11
- remote 3270 terminals, using the CMS Editor 232
- RENAME command
  - description 164
  - NOTYPE option 164
  - NOUPDIRT option 164
  - TYPE option 164
  - UPDIRT option 164
- renaming, CMS files 164
- RENT
  - operand, LINEDIT macro 327
  - option, ASSEMBLE command 35
- RENUM subcommand, description 243
- renumbering
  - records in a file, SERIAL subcommand 249
  - statements in VSBASIC and FREEFOT files 243
- REP
  - operand, of MACLIB command 135
  - option
    - of INCLUDE command 114
    - of LOAD command 126
    - of UPDATE command 204
- REPEAT subcommand 244
  - used with OVERLAY subcommand 240
- repeating
  - EDIT subcommands 246
  - X/Y subcommands 257
- REPLACE
  - control statement, for UPDATE command 208
  - option, of COPYFILE command 44
  - subcommand
    - description 245
    - effect of image setting 234
    - restriction while using line-number editing 237
- Replace (REP)
  - loader control statement 132
  - image of in a load map 114
- replacing
  - a source file 204
  - an old file with a new copy 44
  - members in macro libraries 135
  - records in a file 208
  - records in a file being edited 245
- RESET
  - operand of &TIME control statement 294
  - option
    - of INCLUDE command 113
    - of LOAD command 125
- resetting
  - execution starting point 113
  - the number of cylinders on a virtual disk 104
- resolving, unresolved references, with the LOAD command 126
- responses, CMS Editor, controlling format of 238
- RESTORE
  - function statement, of DDR command 57
  - subcommand, description 245
- restoring
  - CMS files punched with the DISK DUMP command 66
  - dumped files on disk 191
  - files to disk from tape 54
  - settings of EDIT subcommands 245
  - terminal output 218
- restrictions
  - Access Method Services and VSAM
    - DOS/VS users 345
    - OS/VS users 347
- resuming
  - program execution, in the debug environment 269
  - terminal output, in an EXEC procedure 293
  - tracing 217

**RETURN**  
 command, description 246  
 subcommand (DEBUG) 272  
 return codes  
 CMS, in an EXEC procedure 92  
 displaying during EXEC processing 283  
 from Access Method Services 30  
 from CMS commands, testing in an EXEC procedure 301  
 from CMS macro instructions 303  
 from the EXEC interpreter 93  
 specifying in an EXEC procedure 286  
 -1 53  
 REUSE subcommand (see also = subcommand)  
 description 246  
 examples 246  
 REW, tape control function 191  
 rewind, a tape 191  
 REWIND option, of DDR command INPUT/OUTPUT control statement 56  
 ribbon, two-color, controlling use of 154  
 RIGHT operand of LINEMODE subcommand 236  
 RLD option, of ASSEMBLE command 33  
 RO Immediate command 217  
 RSCS (Remote Spooling Communications Subsystem) 11  
 RSERV command  
 description 166  
 DISK option 166  
 PRINT option 166  
 PUNCH option 166  
 TERM option 166  
 RT Immediate command 218  
 stacking in an EXEC procedure 293  
 RUN  
 command, description 168  
 tape control function 191

**S**  
 SAME option, of INCLUDE command 114  
 SAVE subcommand, description 248  
 saved system names  
 querying 154  
 setting 172  
 saving  
 CMS files on disk, during an edit session 248  
 files during an edit session, automatically 221  
 mindisks on tape 54  
 SCAN operand, of TAPE command 191  
 scanning  
 &ERROR control statement 285  
 contents of a CMS file 248  
 in an EXEC procedure 279  
 the contents of a CMS tape 191  
 SCRIPT  
 files  
 CASE setting 223  
 default image setting 234  
 filetype, default editor settings 343  
 SCROLL subcommand, description 248  
 SCROLLUP subcommand, description 248  
 SD operand of DSERV command 84  
 S-disk, accessed after IPLing CMS 27  
 SEARCH operand, of CMS QUERY command 155  
 search order  
 for CMS commands 16  
 for executable phases in CMS/DOS 94  
 for relocatable modules in CMS/DOS 82  
 for the CMS loader 127,128  
 of CMS disks, querying 155  
 searching, TXTLIB files for unresolved references 114  
 SEQUENCE control statement, for UPDATE command 206  
 sequence numbers  
 assigned to VSAM extents 76  
 in CMS/DOS 72  
 sequencing records in a source file  
 using the Editor 250  
 with the UPDATE command 204  
 SEQ8 option, of UPDATE command 204  
 SERIAL subcommand  
 ALL operand 250  
 description 249  
 OFF operand 249  
 ON operand 250  
 serializing  
 records in a file 249  
 when line-number editing is in effect 250  
 with the UPDATE command 204  
 SET  
 command (CMS)  
 ABBREV option 172  
 AUTOREAD option 172  
 BLIP option 170  
 description 170  
 determining status of SET operands for virtual machine environment 152  
 DOS operand 173  
 DOSPART operand 173  
 IMPCP option 172  
 IMPEX option 172  
 INPUT option 171  
 LDRTBLS option 171  
 NONSHARE operand 173  
 OUTPUT option 171  
 PROTECT option 172  
 RDYMSG operand 171  
 REDTYPE option 172  
 RELPAGE option 171  
 UPSI operand 173  
 operand  
 of HNDEXT macro 314  
 of HNDINT macro 315  
 of HND SVC macro 316  
 subcommand (DEBUG) 273  
 CAW operand 273  
 CSW operand 273  
 GPR operand 273  
 PSW operand 273  
 Set Location Counter (SLC), loader control statement 131  
 setting  
 automatic read function 172  
 the blip characters for your virtual machine 170  
 the load point for execution 113  
 the number of loader tables 171  
 sharing  
 disks, read/write 27  
 saved systems 172

short form, of the editor error message 251

SHORT subcommand, description 251

SKIP  
 operand, of TAPE command 191  
 option, of DDR command INPUT/OUTPUT control statement 56

skipping, lines in an EXEC procedure 292

SLC statement (see Set Location Counter (SLC) statement)

SO Immediate command 218

SORT  
 command  
 description 175  
 storage requirements 175  
 option of DSERV command 84

sort fields, defining 175

sorting  
 directories of DOS/VS libraries 84  
 the user file directory 162

source files  
 for the assembler 32  
 replacing 204

source statement libraries, DOS/VS,  
 displaying the directories of 84

source symbol table, assembler, generating 34

space, determine free extents for VSAM 116

special variables (see EXEC special variables)

specification list, for COPYFILE command, format 49

specifying  
 carriage control characters, for PRINT command 144  
 substitution list for LINEDIT macro 320

SPECS option of COPYFILE command 44  
 usage 49

SPOOL command  
 used with DISK DUMP command 66  
 used with PRINT command 145

SSERV command  
 description 177  
 DISK option 177  
 PRINT option 177  
 PUNCH option 177  
 TERM option 177

STACK  
 subcommand, description 251  
 value of &READFLAG special variable 301

stacking  
 commands in the console buffer 19  
 EDIT subcommands 246,251  
 in an EXEC procedure, testing whether there are lines in the stack 301  
 lines in the console stack  
 &BEGSTACK control statement 281  
 &STACK control statement 293  
 meaning in command format box 15

START  
 command  
 description 179  
 passing arguments 179

option  
 of FETCH command 94  
 of INCLUDE command 114  
 of LOAD command 126

starting  
 program execution 179  
 program execution in CMS/DOS 94

starting point for execution of a module, setting 125

STAT option, of LISTIO command 123

STATE command, description 180

STATEW command, description 180

status of virtual machine environment 152

STD option, of SYNONYM command 186

STK option  
 of UPDATE command 205  
 UPDATE command 212

STMT option, of ASSEMBLE command 34

stopping, execution of a program or command 217

STOR option, of UPDATE command 205

storage  
 clearing to zeros 125  
 in CMS/DOS 83  
 displaying with the LINEDIT macro 322  
 examining in debug environment 275  
 initializing for MODULE file execution 109  
 modifying during program execution 274  
 releasing pages of after command execution 153,171  
 requirements for the SORT command 175  
 specifying storage for a CMS/DOS partition 173  
 used by GETFILE subcommand 233

STORE subcommand, description 274

storing, data into virtual storage locations 274

STR option, of GENMOD command 109

SUB operand of LINEDIT macro 320

sublibraries, of DOS/VS source statement, copying books 177

subset, CMS (see CMS subset)

substituting  
 message text in a LINEDIT macro 318  
 variable symbols in an EXEC procedure 278

substitution  
 in an EXEC procedure, inhibiting 298  
 list for LINEDIT macro 320  
 specifying length 323

substrings, extracting in an EXEC procedure, &SUBSTR built-in function 298

summary, of CMS commands 20

suppressing  
 display of long form of editor error message 251  
 FILE NOT FOUND error message during EXEC processing 283  
 hexadecimal substitution in an EXEC procedure 287  
 terminal output, in an EXEC procedure 293  
 translation of lowercase letters to uppercase 223

suspending trace recording 182,218

SVC instructions  
 handling interrupts during program execution 316  
 tracing 182

SVCTRACE command  
   description 182  
   output 185  
 SYM option, of OPTION command 142  
 symbol table, debug 267  
 symbolic names, assigning to storage locations, in the debug environment 267  
 symbols  
   debug  
     defining 267  
     modifying 274  
     used to set breakpoints 264  
   in an EXEC procedure  
     effect of undefined in &IF statement 289  
     reading from the terminal or console stack 291  
   substituted in an EXEC procedure, displaying 283  
   variable (see variable symbols)  
 SYNAMES operand, of CMS QUERY command 154  
 SYNONYM  
   command  
     CLEAR option 186  
     description 186  
     example 187  
     NOSTD option 186  
     relationship to SET ABBREV command 189  
     STD option 186  
   operand, of CMS QUERY command 156  
 SYNONYM ALL operand, of CMS QUERY command 156  
 SYNONYM SYSTEM operand, of CMS QUERY command 156  
 synonym table  
   clearing 186  
   defining 187  
   format for entries in 187  
   invoking 186  
 SYNONYM USER operand, of CMS QUERY command 156  
 synonyms  
   for CMS and user-written commands 186  
     displaying 156  
     examples 187  
   system, displaying 156  
 synonyms for CMS and user-written commands, displaying 188  
 synonyms for user-written and CMS commands, defining 187  
 SYS operand of LISTIO command 123  
 SYSCAT, assign in CMS/DOS 73  
 SYSIN  
   assembler input 36  
   logical unit assignment in CMS/DOS 38  
 SYSIPT, assigning for the ESERV program 90  
 SYSLOG, assigning in CMS/DOS 38  
 SYSNAME operand, of CMS SET command 172  
 SYSPARM option, ASSEMBLE command 35  
 SYSPRINT control statement of DDR command 56  
 SYSRES, assigning in CMS/DOS 38  
 system and programmer logical units, entering on DLBL command 70  
 system disk  
   files available 27  
   releasing 162  
 system logical units  
   invalid assignments in CMS/DOS 38  
   listing assignments for in CMS/DOS 123  
   valid assignments in CMS/DOS 37  
 SYSTEM option, GENMOD command 109  
 system residence volume, DOS/VS, specifying 173  
 SYSTEM, option, ASSEMBLE command 34  
 SYSxxx  
   operand  
     of ASSGN command 37  
     of LISTIO command 123  
   option of DLBL command 69  
  
 T  
 tab  
   characters, how the editor handles 234  
   settings, used by the editor 252  
 TABSET subcommand  
   affected by IMAGE subcommand 234  
   description 252  
 tape  
   control functions 191  
   restrictions when using 193  
   TAPECTL macro 334  
   files  
     created by OS utility programs 197  
     created by TAPE command 193  
     writing to disk 191  
   marks  
     writing 191,192  
   recording technique, specifying 192  
 TAPE command  
   control functions  
     BSF 191  
     BSR 191  
     ERG 191  
     FSF 191  
     FSR 191  
     REW 191  
     RUN 191  
     WTM 191  
   DEN option 192  
   description 190  
   DISK option 192  
   DUMP operand 191  
   EOF option 192  
   EOT option 192  
   LOAD operand 191  
   MODESET operand 191  
   NOPRINT option 192  
   NOWTM option 192  
   PRINT option 192  
   SCAN operand 191  
   SKIP operand 191  
   TAPn option 192  
   TERM option 192  
   TRTCH option 192  
   WTM option 192  
   7TRACK option, 192  
   9TRACK option 192  
   TAPECTL macro  
     description 334  
     ERROR operand 335  
     MODE operand 335  
   TAPEMAC command, description 195

tapes

- assigning to logical units in CMS/DOS 38
- controlling, TAPECTL macro 334
- creating CMS disk files 197
- density of, specifying 192
- displaying the filenames on 191
- dumping and loading CMS files 190
- dumping and restoring disk data 54
- positioning 191
  - at a specified file 191
  - TAPECTL macro 334
- reading records from, RDTAPE macro 331
- used for AMSERV input and output 29
  - entering ddnames 30
  - in CMS/DOS 30
- writing records to, WRTAPE macro 337
- writing tape marks on 192

TAPIN option, of AMSERV command 29

TAPn

- operand
  - of ASSGN command 37
  - of FILEDEF command 97
- option
  - of TAPE command 192
  - TAPADS command 198

TAPOUT option, of AMSERV command 29

TAPADS command

- COL1 option 198
- description 197
- END option 198
- MAXTEN option 198
- NOCOL1 option 198
- NOEND option 198
- NOMAXTEN option 198
- NOPDS option 197
- PDS option 197
- TAPn option 198
- UPDATE option 198

TD operand of DSERV command 84

TERM

- option
  - of DOSLIB command 79
  - of DOSLKED command 82
  - of DSERV command 84
  - of MACLIB command 135
  - of PSERV command 147
  - of RSERV command 166
  - of SSERV command 177
  - of TAPE command 192
  - of TXTLIB command 200
  - of UPDATE command 205

TERMINAL

- operand
  - of ASSGN command 37
  - of FILEDEF command 96
- option, of ASSEMBLE command 34

terminals

- displaying lines at, WRTERM macro 339
- output
  - determine if terminal is displaying 301
  - halting 217
  - restoring 218
- reading data from, RDTERM macro 332
- waiting for I/O to complete, WAITT macro 337

TEST option, of ASSEMBLE command 34

testing

- return codes from CMS commands, in an EXEC procedure 301
- variable symbols in an EXEC procedure 288

TEXT

- assembler output ddname 36
- files
  - automatic loading 126
  - cards read by the loader 127
  - creating with the assembler 34
  - executing, with the RUN command 168
  - link-editing in CMS/DOS 81,82
  - linking in storage 125
  - loading into virtual storage 125
  - resolving unresolved refernces with the LOAD command 126
  - libraries (see TXTLIB)
    - operand, of LINEDIT macro 318
  - TEXTA operand, of LINEDIT macro 319
- TIME, operand of &CONTROL control statement 283
- time information, displaying during EXEC processing 294
- time-of-day, displaying during EXEC processing 283
- timer, virtual interval 170

TO

- operand, of \$MOVE edit macro 262
- option, of GENMOD command 108

tokens 279

TOLABEL option, of COPYFILE command 44

TOP

- operand of &GOTO control statement 287
- subcommand, description 253

trace information, halting recording of 216

tracing

- resuming after temporarily halting 217
- suspending recording temporarily 218
- SVC instructions 182

trailing fill characters, removing from records 49

TRANS option, of COPYFILE command 45

transferring

- CMS files, using the DISK DUMP command 66
- control in an EXEC procedure
  - &GOTO control statement 287
  - &SKIP control statement 292

transient

- area
  - CMS commands that execute in 16
  - creating modules to execute in 110
  - loading programs into 125
  - directories in DOS/VS, displaying 84

translate

- tables
  - defining input characters for translation 171
  - defining output characters for translation 171
  - displaying 154

translating

- character representations
  - with the ALTER subcommand 220
  - with the COPYFILE command 50
- characters 50

lowercase letters to uppercase letters,  
with the PRINT command 144

translation list, for COPYFILE command,  
description 51

TRTCH option  
of ASSGN command 38  
of FILEDEF command 99  
of TAPE command 192

TRUNC  
option of COPYFILE command 45  
example 48  
subcommand, description 253

truncating  
commands 14  
input records with the editor, default  
settings 254  
records in a CMS file 45  
records in a file  
during GETFILE subcommand 233  
following a CHANGE subcommand 224  
tokens in an EXEC procedure 279  
trailing blanks from a CMS file 45

truncation  
column, for input mode 254  
settings used by the editor 254

truncations  
determine whether truncations are  
accepted for command names 153  
make command abbreviations acceptable as  
input 172  
make command abbreviations unacceptable  
as input 172

two-color ribbon, controlling use of  
154,172

TXTLIB  
command  
ADD operand 200  
DEL operand 200  
description 200  
GEN operand 200  
MAP operand 200

files  
adding members 200  
creating 200  
deleting members 200  
determining which TXTLIBs are  
searched 157  
identify for LOAD and INCLUDE command  
processing 111  
listing members in 200  
maximum number of members 201  
searched during INCLUDE command  
processing 113  
searched during LOAD command  
processing 125  
search for unresolved references 126  
operand, of GLOBAL command 111  
operand of CMS QUERY command 157

TXTLIB command  
DISK option 200  
PRINT option 200  
TERM option 200

TYPE  
command  
COL option 202  
description 202  
HEX option 202  
MEMBER option 203

function statement of DDR command 59  
operand, of &TIME control statement 294  
option  
of COPYFILE command 44  
of COPYFILE command (example) 48  
of ERASE command 88  
of INCLUDE command 114  
of LOAD command 126  
of RENAME command 164  
subcommand, description 254  
TYPE/PRINT output of DDR command 61  
typing, error messages in red 172

U  
U operand, of CASE subcommand 223  
UA operand  
of ASSGN command 38  
of LISTIO command 123

unassign  
logical units in CMS/DOS 38  
system and programmer logical units in  
CMS/DOS 173

undefined, symbols in an EXEC procedure,  
effect on &IF control statement 289

underscore  
character, on OVERLAY subcommand 240  
data records, using backspaces 235  
meaning in command format box 15

UNLOAD option, of DDR command INPUT/OUTPUT  
control statement 56

UNPACK option, of COPYFILE command 45

unpacking, CMS disk files 45

unresolved references  
during MODULE file generation 109  
loader handling of 128  
resolving with the INCLUDE command 114  
searching for TEXT files 126  
searching TXTLIBs for 126

UP  
operand, of \$MOVE edit macro 262  
subcommand, description 255

UPCASE option  
of ASSGN command 38  
of COPYFILE command 45  
of FILEDEF command 99  
of PRINT command 144

UPDATE  
command  
control statements 206  
CTL option 205,210  
description 204  
DISK option 205  
error handling for 213  
INC option 205  
input files 209  
multilevel updates, examples of 212  
NOCTL option 205  
NOINC option 205  
NOREP option 204  
NOSEQ8 option 205  
NOSTK option 205  
NOSTK option of 212  
NOTERM option 205  
output files 210  
PRINT option 205  
REP option 204



- SEQ8 option 204
- STK option 205,212
- STOR option 205
- TERM option 205
- warnings by 213
- control statements
  - comments 209
  - DELETE 208
  - INSERT 207
  - REPLACE 208
  - SEQUENCE 206
- filetype, default editor settings 343
- option of the TAPPDS command 198
- update log
  - for UPDATE command operations 205
  - generating at your terminal 205
- updating
  - CMS files, FSWRITE macro 313
  - master file directory 162
  - source files 204
- UPDIRT option, of RENAME command 164
- uppercase letters
  - converting to lowercase 45
  - meaning in command format boxes 15
  - suppress translation of lowercase letters with the editor 223
- UPSI
  - byte
    - query the setting of 158
    - setting 173
  - operand of CMS QUERY command 158
  - operand of CMS SET command 173
- UPTDxxxx filetype, default editor settings 343
- user catalog
  - identifying 77
    - in CMS/DOS 73
- user file directory 26
  - contents of 27
  - creating 26
  - writing on disk 162
- user-defined synonyms, displaying 156
- user-written commands
  - assigning synonyms for 186
  - creating 109

V

- valid
  - characters in CMS usage 14
  - CMS commands in CMS subset 226
  - virtual disk addresses 26
- variable data
  - in an EXEC procedure
    - displaying 295
    - punching 290
    - stacking 293
- variable symbols
  - assigning values to in EXEC procedures 278
  - reading from the terminal or console stack, in an EXEC procedure 291
  - substituting 278
- variable-length files
  - converting to fixed-length 48
  - using the RECFM subcommand 242
- VARS operand of &READ control statement 291
- verification setting, for the editor, changing 256
- VERIFY subcommand, description 256
- verifying
  - changes made by the editor 256
  - existence of a CMS file, FSSTATE macro 311
  - existence of a file 180
  - existence of CMS file, during program execution 308
- virtual disks (see also disks)
  - counting cylinders on 104
  - initializing 104
  - resetting the number of cylinders on 104
  - valid addresses for 26
- virtual machine
  - components of 11
  - console 11
  - definition 11
- virtual machine environment, determining the status of 152
- VM/370, basic description 11
- VSAM
  - catalogs
    - determining which catalog is searched 74
    - identifying 77
    - identifying in CMS/DOS 73
  - determining freespace extents 116
  - files
    - specifying disk extents 75
    - specifying disk extents in CMS/DOS 72
  - master catalog
    - identifying 77
    - identifying in CMS/DOS 73
  - option
    - of DLBL command 69
    - of the SET DOS ON command 173
  - restrictions
    - for DOS/VS users 345
    - for OS/VS users 347
- VSBASIC, filetype, default editor settings 343
- VSBASIC files, renumbering 243
- VSBDATA filetype, default editor settings 343

W

- wait, for terminal I/O to complete, WAITT macro 337
- WAITD macro
  - description 336
  - ERROR operand 336
  - used with HNDINT macro 315
- WAITT macro, description 337
- writing
  - CMS files
    - during program execution 312
    - sequentially 313
  - CMS files to disk 229
    - during an edit session 221,248
  - comments in VM/370 13

|                                      |     |                                            |                   |
|--------------------------------------|-----|--------------------------------------------|-------------------|
| labels on CMS disks                  | 104 |                                            |                   |
| nonreentrant code for LINEDIT macro  | 327 | 1                                          |                   |
| records on tape, WRTAPE macro        | 337 | 19E virtual disk address, accessed as      | Y-disk 27         |
| reentrant code for the LINEDIT macro | 326 | 190 virtual disk address, accessed as      | S-disk 27         |
| tape files to disk                   | 191 | 191 virtual disk address, accessed as      | A-disk 27         |
| WRTAPE macro                         |     | 192 virtual disk address, accessed as      | D-disk 27         |
| description                          | 337 | 195 virtual disk address, formatted by CMS | Batch Facility 40 |
| ERROR operand                        | 338 |                                            |                   |
| MODE operand                         | 337 |                                            |                   |
| WRTERM macro                         |     |                                            |                   |
| COLOR operand                        | 339 |                                            |                   |
| description                          | 339 |                                            |                   |
| EDIT operand                         | 339 |                                            |                   |
| WTM                                  |     | 3                                          |                   |
| option of TAPE command               | 192 | 3350, restriction on use in CMS/DOS        | 39                |
| tape control function                | 191 |                                            |                   |
|                                      |     |                                            |                   |
| X                                    |     | 4                                          |                   |
| X                                    |     | 48C, option, of OPTION command             | 142               |
| DEBUG subcommand                     | 275 |                                            |                   |
| EDIT subcommand                      |     |                                            |                   |
| description                          | 257 | 6                                          |                   |
| example                              | 257 | 60C, option, of OPTION command             | 142               |
| XREF option                          |     |                                            |                   |
| of ASSEMBLE command                  | 33  |                                            |                   |
| of OPTION command                    | 142 |                                            |                   |
| XTENT option, of FILEDEF command     | 98  | 7                                          |                   |
|                                      |     | 7TRACK option                              |                   |
|                                      |     | of ASSGN command                           | 38                |
|                                      |     | of FILEDEF command                         | 99                |
|                                      |     | of TAPE command                            | 192               |
|                                      |     | 7-track tapes, specifying on the TAPE      | command 192       |
|                                      |     |                                            |                   |
| Y                                    |     | 9                                          |                   |
| Y subcommand                         |     | 9TRACK option                              |                   |
| description                          | 257 | of ASSGN command                           | 38                |
| example                              | 257 | of FILEDEF command                         | 99                |
| Y-disk, accessed after IPLing CMS    | 27  | of the TAPE command                        | 192               |
| YFLAG option, of ASSEMBLE command    | 35  | 9-track tapes, specifying on the TAPE      | command 192       |
|                                      |     |                                            |                   |
| Z                                    |     |                                            |                   |
| zone settings, for an edit session   | 258 |                                            |                   |
| ZONE subcommand, description         | 258 |                                            |                   |

**READER'S COMMENTS**

**Title:** IBM Virtual Machine Facility/370:  
CMS Command and Macro Reference

**Order No.** GC20-1818-0

Please check or fill in the items; adding explanations/comments in the space provided.

Which of the following terms best describes your job?

- |                                            |                                        |                                               |                                                |
|--------------------------------------------|----------------------------------------|-----------------------------------------------|------------------------------------------------|
| <input type="checkbox"/> Customer Engineer | <input type="checkbox"/> Manager       | <input type="checkbox"/> Programmer           | <input type="checkbox"/> Systems Analyst       |
| <input type="checkbox"/> Engineer          | <input type="checkbox"/> Mathematician | <input type="checkbox"/> Sales Representative | <input type="checkbox"/> Systems Engineer      |
| <input type="checkbox"/> Instructor        | <input type="checkbox"/> Operator      | <input type="checkbox"/> Student/Trainee      | <input type="checkbox"/> Other (explain below) |

How did you use this publication?

- |                                            |                                           |                                   |                                          |
|--------------------------------------------|-------------------------------------------|-----------------------------------|------------------------------------------|
| <input type="checkbox"/> Introductory text | <input type="checkbox"/> Reference manual | <input type="checkbox"/> Student/ | <input type="checkbox"/> Instructor text |
| <input type="checkbox"/> Other (explain)   | _____                                     |                                   |                                          |

Did you find the material easy to read and understand?     Yes     No (explain below)

Did you find the material organized for convenient use?     Yes     No (explain below)

Specific criticisms (explain below)

- Clarifications on pages \_\_\_\_\_
- Additions on pages \_\_\_\_\_
- Deletions on pages \_\_\_\_\_
- Errors on pages \_\_\_\_\_

Explanations and other comments:

Trim Along This Line

YOUR COMMENTS PLEASE . . .

Your views about this publication may help improve its usefulness; this form will be sent to the author's department for appropriate action. Using this form to request system assistance and/or additional publications or to suggest programming changes will delay response, however. For more direct handling of such requests, please contact your IBM representative or the IBM Branch Office serving your locality. Your comments will be carefully reviewed by the person or persons responsible for writing and publishing this material. All comments or suggestions become the property of IBM.

FOLD

FOLD


FIRST CLASS  
PERMIT NO. 172  
BURLINGTON, MASS.

**BUSINESS REPLY MAIL**

NO POSTAGE STAMP NECESSARY IF MAILED IN U.S.A.

POSTAGE WILL BE PAID BY

**IBM CORPORATION  
VM/370 PUBLICATIONS  
24 NEW ENGLAND EXECUTIVE PARK  
BURLINGTON, MASS. 01803**



FOLD

FOLD



**International Business Machines Corporation  
Data Processing Division  
1133 Westchester Avenue, White Plains, New York 10604  
(U.S.A. only)**

**IBM World Trade Corporation  
821 United Nations Plaza, New York, New York 10017  
(International)**

Trim Along This Line

IBM VM/370: CMS Command

Macro Reference

Printed in U.S.A.

GC20-1818-0