

# OPAL On-line Presentation Access Library

May 1993

**digital**<sup>TM</sup>

# OPAL ISO 9660 CD-ROM

# Operating Instructions for OpenVMS for F11CD Installation

In order to use the OPAL ISO 9660 CD-ROM on an OpenVMS VAX system, the operating system must be running VMS 5.5 or greater and the F11CD software. The F11CD kit is also on the OPAL CD-ROM.

To install F11CD software on an OpenVMS VAX System verify that the CD-ROM Drive is on-line. Place the OPAL CD-ROM into the drive and enter the following commands at the DCL prompt:

- \$ MOUNT <CD-ROM-device-name:> OPALCDKIT <RET>  
(i.e. \$ MOUNT \$42\$DUC0: OPALCDKIT <RET>)  
(if the CD-ROM device logical is \$42\$DUC0:)

Follow the instructions in the file F11CD\_BOOKLET.TXT located in the directory <CD-ROM-device-name:>[F11CD055.LINE\_DOCS] to install the F11CD software on an OpenVMS VAX System

- Note: The F11CD saveset is contained on the CD-ROM in the directory <CD-ROM-device-name:>[F11CD055.KIT]

For further information regarding the F11CD055 software refer to F11CD055.RELEASE\_NOTES in [F11CD055.LINE\_DOCS]

## To Exit the System

After the installation enter the following commands:

- \$ DISMOUNT <CD-ROM-device-name> <RET>  
(i.e. \$ DISMOUNT \$42\$DUC0: <RET>)

# Executing the OPALMENU Interface

Once the F11CD software is loaded on the OpenVMS system, verify that the CD-ROM Drive is on-line. Place the OPAL CD-ROM into the drive and enter the following commands at the DCL prompt:

- \$ SET PROCESS/PRIVILEGES = VOLPRO <RET>
- \$ CD\_MOUNT /MEDIA=CDROM /UNDEFINED\_FAT=(STREAM:2048) -  
<CD-ROM-device-name:> OPAL <RET>  
i.e. \$ CD\_MOUNT /MEDIA=CDROM /UNDEFINED\_FAT=(STREAM:2048) -  
\$42\$DUC0: OPAL <RET>
- \$ @ <CD-ROM-device-name:>[CDMENU]OPALSTART <RET>  
(i.e. \$ @ \$42\$DUC0:[CDMENU]OPALSTART <RET>)

## To Exit the System

After the installation enter the following commands:

- \$ CD\_DISMOUNT <CD-ROM-device-name> <RET>  
(i.e. \$ CD\_DISMOUNT \$42\$DUC0: <RET>)

## CAUTION:

You need VOLPRO privileges to operate this CD-ROM!!  
If you mount the CD-ROM without VOLPRO PRIVILEGE by issuing CD\_MOUNT and the CD-ROM mounts, dismount the CD-ROM using the regular 'DISMOUNT' command!

# Operating Instructions for DOS

Before mounting the CD-ROM on a PC, Verify that the device-drivers for the CD\_ROM drive are loaded via CONFIG.SYS  
Then verify MSCDEX.EXE has been started, usually in AUTOEXEC.BAT.

Once verifications are complete, place the OPAL CD-ROM into the drive and enter the following commands at the DOS prompt:

- C:\> J: <RET>  
(J: = the CD-reader drive verified above.)
- J:\> CD OPALCDPC <RET>
- J:\OPALCDPC> OPALCD <RET>

# Operating Instructions for MS Windows

- Bring up Windows
- Choose the 'Run' option from the Program Managers 'File' menu.
- On the Command line box type J:\OPALCDPC\OPALCD  
(J: = the CD-reader drive verified above.)
- Click on the OK Button.