

CUSTOMER SERVICE BULLETIN

Radio Shack® CUSTOMER SERVICE BULLETIN

400 Atrium—One Tandy Center, Fort Worth, Texas 76102

Bulletin No.	1705-4
Description	Advanced Stat Analysis
Model	Model I/III
Stock No.	26-1705 Version 1.0
Date	June 23, 1980
Page 1 of	1

Problem

In the Analysis of Variance with two groups, evidently the counter for group two does not count correctly. This occurs on Updates involving two groups in the Analysis of Variance.

Solution

The problem is corrected by following the steps listed below.

1. CLOAD the Tape Data Files tape.
2. Make the following corrections:

CHANGES (Retype the line or refer to the Edit section of the owners manual)

Old Line: 1060 GOSUB6000:JJ=0:FORJ=1TO8:JJ=JJ+1:IFZ(J)="@N(K)=M+JJ-1:JL=J:
GOSUB7000:JJ=0:K=K+1

New Line: 1060 GOSUB6000:JJ=0:FORJ=1TO8:JJ=JJ+1:IFZ(J)="@N(K)=M+JJ-1:JL=J:
GOSUB7000:JJ=0:K=K+1:IFMT=3M=M-JL

Old Line: 10090 KL=1:FORK=1TONT:IFZI="Y"LPRINT"ELEMENT #";K,"GROUP
#";KL,ZD(K)

New Line: 10090 E=0:KL=1:FORK=1TONT:E=E+1:IFZD(K)="@THENKL=KL+1:E=E-1:
GOTO10100:ELSEIFZI="Y"LPRINT"ELEMENT #";E,"GROUP #";KL,ZD(K)

Old Line: 10095 PRINT"ELEMENT #";K,"GROUP #";KL,ZD(K):GOSUB9900:
IFZD(K)="@KL=KL+1

New Line: 10095 PRINT"ELEMENT #";E,"GROUP #";KL,ZD(K):GOSUB9900

LINES THAT SHOULD BE DELETED (Type the line number followed by an <ENTER>)

1090

3. Insert a new blank tape into the recorder and type CSAVE"A" to save the changes in the program.